# Windows Remote Desktop (RDP) Setup

Document Author: arho.virkki@vtt.fi

Xrdp is an Open Source Remote desktop Protocol server, which allows you to RDP to your Linux server from Windows machine with the Windows native remote desktop program.

#### **Install RDP to CentOS 7**

This is possible with additional repositories (not only EPEL): For details, see: http://www.itzgeek.com/how-tos/linux/centos-how-tos/install-xrdp-on-centos-7-rhel-7.html.

## **Install RDP to Ubuntu Desktop**

### First, install xrdb

```
sudo apt-get install xrdp
```

#### And check its status

sudo service xrdp status

## Then add some extra packages

```
sudo apt-get install gnome-panel metacity
```

#### Edit the ~/.xsession file as follows

```
[ -x /etc/vnc/xstartup ] && exec /etc/vnc/xstartup
[ -r $HOME/.Xresources ] && xrdb $HOME/.Xresources
xsetroot -solid darkgrey
metacity &
unity-settings-daemon &
gnome-panel &
gnome-terminal
```

The background color can be changed with the *xsetroot -solid <colorname*> command on the terminal, and set permanently by editing the above config. The colors names are same than in CSS, see e.g. http://davidbau.com/colors/.

Due to the missing 3D support, some features of Gnome cannot be used. For example, *unity-control-center* does not launch. Nonetheless, we can change the Desktop theme from command line.

To switch from the default dark (Ambiance) theme to the optional light (Radiance) theme in Terminal, issue

```
gsettings set org.gnome.desktop.interface gtk-theme Radiance
gsettings set org.gnome.desktop.wm.preferences theme Radiance
```

# And to restore the default

```
gsettings set org.gnome.desktop.interface gtk-theme Ambiance
gsettings set org.gnome.desktop.wm.preferences theme Ambiance
```

Reference: http://c-nergy.be/blog/?p=5305

2018-01-18 Subtopic Page 1/1