SLEM CV on PlayStation - step by step

discord.gg/slem

What this is

A PC program. It watches your PS5 on the PC screen, reads the shot meter, and lets go of Square for you at the right moment. Nothing is installed on the PS5.

It does NOT use Sony's PS Remote Play app. It uses chiaki-ng, a free app that shows your PS5 on the PC the same way.

Do the steps in order. One step at a time. Do not skip.

PART 1 - Install 3 programs (only once)

Step 1. Install ViGEmBus. Go to github.com/nefarius/ViGEmBus/releases, download the newest .exe, run it, Next, Next, Finish.

Step 2. Install HidHide 1.5.230. Go to github.com/nefarius/HidHide/releases, download HidHide_1.5.230_x64.exe, run it. Your PC will restart. That is normal. After the restart, do NOT open HidHide and do not change anything in it. SLEM controls it.

Step 3. Install chiaki-ng v1.10.0. Go to github.com/streetpea/chiaki-ng/releases/tag/v1.10.0, download chiaki-ng-win_x64-MSYS2-Release-installer.exe.zip, unzip it, run the installer. It must be exactly 1.10.0. Newer test builds are slower.

Step 4. If you have DS4Windows or DSX on the PC: uninstall them. They break this.

Step 5. No Cronus Zen and no Titan Two anywhere in the chain. The DualSense goes straight into the PC. With a Zen in between, SLEM never gets to see the real controller and nothing is timed. Setup refuses to continue while one is plugged in.

PART 2 - PS5, PC and game (only once)

Step 6. PS5: Settings > System > Remote Play > Enable Remote Play = ON.

Step 7. One Ethernet cable per device: one cable from the router to the PS5, one cable from the router to the PC. The PC does not need two cables. No Ethernet port on the PC? A USB-to-Ethernet adapter (10 to 15 dollars) works. Wi-Fi anywhere = late shots.

Step 8. Windows display: 1920x1080, 60 Hz, HDR off (Settings > System > Display). HDR off looks duller on the screen. That is normal and it is not lower quality: the meter is found by its colours and HDR shifts them, so keep it off. A 4:3, 16:10 or ultrawide desktop does not work: SLEM refuses to go live and says the picture size it sees.

Step 9. In 2K, Settings > Controller Settings:

Setting	Set it to
Shot meter	ON
Shot meter type	Arrow 2
Shot meter size	Large

Shot meter position	To the side of the player
Shot feedback	Timing ON

PART 3 - chiaki-ng (only once)

Step 10. Open chiaki-ng. Your PS5 appears. Click it > Register. Log in with your PSN account. It asks for a PIN: on the PS5 go to Settings > System > Remote Play > Link Device, the PIN is on the screen. Type it in.

Step 11. Start the stream once without SLEM. Play one minute with your DualSense. Works? Good. Close chiaki-ng.

Step 12. chiaki-ng settings. SLEM's setup sets them for you in Part 4 (button Apply recommended). If you ever set them by hand, the two that matter are: chiaki-ng: Settings > Window type = Fullscreen, Resolution 1080p. A maximised window is NOT Fullscreen: it has a title bar, and SLEM keeps telling you to put chiaki-ng on Fullscreen until that setting is changed.

PART 4 - SLEM, first time

Step 13. Unzip the SLEM folder anywhere (Desktop is fine). Open the folder, double-click SLEM Scripts.exe.
Windows says "protected your PC"? Click More info > Run anyway.

Step 14. Press Log in with Discord. Your browser opens Discord, press Authorize, then This is my PC. The page shows a 6-letter code; the app shows the same code. Back in the app your name is in the top bar.

Step 15. Top right: press the console button and pick PlayStation.

Step 16. The Setup window opens. Go through every step, top to bottom. Each one checks something and turns green. If one is red, it tells you what to fix. In the chiaki-ng step press Apply recommended. In the controller step plug the DualSense in by USB and press the probe.

HidHide step red with "untick Inverse application cloak"? Another program set HidHide up its own way. Open HidHide Configuration Client > Applications, untick Inverse application cloak, press Check again. The detail lists any other programs on HidHide's list: they still see the hidden controller, remove them if you do not need them.

Step 17. At the end it says Setup done. Now Start is unlocked.

PART 5 - Every time you play (the order matters)

Step 18. Close Steam (bottom right tray icon > Exit). Close DS4Windows, DSX, Sony Remote Play if any of them is open. SLEM will not start while they run. Close chiaki-ng too if it is still open from last time.

Step 19. DualSense plugged in by USB.

Step 20. Open SLEM Scripts. Check it says PlayStation mode top right. Press Start.
The log must say: real pad on SDL: DualSense and controller hidden from other apps.

Step 21. Now open chiaki-ng and start the stream. In chiaki-ng Settings > Controllers there must be only "Xbox 360 controller". If your DualSense is in that list too: press Stop in SLEM, close chiaki-ng, do Step

20 and 21 again.

Step 22. The red chip replug the controller. If SLEM shows it (log: "controller: unplug it and plug it back in (chiaki-ng still holds it)"), chiaki-ng grabbed the DualSense before SLEM hid it and keeps it. SLEM does not go live until you do this: pull the USB cable out, wait two seconds, plug it back in. On Bluetooth: hold the PS button 10 seconds (off), then press it again. The log says "controller: back, hidden from chiaki-ng" and the chip turns to LIVE. Without this every shot is late: the game keeps seeing your own hand on Square and SLEM's release never reaches it.

Step 23. SLEM's window minimises itself the moment it goes live and comes back on Stop. That is normal: a window on top of the stream would block the picture. Do not bring it back over the game while you play.

Step 24. Play. Hold Square and keep holding it. SLEM lets go for you. Do not tap, do not let go on your own: if the panel says "you let go first: N of last 10", you released before SLEM did and those shots were on your timing, not SLEM's. Everything else works like normal.

Step 25. Happy with the timing? Press Lock aims next to the aims. The badge reads LOCKED, learning stops, and the set / fade numbers become boxes you can type into (Enter applies, 80 to 400 ms). The lock is saved per book (Park, Theater and MyCOURT, offline and online are separate books) and survives a restart. Press it again to let SLEM learn again.

Step 26. Done playing: press Stop in SLEM. That gives your DualSense back to Windows.

If something is wrong

What you see	What to do
Red chip replug the controller	Step 22: cable out, two seconds, cable in (Bluetooth: PS button 10 s off, then on). Not live until you do
"the game still sees your controller: unplug and replug it" while playing	Three fired shots in a row were not seen by the game. Same as Step 22: cable out and in. Learning pauses until the next shot the game accepts
Red controller unplugged: plug it back in	The USB dropped or you pulled it. Plug it in, SLEM says "controller back" and carries on
Every shot late while you hold Square	Step 22. If it keeps happening: a Zen or Titan in the chain (Step 5), or chiaki-ng was open before SLEM (Step 18)
"you let go first: N of last 10"	You are releasing before SLEM does. Hold the button, SLEM lets go for you
"aim moved 20 ms this run: press Reset aims if shots feel off"	Learning moved the aim as far as it may in one run. If shots feel wrong press Reset aims, or Lock aims at a value you trust
"picture: Windows must be 1920x1080 and chiaki-ng Fullscreen 1080p (picture is ...)"	Step 8 and Step 12. The desktop is not 16:9, or chiaki-ng is windowed, maximised or on 720p
"chiaki-ng: Settings > Window type = Fullscreen, Resolution 1080p"	Exactly that setting in chiaki-ng. Maximised is not Fullscreen
Stream health yellow although both are on cable	The stream skips pictures; check the PS5 cable and that chiaki-ng is on 1080p 60 fps. Yellow still lets you play
SLEM refuses to start	One of the programs from Step 18 is still open. Check the tray icons bottom right
DualSense does nothing in other games after chiaki-ng shows your DualSense in Controllers	Open SLEM Scripts once and close it. That un-hides it Stop SLEM, close chiaki-ng, Step 20, then 21. SLEM must start BEFORE chiaki-ng
Setup says a Cronus Zen / Titan Two is in the chain	Unplug it. The DualSense goes straight into the PC (Step 5)

To switch USB <-> Bluetooth: Stop in SLEM, switch, Start again.

Problems

- This is a test release. It can be inconsistent or not work on your setup. Do not open a ticket for it.
- Post in #cv-feedback what happened, and press Send issue in the app: it sends the log to us by itself. Write one line about what you saw; an empty report is filled with the last status line.