#### Developer

- / Documentation
- / Unreal Engine ∨
- / Unreal Engine 5.4 Documentation
- / Designing Visuals, Rendering, and Graphics
- / Optimizing and Debugging Projects for Real-Time Rendering
- / Using RenderDoc with Unreal Engine

# **Using RenderDoc with Unreal Engine**

RenderDoc is a standalone open-source graphics debugger that you can use to perform single-frame captures and inspect them.



RenderDoc is a free standalone open-source graphics debugger that you can use to perform single-frame captures of an application, such as Unreal Engine. The capture is loaded into RenderDoc to inspect what is happening on the GPU through the events, API, and much more, in full detail.

## **Install RenderDoc**

RenderDoc is an open-source graphics debugger that is free, and available to download and install from <a href="RenderDoc.org">RenderDoc.org</a>.



The list of supported operating systems and APIs below reflect what RenderDoc currently supports, which may differ from what Unreal Engine supports. For the latest updates, see RenderDoc's FAQ page.

RenderDoc supports the following Operating Systems:

Windows 7, 10, and 11

- Linux
- Android
- Nintendo Switch


RenderDoc supports the following APIs:

- Vulkan
- D3D11
- D3D12
- OpenGL 3.2+
- OpenGL ES 2.0 3.2

## **Enable RenderDoc in Your Project**

The **RenderDoc** plugin is included with the engine and enabled by default. There are two ways you can run RenderDoc with your project: by command line argument, or a project setting.


When RenderDoc attaches on startup, you'll see the RenderDoc icon in the upper-right corner of the Level Viewport.



Follow the steps below to see how each is enabled.


## **Enabling with Plugin Project Settings**

In the Project Settings in **Plugins > RenderDoc** under **Advanced Settings**, enable **Auto attach on startup**. This method is ideal when you want to run RenderDoc on startup anytime the project loads.



## **Enabling with Command Line**

Enable command line arguments using an editor shortcut. In the **Shortcut** tab, add the following to the **Target** line: —AttachRenderDoc. This method is ideal when you only want to run RenderDoc some of the time.



## **Performing a Frame Capture**

The steps below describe at a high level how to perform a single-frame capture with your Unreal Engine project using the integrated RenderDoc plugin or directly from RenderDoc application.


Further details on functionality and use of RenderDoc can be found in RenderDoc Documentation.

## **RenderDoc Plugin**

The following steps are used to capture a frame using Unreal Engine's RenderDoc Plugin:

- 1. Enable the RenderDoc plugin for your project.
- 2. Open your project and scene where you want to perform a capture.

3. Click the **RenderDoc Capture** button in the Level Viewport.



Click image for full size.


## **RenderDoc Application**

The following are the high-level steps required to capture a frame using Unreal Engine with the standalone RenderDoc executable:

- 1. Configure RenderDoc to launch your game or the UEEditor.exe with the appropriate command line arguments.
  - i Enable Capture Child Processes when launching with the UEEditor.exe.
- 2. Launch the executable.
- 3. Press the **F12** hotkey to perform a frame capture.
  - For full details on setting up RenderDoc, launching an application and performing a frame capture, see the RenderDoc Getting Started Guide.

# **Project Settings**

Use the Project Settings window to set additional RenderDoc Plugin settings. From the main menu, select **Edit** > **Project Settings** and then under the **Plugins** category, select **RenderDoc**.



Property Description

Property	Description
Frame Capture Settings	
Capture all activity	When enabled, RenderDoc captures all activity in all viewports and Editor windows for the entire frame instead of only the current viewport.
Capture all call stacks	When enabled, RenderDoc captures call stacks for all API calls.
Reference all resources	When enabled, RenderDoc includes all rendering resources in the capture, even those that have not been used during the frame.  ! Enabling this property will significantly increase capture size.
Save all initial states	When enabled, RenderDoc always captures the initial state of all rendering resources, even if they are not likely to be

used during the frame.

0

Property	Description
	Enabling this property will significantly increase capture size.
Advanced Settings	
Show help on startup	When enabled, a help window with RenderDoc is shown on Editor startup.
Use the RenderDoc crash handler	If enabled, the RenderDoc crash handler is used if a crash occurs.  This should only be used if you know the problem is with the RenderDoc application and would like to notify the RenderDoc developers.
RenderDoc executable path	Sets the path to the RenderDoc executable to use.  This should automatically fill in when with the correct path when RenderDoc is installed.

## **Additional Notes and Resources**

- See <u>RenderDoc Documentation</u> for further reading on RenderDoc use and analysis of frame captures.
- The RenderDoc Plugin was created and developed by Fredrik Lindh ("Temaran") for Unreal Engine. For additional information, see the RenderDoc <u>GitHub respository</u>.