VYSOKÉ UČENÍ TECHNICKÉ V BRNĚ

Fakulta informačních technologií

ISS – SIGNÁLY A SYSTÉMY

Projekt

(A.R. 2022/2023)

Autor: Kukhta Myron (xkukht01) Brno, 18.12.2022

OBSAH

- 1. Základy
- 2. Určení základní frekvence
- 3. Zpřesnění odhadu základní frekvence
- 4. Syntéza tónů

1. Základy

UPOZORNĚNÍ: 1) svuj kod budu odělovat od texta protokolu szmbolem ">>"; 2) kod v pythonnotebook může dlouho vypracovovat vysledky kvuli osobnostem jazyku Python.

Pro návrh projektu od začatku vybral Python, prosředi JupyterNotebook. Pro načtení signal použil kod už napsani a přiložení v popisu projektu.

Dál zobrazil 3 perioda mych tonu (měl tony 34, 63, 105). Spočital period pro každy ton, přes frekvence, který my už měli v souboru.

```
T = 1/F (T - period[s], F - frekvence[Hz])
```

V kodu vypada takhle:

```
>> period34 = 1/58.27
>> period63 = 1/311.13
>> period105 = 1/3520.00
```

Dal té hodnoty plotnul(př. Pro ton 34):

```
>>plt.figure(figsize=(10, 5))
>>plt.plot(np.arange(xall[34].size)/Fs, xall[34])
>>plt.xlim(0, period34*3)
```

Ve grafu uložil na OX v čas v secundech(dostal přes počet vzorku tona dělení Fs) a ohraničel v rozsahu 3 periodu; na OY uložil amplitudu hodnot tonu.

Dál spočital DFT celého 0.5 s dlouhého úseku a vzýkreslil ho (pro každý ton).

Spočital module DFT tonu přes funkce np.fft.fft(), udělal vypočet frekvence přes dělení pulky modulu DFT(DFT pracuje jenom na půlce Fs, že od 0 do 24 kHz) počtem vzorku a nasobením vzorkovaci frekvence.


```
>>moduleDFT34 = np.abs(np.fft.fft(xall[34]))
>>F34 = np.arange(moduleDFT34[:moduleDFT34.size//2].size)*(Fs/xall[34].size)
```


Zatím plotnul v graf hodnoty DFT. OX: frekvenc; OY: log PSD plus moc mala hodnota pro spřesnění (PSD – Power Spectral Density = pulka modula DFT ** 2 + mala konstanta)


```
>>plt.plot(F34, np.log((moduleDFT34[:moduleDFT34.size//2])**2 + 10**(-5)))
```


Na konce sve tony uložil jako audio přes funkce sf.write(), kde argumentamz byly jmeno audio, data audio a vzorkovaci frekvnece:


```
>>sf.write("audio/a orig.wav", xall[34], Fs)
```














2 Určení základní frekvence

Pro spočitaní základní frekvence (f0) jsem použil spolu dva metoda: přes DFT a autokorelace. Proč potřeboval oba? Ják víme z teorii a budeme vídět to na hodnotach mého vysledku, pro tony z nížší frekvence lepší použít autokorelace, protože DFT bude tám selhavat, opačně bude pracovat z tony vyšší frekvence. Za spravní hodnoty na který orientoval se bylá frekvence z souboru.

1. zakladní frekvence přes DFT:

Jsem vytvořil funkce my_find_peaks(), ktéra přijála index tonu(od 24 do 108), vypočitala DFT pro ten ton, a prochazela po nemu cyklem, snaží se najít největší peak(největší hodnotu po log(PSD), hodnota po OY) a když nachazelá, vratí odpovidající frekvence(hodnota na ose OX), a její index v DFT(pro další lehší kreslení peaku)). Smysl v tom, je-li my pracujeme přes DFT, zakladnou frekvencí budou frekvencí největšího peaku ve DFT.

```
>>def my find peaks(number ton): #found fundamental frequency by DFT
>>
>>
      oy = -1000 # the highest peak
>>
      index = 0 # his index
>>
>>
      moduleDFTactual = np.abs(np.fft.fft(xall[number ton])) #the module of the actual
DFT ton
>>
      FActual=np.arange(moduleDFTactual[:moduleDFTactual.size//2].size)*(Fs/xall[number t
on].size)
>>
      for i in range(0, FActual.size):
>>
>>
             if (np.log((moduleDFTactual[i])**2 + 10**(-5)) > oy):
                    oy = np.log((moduleDFTactual[i])**2 + 10**(-5))
                    index = i
>>
      return FActual[index], index #fundamental frequency, index of fundamental frequency
>>
```

Pak vypočital základní frekvence pro každý ton, ulozil do array_fr_by_DFT, jejich indexy do array_index_fr_by_DFT a vypsal.

```
Fundamental frequency by DFT fundamental frequency of 24 ton: 66.0 fundamental frequency of 25 ton: 70.0 fundamental frequency of 26 ton: 74.0 fundamental frequency of 27 ton: 78.0 fundamental frequency of 28 ton: 82.0 fundamental frequency of 29 ton: 88.0 fundamental frequency of 30 ton: 92.0
```

```
fundamental frequency of 31 ton: 98.0
fundamental frequency of 32 ton: 104.0
fundamental frequency of 33 ton: 110.0
fundamental frequency of 34 ton : 116.0
fundamental frequency of 35 ton: 124.0
fundamental frequency of 36 ton: 130.0
fundamental frequency of 37 ton: 138.0
fundamental frequency of 38 ton: 220.0
fundamental frequency of 39 ton: 234.0
fundamental frequency of 40 ton : 248.0
fundamental frequency of 41 ton: 88.0
fundamental frequency of 42 ton : 92.0
fundamental frequency of 43 ton: 98.0
fundamental frequency of 44 ton : 104.0
fundamental frequency of 45 ton: 110.0
fundamental frequency of 46 ton : 118.0
fundamental frequency of 47 ton : 124.0
fundamental frequency of 48 ton: 130.0
fundamental frequency of 49 ton: 138.0
fundamental frequency of 50 ton : 146.0
fundamental frequency of 51 ton: 156.0
fundamental frequency of 52 ton: 164.0
fundamental frequency of 53 ton: 350.0
fundamental frequency of 54 ton: 370.0
fundamental frequency of 55 ton: 392.0
fundamental frequency of 56 ton : 208.0
fundamental frequency of 57 ton: 220.0
fundamental frequency of 58 ton: 234.0
fundamental frequency of 59 ton : 248.0
fundamental frequency of 60 ton : 262.0
fundamental frequency of 61 ton : 278.0
fundamental frequency of 62 ton: 294.0
fundamental frequency of 63 ton: 312.0
fundamental frequency of 64 ton: 330.0
fundamental frequency of 65 ton: 350.0
fundamental frequency of 66 ton: 370.0
fundamental frequency of 67 ton : 392.0
fundamental frequency of 68 ton: 416.0
fundamental frequency of 69 ton: 440.0
fundamental frequency of 70 ton: 466.0
fundamental frequency of 71 ton: 494.0
fundamental frequency of 72 ton : 524.0
fundamental frequency of 73 ton: 554.0
fundamental frequency of 74 ton: 588.0
fundamental frequency of 75 ton: 622.0
fundamental frequency of 76 ton: 660.0
fundamental frequency of 77 ton: 698.0
fundamental frequency of 78 ton: 740.0
fundamental frequency of 79 ton: 784.0
fundamental frequency of 80 ton: 830.0
fundamental frequency of 81 ton: 882.0
fundamental frequency of 82 ton: 932.0
fundamental frequency of 83 ton : 988.0
fundamental frequency of 84 ton : 1046.0
fundamental frequency of 85 ton: 1108.0
fundamental frequency of 86 ton: 1174.0
fundamental frequency of 87 ton : 1244.0
```

```
fundamental frequency of 88 ton: 1318.0
fundamental frequency of 89 ton: 1396.0
fundamental frequency of 90 ton: 1478.0
fundamental frequency of 91 ton: 1566.0
fundamental frequency of 92 ton: 1660.0
fundamental frequency of 93 ton: 1758.0
fundamental frequency of 94 ton: 1864.0
fundamental frequency of 95 ton : 1976.0
fundamental frequency of 96 ton: 2094.0
fundamental frequency of 97 ton: 2218.0
fundamental frequency of 98 ton: 2350.0
fundamental frequency of 99 ton: 2490.0
fundamental frequency of 100 ton: 2638.0
fundamental frequency of 101 ton: 2796.0
fundamental frequency of 102 ton: 2962.0
fundamental frequency of 103 ton: 3138.0
fundamental frequency of 104 ton: 3324.0
fundamental frequency of 105 ton: 3522.0
fundamental frequency of 106 ton: 3732.0
fundamental frequency of 107 ton: 3954.0
fundamental frequency of 108 ton: 4188.0
```

Poravnaváme hodnoty s hodnotamy z souboru a vídíme, jak stejně jako jsem předpokladal, máme selhaní v tonéch z nížší frekvence. Po druhé hodnoty ne taký přesný jak bych chtěli. Můžeme to řešít vypočtem přes autokorelace.

2. základní frekvence přes autokorelace:

Jsem vytvořil funkce <code>autocorrelation()</code> ktéra spočitala autokorelace, a přes nejí nachazela základní frekvence. Ona příjma index tonu, vypočitala koralace přes funkce <code>np.correlate()</code> (uděla posun pro OX a vynasobila muj ton sama na sebe) a uložila vyslední hodnoty do <code>correlate_ton</code>. Pak jsem rozdělil ten <code>correlate_ton</code> na pul, protože víme že autocorelace uděla symetricky signal, pro naše pohodlí můžeme to skrátit. Dál nejdůležítější čast, nášou zakladní frekvence my najdeme přes vzdalenost mezí dvéma největší peaky, tohle bude hodnota <code>N</code> (vzorky), nachazíme jí, přes funkce <code>max()</code>, <code>min()</code>, porovnavání hodnot atd. Dál přes formulu můžeme najit základní frekvence.

```
F = (1/N)*Fs \quad (F - základní \ frekvence[Hz], \ N - vzorky, \ Fs - vzorkovací \ frekvece)
```

Kod:

```
>>
      index max peak col = index max peak col[0][0]
>>
      min peak col = min(correlate tonHalf)
>>
>>
      index min peak col = np.where(correlate tonHalf == min peak col)
      index_min_peak_col = index_min_peak_col[0][0]
>>
>>
>>
      second max peak col = max(correlate tonHalf[index min peak col+1:])
>>
      second index max peak col = np.where(correlate tonHalf == second max peak col)
>>
      second index max peak col = second_index_max_peak_col[0][0]
>>
      fundamental frequency = ((1/second index max peak col)*Fs)
>>
>>
      return fundamental frequency
```


Vypíšu vysledek, abych uvídět roudil mezí hodnotamy frekvence přes autokorelace, DFT a hodnotamy z souboriu.


Fundamental frequency by autocorrelation

```
fundamental frequency of 24 ton : 32.80929596719071
fundamental frequency of 25 ton : 34.757422157856624
fundamental frequency of 26 ton : 36.83806600153492
fundamental frequency of 27 ton: 39.02439024390244
fundamental frequency of 28 ton : 41.343669250645995
fundamental frequency of 29 ton: 43.7956204379562
fundamental frequency of 30 ton : 46.42166344294004
fundamental frequency of 31 ton: 49.18032786885246
fundamental frequency of 32 ton : 52.11726384364821
fundamental frequency of 33 ton : 55.172413793103445
fundamental frequency of 34 ton : 58.465286236297196
fundamental frequency of 35 ton : 61.935483870967744
fundamental frequency of 36 ton: 65.57377049180327
fundamental frequency of 37 ton: 69.46454413892909
fundamental frequency of 38 ton: 73.61963190184049
fundamental frequency of 39 ton : 77.92207792207793
fundamental frequency of 40 ton: 82.61617900172118
fundamental frequency of 41 ton: 87.75137111517367
fundamental frequency of 42 ton: 92.84332688588007
fundamental frequency of 43 ton: 98.36065573770492
fundamental frequency of 44 ton : 104.34782608695652
fundamental frequency of 45 ton : 110.59907834101382
fundamental frequency of 46 ton: 117.07317073170732
fundamental frequency of 47 ton : 123.71134020618557
fundamental frequency of 48 ton : 131.14754098360655
fundamental frequency of 49 ton : 138.72832369942196
fundamental frequency of 50 ton : 147.23926380368098
fundamental frequency of 51 ton : 155.84415584415586
fundamental frequency of 52 ton : 164.94845360824743
fundamental frequency of 53 ton: 175.1824817518248
fundamental frequency of 54 ton : 185.32818532818533
```


```
fundamental frequency of 55 ton : 196.72131147540983
fundamental frequency of 56 ton: 207.7922077922078
fundamental frequency of 57 ton: 220.1834862385321
fundamental frequency of 58 ton: 77.79578606158833
fundamental frequency of 59 ton: 35.34609720176731
fundamental frequency of 60 ton : 32.76450511945392
fundamental frequency of 61 ton: 34.70715835140998
fundamental frequency of 62 ton : 294.47852760736197
fundamental frequency of 63 ton: 311.6883116883117
fundamental frequency of 64 ton : 328.7671232876712
fundamental frequency of 65 ton: 350.3649635036496
fundamental frequency of 66 ton: 369.2307692307692
fundamental frequency of 67 ton : 393.44262295081967
fundamental frequency of 68 ton : 417.39130434782606
fundamental frequency of 69 ton: 440.3669724770642
fundamental frequency of 70 ton : 466.0194174757281
fundamental frequency of 71 ton: 494.8453608247423
fundamental frequency of 72 ton : 521.7391304347826
fundamental frequency of 73 ton: 551.7241379310344
fundamental frequency of 74 ton : 585.3658536585366
fundamental frequency of 75 ton : 623.3766233766235
fundamental frequency of 76 ton : 657.5342465753424
fundamental frequency of 77 ton: 350.3649635036496
fundamental frequency of 78 ton : 247.42268041237114
fundamental frequency of 79 ton : 156.86274509803923
fundamental frequency of 80 ton: 827.5862068965517
fundamental frequency of 82 ton: 941.1764705882352
fundamental frequency of 83 ton : 109.83981693363845
fundamental frequency of 84 ton : 116.50485436893203
fundamental frequency of 85 ton: 123.39331619537275
fundamental frequency of 86 ton: 130.7901907356948
fundamental frequency of 87 ton: 138.32853025936598
fundamental frequency of 88 ton : 146.78899082568807
fundamental frequency of 89 ton : 126.98412698412697
fundamental frequency of 90 ton : 134.45378151260505
fundamental frequency of 91 ton: 142.433234421365
fundamental frequency of 92 ton: 150.9433962264151
fundamental frequency of 93 ton: 160.0
fundamental frequency of 94 ton: 155.33980582524273
fundamental frequency of 95 ton : 179.77528089887642
fundamental frequency of 96 ton : 233.00970873786406
fundamental frequency of 97 ton : 201.68067226890756
fundamental frequency of 98 ton: 235.2941176470588
fundamental frequency of 99 ton : 226.41509433962264
fundamental frequency of 100 ton : 240.0
fundamental frequency of 101 ton : 253.96825396825395
fundamental frequency of 102 ton : 155.84415584415586
fundamental frequency of 103 ton: 156.86274509803923
fundamental frequency of 104 ton: 475.2475247524753
fundamental frequency of 105 ton : 440.3669724770642
fundamental frequency of 106 ton : 533.3333333333333
fundamental frequency of 107 ton: 4000.0
fundamental frequency of 108 ton: 695.6521739130435
```

Na mych hodnotách přesně vídím, jak lepší vychazí základní frekvence pro nížší tony, něž přes DFT. Ale taký je selhaní pro vyšší tony. Můžeme podívat proč tak stalo přes graf (nejvýšší peaky je červené kruhy









Porovnavá všechny sve hodnoty jsem řešíl že nejlepší pro tony od 0 do 42 základní frekvence lepší vypočítat přes autokorelace, ostatní přes DFT. Koneční hodnoty uložil do f_f. Vídímé že plus mínus mojí hodnoty mohou mít nejaký malí rozdil od frekvence v souboru. Jsem předpokladam, že porbelm může byt kvuli odchylkam ve vypočtéch a taký tomu, že klavír s velkou pravděpodoností rozladení (vídíme to na největších tonech, kde odchylka dosauje 1 nebo 2 body).


Fundamental frequency


```
Fundamental frequency of 24 ton: 32.80929596719071
Fundamental frequency of 25 ton: 34.757422157856624
Fundamental frequency of 26 ton: 36.83806600153492
Fundamental frequency of 27 ton: 39.02439024390244
Fundamental frequency of 28 ton: 41.343669250645995
Fundamental frequency of 29 ton: 43.7956204379562
Fundamental frequency of 30 ton : 46.42166344294004
Fundamental frequency of 31 ton: 49.18032786885246
Fundamental frequency of 32 ton : 52.11726384364821
Fundamental frequency of 33 ton : 55.172413793103445
Fundamental frequency of 34 ton : 58.465286236297196
Fundamental frequency of 35 ton: 61.935483870967744
Fundamental frequency of 36 ton : 65.57377049180327
Fundamental frequency of 37 ton : 69.46454413892909
Fundamental frequency of 38 ton : 73.61963190184049
Fundamental frequency of 39 ton: 77.92207792207793
Fundamental frequency of 40 ton: 82.61617900172118
Fundamental frequency of 41 ton: 87.75137111517367
Fundamental frequency of 42 ton: 92.0
Fundamental frequency of 43 ton: 98.0
Fundamental frequency of 44 ton: 104.0
```


```
Fundamental frequency of 45 ton: 110.0
Fundamental frequency of 46 ton: 118.0
Fundamental frequency of 47 ton: 124.0
Fundamental frequency of 48 ton: 130.0
Fundamental frequency of 49 ton: 138.0
Fundamental frequency of 50 ton: 146.0
Fundamental frequency of 51 ton: 156.0
Fundamental frequency of 52 ton: 164.0
Fundamental frequency of 53 ton: 350.0
Fundamental frequency of 54 ton : 370.0
Fundamental frequency of 55 ton: 392.0
Fundamental frequency of 56 ton: 208.0
Fundamental frequency of 57 ton: 220.0
Fundamental frequency of 58 ton: 234.0
Fundamental frequency of 59 ton: 248.0
Fundamental frequency of 60 ton : 262.0
Fundamental frequency of 61 ton: 278.0
Fundamental frequency of 62 ton: 294.0
Fundamental frequency of 63 ton: 312.0
Fundamental frequency of 64 ton : 330.0
Fundamental frequency of 65 ton: 350.0
Fundamental frequency of 66 ton: 370.0
Fundamental frequency of 67 ton: 392.0
Fundamental frequency of 68 ton: 416.0
Fundamental frequency of 69 ton: 440.0
Fundamental frequency of 70 ton: 466.0
Fundamental frequency of 71 ton: 494.0
Fundamental frequency of 72 ton: 524.0
Fundamental frequency of 73 ton : 554.0
Fundamental frequency of 74 ton: 588.0
Fundamental frequency of 75 ton : 622.0
Fundamental frequency of 76 ton : 660.0
Fundamental frequency of 77 ton: 698.0
Fundamental frequency of 78 ton: 740.0
Fundamental frequency of 79 ton: 784.0
Fundamental frequency of 80 ton: 830.0
Fundamental frequency of 81 ton : 882.0
Fundamental frequency of 82 ton: 932.0
Fundamental frequency of 83 ton: 988.0
Fundamental frequency of 84 ton: 1046.0
Fundamental frequency of 85 ton: 1108.0
Fundamental frequency of 86 ton: 1174.0
Fundamental frequency of 87 ton: 1244.0
Fundamental frequency of 88 ton: 1318.0
Fundamental frequency of 89 ton: 1396.0
Fundamental frequency of 90 ton: 1478.0
Fundamental frequency of 91 ton: 1566.0
Fundamental frequency of 92 ton: 1660.0
Fundamental frequency of 93 ton: 1758.0
Fundamental frequency of 94 ton: 1864.0
Fundamental frequency of 95 ton: 1976.0
Fundamental frequency of 96 ton: 2094.0
Fundamental frequency of 97 ton: 2218.0
Fundamental frequency of 98 ton: 2350.0
Fundamental frequency of 99 ton: 2490.0
Fundamental frequency of 100 ton: 2638.0
Fundamental frequency of 101 ton: 2796.0
```

```
Fundamental frequency of 102 ton: 2962.0 Fundamental frequency of 103 ton: 3138.0 Fundamental frequency of 104 ton: 3324.0 Fundamental frequency of 105 ton: 3522.0 Fundamental frequency of 106 ton: 3732.0 Fundamental frequency of 107 ton: 3954.0 Fundamental frequency of 108 ton: 4188.0
```

Taky v zádaní potřeboval ukazat základní frekvence(červené kruhy) pro své tři tony na obrazku:







3. Zpřesnění odhadu základní frekvence f0

Pro navrh DTFT použil kod pana Černockého z pythonotebook pro 2 přednašku a předělal pod svuj nazor na řešení projektu. Funkce jmenuje found_f0_by_dtft(index_ton).

```
>>def found f0 by dtft(index ton):
      if(index_ton<41):</pre>
>>
                                    # work with 24-40 tons with small frequancy
          freq interval = 92
                                    # diaposon for found approximate fundamental frequency
>>
          freq points = 300
                                    # point for found in interval
>>
      elif(index ton>80):
                                    # work with 41-80 tons with middle frequancy
>>
          freq interval = 3
          freq points = 1000
>>
      else:
                                    #work with 80-108 tons with big frequancy
>>
          freq interval = 4
>>
>>
          freq points = 600
      N = 24000
                                # frekquency of my ton
>>
>>
      n = np.arange(0, Fs/2) # range 0...24
>>
>>
      freq from = f f[index ton-24]-freq interval
      freq to = f [index ton-24]+freq interval
>>
      freq_distribution = np.linspace(freq_from, freq_to, freq_points)
>>
>>
      A = np.zeros([freq points, N],dtype=complex)
      for k in np.arange(0,freq points):
>>
          A[k,:] = np.exp(-1j * 2 * np.pi * freq distribution[k] / Fs * n)
      dtft out = np.matmul(A,xall[index ton].T)
>>
      f0 = freq distribution[np.argmax(np.abs(dtft out))]
>>
>>
      if(index ton<41 or (index ton>=53 and index ton<56)):
          return f0/2
>>
>>
       return f0
```

Zakladni princip funkce v tom ze vybírám nejaky interval pro vyhledaní f0. ten interval bude rovnat (freq_interval) a cislo bodu na kterých rozdělim ten interval(freq_points) zaleží na tom jakou frekvence má ton. Experementalním metodem jsem vyřešíl, že pro malý frekvence(<41 ton) lepší freq_interval = 92, freq_points = 300; pro střední frekvence(41...79 ton): freq_interval = 4, freq_points = 600; a pro velky(>=80 ton): freq_interval = 3, freq_points = 1000.

Dál přesně popíšu interval své frekvnece přídaním a odebíraním od už nalezene v minulé uloze základní frekvence mého tonu (freq_from, freq_to). Rozdělim ten interval po bodech, který zádal v freq_points přes funkce np.linspace a uložíme do freq_distribution. Dál budu pracovat přes základní formulu DTFT, kde vynasobím transponované zodpovědné hodnoty svého tonu a exponencial v stupnu s urcitou omegou.

$$X(e^{j\omega}) = \sum_{n=-\infty}^{\infty} x[n]e^{-j\omega n}$$

Pro exponencialu vytvořím prazdnu maticu A[] a načtem hodnoty.

```
>> for k in np.arange(0,freq_points):
>> A[k,:] = np.exp(-1j * 2 * np.pi * freq distribution[k] / Fs * n)
Jak vidime na každu položku maticy načteme e**(-j*omega*n).
```

Omega = 2*pi* freq_distribution[k]/Fs.

Vynasobíme transponované zodpovědné hodnoty svého tonu a exponencial v stupnu s urcitou omegou a uložíme hodnoty do dtft_out. Tohlé budou DTFT mého tonu. Základnou frekvence bode maximalná hodnota DTFTF. Uložil ji do fo a vratíme(kdy vratíme hodnoty tonu 0...40 musíme ji rozdělit dvema, kvůli zvláštnosti prace z tony malych frekvencí.).

Můj metod vypočtu může mít nejaký malý odchyclku kvůli výbrané metody vyhledávání hodnot f0, a taký můžeme vídět chybu +- 1 nebo 2 Hz na vyšších tonu kvůli tomu, o čem už psal, že klavír s velkou pravděpodoností rozladení.

Hodnoty zachovám v fo dtft.

Finaly fundamental frequency by DTFT

```
Fundamental frequency of 24 ton : 32.558494137441514
Fundamental frequency of 25 ton: 34.7633264635437
Fundamental frequency of 26 ton: 36.72672530845976
Fundamental frequency of 27 ton: 38.74296435272046
Fundamental frequency of 28 ton: 41.13337308686147
Fundamental frequency of 29 ton : 43.590117911285795
Fundamental frequency of 30 ton : 46.13390864454695
Fundamental frequency of 31 ton : 49.051702395964696
Fundamental frequency of 32 ton : 51.750939614131795
Fundamental frequency of 33 ton : 54.81697612732096
Fundamental frequency of 34 ton: 58.30956619507168
Fundamental frequency of 35 ton : 61.583126550868485
Fundamental frequency of 36 ton : 65.24842370744011
Fundamental frequency of 37 ton: 69.03996437715685
Fundamental frequency of 38 ton: 73.57904672015101
Fundamental frequency of 39 ton: 77.8841158841159
Fundamental frequency of 40 ton: 82.38501257778367
Fundamental frequency of 41 ton: 87.70462654088318
Fundamental frequency of 42 ton : 92.92821368948248
Fundamental frequency of 43 ton: 98.46076794657763
Fundamental frequency of 44 ton: 104.30050083472455
Fundamental frequency of 45 ton: 110.51419031719533
```

```
Fundamental frequency of 46 ton: 117.07178631051752
Fundamental frequency of 47 ton : 123.17863105175292
Fundamental frequency of 48 ton: 130.51419031719533
Fundamental frequency of 49 ton: 138.2737896494157
Fundamental frequency of 50 ton: 146.6744574290484
Fundamental frequency of 51 ton : 155.37896494156928
Fundamental frequency of 52 ton: 164.6076794657763
Fundamental frequency of 53 ton: 174.7696160267112
Fundamental frequency of 54 ton : 185.15692821368947
Fundamental frequency of 55 ton : 196.17028380634392
Fundamental frequency of 56 ton : 207.80634390651085
Fundamental frequency of 57 ton : 220.15358931552586
Fundamental frequency of 58 ton : 233.24540901502505
Fundamental frequency of 59 ton: 247.07178631051752
Fundamental frequency of 60 ton: 261.7662771285476
Fundamental frequency of 61 ton: 277.338898163606
Fundamental frequency of 62 ton : 293.6193656093489
Fundamental frequency of 63 ton: 311.085141903172
Fundamental frequency of 64 ton : 329.59265442404006
Fundamental frequency of 65 ton : 349.13856427378965
Fundamental frequency of 66 ton : 369.88647746243737
Fundamental frequency of 67 ton : 391.87312186978295
Fundamental frequency of 68 ton: 415.4590984974958
Fundamental frequency of 69 ton : 440.12687813021705
Fundamental frequency of 70 ton: 466.2737896494157
Fundamental frequency of 71 ton: 493.8330550918197
Fundamental frequency of 72 ton: 523.1919866444074
Fundamental frequency of 73 ton: 554.3005008347245
Fundamental frequency of 74 ton : 587.1919866444074
Fundamental frequency of 75 ton: 622.1001669449082
Fundamental frequency of 76 ton : 659.0851419031719
Fundamental frequency of 77 ton: 697.5525876460767
Fundamental frequency of 78 ton : 739.0851419031719
Fundamental frequency of 79 ton: 783.0984974958263
Fundamental frequency of 80 ton: 829.6060100166945
Fundamental frequency of 81 ton: 879.0
Fundamental frequency of 82 ton: 931.3483483483484
Fundamental frequency of 83 ton: 987.6126126126126
Fundamental frequency of 84 ton : 1046.1531531531532
Fundamental frequency of 85 ton: 1108.3213213213214
Fundamental frequency of 86 ton : 1174.2192192192
Fundamental frequency of 87 ton: 1244.099099099099
Fundamental frequency of 88 ton : 1318.1711711712
Fundamental frequency of 89 ton: 1395.930930931
Fundamental frequency of 90 ton: 1478.93993993994
Fundamental frequency of 91 ton: 1566.903903903904
Fundamental frequency of 92 ton: 1660.051051051051
Fundamental frequency of 93 ton: 1758.945945946
Fundamental frequency of 94 ton : 1863.6006006006005
Fundamental frequency of 95 ton : 1976.4714714714
Fundamental frequency of 96 ton: 2093.990990991
Fundamental frequency of 97 ton : 2218.5015015015
Fundamental frequency of 98 ton : 2350.6516516516517
Fundamental frequency of 99 ton : 2490.4174174174173
Fundamental frequency of 100 ton : 2638.5195195197
Fundamental frequency of 101 ton: 2795.066066066066
Fundamental frequency of 102 ton: 2961.252252252252
```

Fundamental frequency of 103 ton : 3137.39039039039
Fundamental frequency of 104 ton : 3324.021021021021
Fundamental frequency of 105 ton : 3521.6906906906906
Fundamental frequency of 106 ton : 3731.1501501501502
Fundamental frequency of 107 ton : 3953.1921921921
Fundamental frequency of 108 ton : 4188.249249249249

4. Reprezentace klavíru

>>

>>

>>

if(index ton<41):</pre>

Abych spočitat koeficienty na násobcích základní frekvence (1f0 . . . 5f0), modulu a faze trochu perepracoval funkce z 3 ulohy found f0 by dtft(index ton) na found f0 by dtft for 4(index ton, f0 dtft old). >># the function found f0 by dtft() takes a VERY long time to process!!!!!!!!!!!!!!!!!! >>def found f0 by dtft for 4(index ton, f0 dtft old): if(index ton<41):</pre> >> freq interval = 92>> freq points = 300>> elif(index_ton>80): >> freq interval = 3>> freq points = 1000 >> >> >> freq interval = 4freq points = 600>> N = 24000>> >> n = np.arange(0, Fs/2)>> >> freq from = f0 dtft old-freq interval >> freq to = f0 dtft old+freq interval >> >> freq distribution = np.linspace(freq from, freq to, freq points) >> A = np.zeros([freq points, N],dtype=complex) >> for k in np.arange(0,freq points): >> A[k,:] = np.exp(-1j * 2 * np.pi * freq distribution[k] / Fs * n)>> dtft out = np.matmul(A,xall[index ton].T) >> f0 = freq distribution[np.argmax(np.abs(dtft out))] >>

Mám moc malí rozdil. První, předavám argementem f0 a neberu ji z f_f. A spočítám module (np.abs (dtft_out)) a fázi (np.angle (dtft_out)).

return f0, np.argmax(np.angle(dtft out)), np.argmax(np.abs(dtft out))

return f0/2, np.argmax(np.angle(dtft out)), np.argmax(np.abs(dtft out))


Pro každžý ton spočítam jeho koeficienty postupním násobením f0 na 2, 3, 4, 5 a předaváním jich jak argument v funkce <code>found_f0_by_dtft_for_4(index_ton, f0_dtft_old)</code>. Uložím všechny hodnoty do <code>_f0_cislotonu_co</code> (koeficienty), <code>_f0_cislotonu_faze</code> (faze), <code>_f0_cislotonu_modul</code> (modul). UPOZORNENÍ: pro ton 34 z toho důvodu že on má malou frekvence vznasobil jeste jednou dva, zodpovědné zvláštnosti prace z tony malych frekvencí. Pro příklad ton 64


```
>>_f0_63_co = np.zeros(5)
>>_f0_63_faze = np.zeros(5)
>>_f0_63_modul = np.zeros(5)
>>_f0_63_co[0], _f0_63_faze[0], _f0_63_modul[0] = found_f0_by_dtft_for_4(63, f_f[63-24])
>>_f0_63_co[1], _f0_63_faze[1], _f0_63_modul[1] = found_f0_by_dtft_for_4(63, 2*f0_dtft[63-24])
>>_f0_63_co[2], _f0_63_faze[2], _f0_63_modul[2] = found_f0_by_dtft_for_4(63, 3*f0_dtft[63-24])
>>_f0_63_co[3], _f0_63_faze[3], _f0_63_modul[3] = found_f0_by_dtft_for_4(63, 4*f0_dtft[63-24])
>>_f0_63_co[4], _f0_63_faze[4], _f0_63_modul[4] = found_f0_by_dtft_for_4(63, 5*f0_dtft[63-24])
```


Hodnoty koeficientu:

```
f0...5f0 for tone 34
tone 34: 1*f0 = 58.30956619507168, faze = 257.0, modul = 244.0
tone 34: 2*f0 = 87.54220931322028, faze = 177.0, modul = 55.0
tone 34: 3*f0 = 204.3902370467535, faze = 104.0, modul = 242.0
tone 34: 4*f0 = 204.46903401105595, faze = 228.0, modul = 56.0
tone 34: 5*f0 = 292.3170617445892, faze = 139.0, modul = 152.0
       f0...5f0 for tone 64
tone 63: 1*f0 = 311.085141903172, faze = 241, modul = 231.0
tone 63: 2*f0 = 621.669449081803, faze = 0, modul = 262.0
tone 63: 3*f0 = 933.4223706176963, faze = 385, modul = 312.0
tone 63: 4*f0 = 1244.8547579298831, faze = 299, modul = 338.0
tone 63: 5*f0 = 1558.2771285475794, faze = 91, modul = 513.0
       f0...5f0 for tone 105
tone 105: 1*f0 = 3521.6906906906906, faze = 356.0, modul = 448.0
tone 105: 2*f0 = 7044.54954954955, faze = 883.0, modul = 694.0
tone 105: 3*f0 = 10564.240240240239, faze = 179.0, modul = 361.0
tone 105: 4*f0 = 14084.60960960961, faze = 31.0, modul = 141.0
tone 105: 5*f0 = 17611.453453453454, faze = 840.0, modul = 999.0
```

Po vše vypočty ukažu své f0...5f0 na grafu spectra třech tonu(34, 63, 105). Pro každý koeficient nalezl odpovídající mu frekvence z F34/F63/F105 a přes nejí spočítam odpovídající číslo na OY. Ale pro te nalezeni musil zaokrehlit hodnoty koeficienty a jindy udělat +- 1, protoze v F34/F63/F105 mám jenom celý sudí čisla a po zaokruhlení koeficinety můžou být lichí, ale je to velmi malá změna a nic nezkazí.







5. Syntéza tónů

Pro syntezu nových tonu jsem použil metod přes cosinus. Jsem udělal array time ve ktrým rozlošíl sekundu kterou musím zapsat na Fs(48000). Pak pro každý ten vozork času udělall součet cosinusu 5 krát, který vydal tahle:

modul*cos(2*PI*time*frequency - faze), kde

modul, frequency, faze mám z minulou ulohy a čas bude aktualní čas mezí 0...48000

```
>>time = np.linspace(0, 1, Fs)  #array for time 0-1s 48000 point in this interval
>>a_signal = np.zeros(48000)  # array for signal
>>for t in range(0, time.size):

    a_signal[t] = _f0_34_modul[0]*np.cos(2*np.pi*time[t]*_f0_34_co[0] +
    _f0_34_faze[0])+_f0_34_modul[2]*np.cos(2*np.pi*time[t]*_f0_34_co[2] +
    _f0_34_faze[1])+_f0_34_modul[3]*np.cos(2*np.pi*time[t]*_f0_34_co[3] +
    _f0_34_faze[3])+_f0_34_modul[4]*np.cos(2*np.pi*time[t]*_f0_34_co[4] + _f0_34_faze[4])
```

Dál rozdělím ten nový signal na jeho dloužku abych zbavít se velkou amplitude.

```
>>a_signal = a_signal/a_signal.size
```

Na konce prostě zapíšem ten novy signal do audio failu a vykreslim 10 periodu original a nového signalu.

