EXPERIMENTS ON BUILDING HIGH LEVEL ABSTRACTIONS WITH C

PART 1: SMART POINTERS

WITH A TASTEFUL HINT OF GNU EXTENSIONS

Franklin "Snaipe" Mathieu – 2017

4/12/2015

EPITA - GCONFS

SMART POINTERS FOR GNU C99

SMART POINTERS FOR GNU C99

Memory management is an unsolved problem.

Known techniques rely on RAII, Reference counting, Garbage collection

There is no silver bullet, each has its drawbacks

A CASE STUDY ON C++

C++ solves the problem with RAII and smart pointers:

A CASE STUDY ON C++

C++ solves the problem with RAII and smart pointers:
File I/O and RAII:
 {
 std::fstream file("foo.txt");
 file << "Hello world";
 } // file is closed when exiting the scope</pre>

```
C++ solves the problem with RAII and smart pointers:
File I/O and RAII:
    std::fstream file("foo.txt");
    file << "Hello world";
  } // file is closed when exiting the scope
Memory allocation:
    auto ptr = std::make unique<int>(42);
    std::cout << *ptr;
  } // the memory is freed when exiting the scope
```

RAII WITH C

There are no RAII facilities in standard C – cleanup is mainly done with goto

```
FILE *f = fopen("foo.txt", "w");
 if (!f)
    goto cleanup;
 // do things
 if (error case)
    goto cleanup;
 // do more things
cleanup:
 if (f) fclose(f);
```

EXTENSIONS TO THE RESCUE

Thankfully, some compilers leverage these limitations with extensions:

EXTENSIONS TO THE RESCUE

Thankfully, some compilers leverage these limitations with extensions:

MSVC: Structured exception handling and try/finally

```
FILE *f = NULL;
__try {
    f = fopen("foo.txt", "w");
} __finally {
    if (f) fclose(f);
}
```

EXTENSIONS TO THE RESCUE

Thankfully, some compilers leverage these limitations with extensions:

```
MSVC: Structured exception handling and try/finally
  FILE *f = NULL;
  trv {
      f = fopen("foo.txt", "w"):
  } finally {
      if (f) fclose(f);
GCC, Clang/LLVM, ICC: cleanup attribute
  void fclose stack(FILE **f) { if (*f) fclose(*f); }
  attribute ((cleanup(fclose stack)))
  FILE *f = fopen("foo.txt", "w");
```

BUILDING AN AUTOMATIC POINTER

The cleanup attribute provides the basic building block for an automatic pointer:

```
void free_stack(void **f) {
    free(*f);
}
#define auto_ptr __attribute__((cleanup(free_stack)))
auto_ptr int *val = malloc(sizeof (int));
*val = 31>174;
```

But it's not good enough.

A FEW ISSUES

```
auto_ptr int *val = malloc(sizeof (int));
 *val = 24;

VS.
auto ptr = std::make_unique<int>(24);
```

· Resource not shareable

· Not convenient to use

In other words, it's useless garbage.

· No support for structure cleanup

IMPLEMENTING DESTRUCTORS

We need to store a destructor function.

We need to store metadata.

We need a custom allocator.

Introducing smalloc/sfree:

```
typedef void (f dtor)(void*);
typedef struct {
    f dtor *dtor;
} s meta;
void *smalloc(size t size, f dtor *dtor) {
    size t prefix sz = align(sizeof (s meta));
    s meta *ptr = malloc(size + prefix sz);
    ptr->dtor = dtor;
    return (char *) ptr + prefix_sz;
void sfree(void *ptr) {
    s meta *meta = get meta(ptr);
    if (meta->dtor) meta->dtor(ptr);
    free(ptr):
```

```
void *smalloc(size_t size, void (*dtor)(void*));
```

```
struct smalloc args {
  size t size;
  void (*dtor)(void*, void*);
  struct {
      void *data;
      size t metasize;
 } meta;
void *smalloc(struct smalloc args *);
#define smalloc(...)
  smalloc(&(struct smalloc_args) {
     __VA_ARGS_
```

```
smart int *ptr = smalloc(sizeof (int));
smart int *ptr = smalloc(sizeof (int), my int dtor);
smart int *ptr = smalloc(
        sizeof (int),
        my int dtor,
        { my meta, sizeof (my meta) }
    );
smart int *ptr = smalloc(
        .size = sizeof (int),
        .dtor = my int dtor,
        .meta = { my meta, sizeof (my meta) }
    );
```



A LOOK BACK ON WHAT WE DID

We could leave it at that, but...

```
sfree is the universal deallocator, just like delete in C++
ISO C99:
    whatever *ptr = smalloc(
             .size = sizeof (whatever),
             .dtor = dtor whatever
         );
    // manipulate ptr
    sfree(ptr):
C99 with GNU extensions:
    smart whatever *ptr = smalloc(
             .size = sizeof (whatever),
             .dtor = dtor whatever
         );
    // manipulate ptr
```

15



SHARED POINTERS

```
Unique pointers (no shared ownership)
  smart int *ptr = smalloc(UNIQUE, sizeof (int));
Shared pointers (shared ownership)
  void *sref(void *); // increments reference counter
  smart int *ptr = smalloc(SHARED, sizeof (int));
  smart int *ref = sref(ptr);
```

SHARED POINTERS: A SIMPLE EXAMPLE

```
smart int *ptr = smalloc(SHARED, sizeof (int));
if (!ptr)
    abort();

*ptr = 42;

list_add(some_list, sref(ptr));
list_add(some_list, sref(ptr));
list_add(some_list, sref(ptr));
```

SYNTAX SUCKS AGAIN

The boilerplate code strikes back.

SYNTAX SUCKS AGAIN

The boilerplate code strikes back.

- Obligatory NULL check.
- · We almost always define a value right away.

Nobody wants to do that hundred of times.

ADDING MORE SYNTACTIC SUGAR TO THE CAKE

```
Let's introduce two macros: unique_ptr and shared_ptr.
smart int *yes = unique_ptr(int, 1);
smart int *yes = unique_ptr(int, .value = 1);

typedef struct { float x; float y; } point;

smart point *zero = unique_ptr(point);
smart point *p = shared ptr(point, { 1.3, 4.2 });
```

HANDLING ARRAYS

smalloc/sfree is the equivalent of new/delete in C++.

There is no equivalent for new[] and delete[].

We need to change the implementation of smalloc to handle arrays and change unique_ptr and shared_ptr.

HANDLING ARRAYS

smalloc/sfree is the equivalent of new/delete in C++.

There is no equivalent for new[] and delete[].

We need to change the implementation of smalloc to handle arrays and change unique_ptr and shared_ptr.

```
smart int *arr = unique_ptr(int[5], {1, 2, 3, 4, 5});
```

HANDLING ARRAYS

smalloc/sfree is the equivalent of new/delete in C++.

There is no equivalent for new[] and delete[].

We need to change the implementation of smalloc to handle arrays and change unique_ptr and shared_ptr.

```
smart int *arr = unique_ptr(int[5], {1, 2, 3, 4, 5});
for (size_t i = 0; i < array_length(arr); ++i)
    printf("%d\n", arr[i]);</pre>
```



WHAT'S NEXT?

- weak pointers
- · move semantics for ownership transfer

Any sensible contribution is welcome.

https://snai.pe/git/libcsptr

franklinmathieu+libcsptr@gmail.com

Snaipe on # criterion - dev @ irc.freenode.net





EXTRACTING THE SIZE OF AN ARRAY

Let T be a type and dummy be a variable of type T[1].

Then:

- sizeof (dummy[0]) is the size in bytes of the compound type of T.
- sizeof (dummy) / sizeof (dummy[0]) is the length of the array if T is an array type, 1 otherwise.

Example:

```
T[1] v;
size_t size = sizeof (v[0]);
size_t lenght = sizeof (v) / sizeof (v[0]);
printf("%lu, %lu\n", size, length);
```

If T is an int, this prints 4, 1.

If T is an int[20], this prints 4, 20.

Note: If T is a multidimensional array type, the yielded length is the