Subprograms ©SoftMoore Consulting Slide 1

Subprograms

- The term subprogram will be used to mean either a procedure or a function.
- We have already addressed subprograms and issues of scope within the scanner, parser, and identifier table, so most of the effort required to implement subprograms involves modifications of the AST classes.

©SoftMoore Consulting Slide

2

Grammar Rules Relevant to Subprograms

• subprogramDecls = (subprogramDecl)* .

1

- subprogramDecl = procedureDecl | functionDecl .
- procedureDecl = "procedure" procId (formalParameters)?
 "is" initialDeclPart statementPart procId ";" .
- functionDecl = "function" funcId (formalParameters)?

 "return" typeName "is" initialDeclPart statementPart
 funcId ";" .
- parameterDecl = ("var")? paramId ":" typeName .
- procedureCallStmt = procId (actualParameters)? ";" .

©SoftMoore Consulting Slide 3

Grammar Rules Relevant to Subprograms (continued)

- actualParameters = "(" expressions ")" .
- returnStmt = "return" (expression)? ";" .
- functionCall = funcId (actualParameters)? .

©SoftMoore Consulting Slide 4

3

Relevant Parser Methods (based on grammar rules)

- List<SubprogramDecl> parseSubprogramDecls()
- SubprogramDecl parseSubprogramDecl()
- ProcedureDecl parseProcedureDecl()
- FunctionDecl parseFunctionDecl()
- List<ParameterDecl> parseFormalParameters()
- ParameterDecl parseParameterDecl()
- ProcedureCallStmt parseProcedureCallStmt()
- List<Expression> parseActualParameters()
- ReturnStmt parseReturnStmt()
- FunctionCall parseFunctionCall()

©SoftMoore Consulting Slide 5

Relevant AST Classes

AST

Declaration
Statement Expression

ParameterDecl SubprogramDecl ProcedureCallStmt ReturnStmt FunctionCall

FunctionDecl ProcedureDecl

GSottMoore Consulting

Slide 6

5 6

Procedure Example - Parameters var x : Integer; procedure inc(var n : Integer) is begin n := n + 1; end inc; begin x := 5; inc(x); writeln(x); end.

What value is printed? If "var" is removed from the parameter declaration, what value is printed?

©SoftMoore Consulting

7

The Scope Level of a Variable Declaration

- During code generation, when a variable or named value is referenced in the statement part of a program or subprogram, we need to be able to determine where the variable was declared.
- Class IdTable contains a method getCurrentLevel() that returns the block nesting level for the current scope.
- PROGRAM for objects declared at the outermost (program) scope.
- SUBPROGRAM for objects declared within a subprogram.
- When a variable is declared, the declaration is initialized with the current level.

ScopeLevel scopeLevel = idTable.getCurrentLevel();
varDecl = new VarDecl(identifiers, varType, scopeLevel);

©SoftMoore Consulting Slid

9

Class IdTable

- Class IdTable supports the ability to open new scopes and to search for declarations, both within the current scope and in enclosing scopes.
- Class IdTable is implemented as a stack of maps from identifier strings (names of things) to their declarations.
 (Note that, since we don't allow subprograms to be nested, our stack has at most two levels.)
- When a new scope is opened, a new map is pushed onto the stack. When a scope is closed, the top map is popped off the stack.

©SoftMoore Consulting Slide 11

```
Procedure Example - Scope
```

```
var x : Integer;
var y : Integer;
procedure P1 is
                                  Variables and constants
   var x : Integer;
                                  can be declared at the
   var n : Integer;
                                  program (global) level or
begin
                                  at the subprogram level,
   x := 5; // which x?
   n := y; // which y?
                                  introducing the concept
end P1;
                                  of scope.
begin
   x := 8;
                // which x?
end.
©SoftMoore Consulting
```

8

Example: Scope Levels

```
var x : Integer;
                          // scope level of declaration is PROGRAM
// scope level of declaration is PROGRAM
var y : Integer;
procedure P1 is
                             // scope level or declaration is PROGRAM
    var x : Integer; // scope level of declaration is SUBPROGRAM
var b : Integer; // scope level of declaration is SUBPROGRAM
    ... x ... // x was declared at SUBPROGRAM scope
... b ... // b was declared at SUBPROGRAM scope
     ... y ... // y was declared at PROGRAM scope
end p;
begin
      ... x ...
                          // x was declared at PROGRAM scope
                          // y was declared at PROGRAM scope
// P1 was declared at PROGRAM scope
     ... y ...
... P1 ...
  ©SoftMoore Consulting
                                                                                     Slide 10
```

10

Class IdTable (continued)

 Within a subprogram, searching for a declaration involves searching within the current level (top map in the stack containing all identifiers declared at SUBPROGRAM scope) and then within the enclosing scope (the map under the top containing all identifiers declared at PROGRAM scope).

©SoftMoore Consulting Slide 12

Selected Methods in Class IdTable

```
/**

* Opens a new scope for identifiers.

*/
public void openScope()

/**

* Closes the outermost scope.

*/
public void closeScope()

/**

* Add a declaration at the current scope level.

* @throws ParserException if the identifier token associated

* with the declaration is already

defined in the current scope.

*/
public void add(Declaration decl) throws ParserException
```

_

13

Constraint Rules for Subprograms

- Return Statement
 - Type Rule: If the statement returns a value for a function, then the type of expression being returned must be the same as the function return type.
 - Miscellaneous Rule: If the return statement returns a value, then the return statement must be nested within a function declaration.
 - Miscellaneous Rule: If the return statement is nested within a function, then it must return a value.
 - Miscellaneous Rule: The return statement must be nested within a subprogram.*

*Handled by the parser using SubprogramContext.

©SoftMoore Consulting

Slide 15

15

Runtime Organization for Subprograms

Understanding the runtime organization for subprograms involves the following four major concepts

- Activation records
- Variable addressing
- · Passing parameters and returning function values
- CVM instructions for subprograms

©SoftMoore Consulting SI

Selected Methods in Class IdTable (continued)

/**

* Returns the Declaration associated with the identifier

* token. Searches enclosing scopes if necessary.

*/
public Declaration get(Token idToken)

/**

* Returns the current scope level.

*/
public ScopeLevel getCurrentLevel()

Note: ScopeLevel is an enum class with only two values, PROGRAM and SUBPROGRAM.

14

Constraint Rules for Subprograms (continued)

- Function Declaration
 - Miscellaneous Rule: There should be no var parameters
 - Miscellaneous Rule: There should be at least one return statement.
 - Miscellaneous Rule: All return statements must return a value.
- Subprogram Call (for both procedures and functions)
 - Type Rule: The number of actual parameters should be the same as the number of formal parameters, and each corresponding pair of parameter types should match.
- Procedure Call
 - Miscellaneous Rule: If the formal parameter is a var parameter, then the actual parameter must be a named value (not an arbitrary expression).

©SoftMoore Consulting

16

______·

CVM Instructions for Subprograms

- PROC (procedure/function)
- LDLADDR (load local address)
- LDGADDR (load global address)
- CALL (call subprogram)
- RET (return from a subprogram)

Note that CVM does not have separate instructions for procedures and functions.

©SoftMoore Consulting

Slide 18

Active Subprograms

- When a program is running, a subprogram is said to be active if it has been called but has not yet returned.
- When a subprogram is called, we need to allocate space on the stack for its parameters and local variables. In addition, if the subprogram is a function, we need to allocate space on the stack for the return value.
- When the subprogram returns, the allocated stack space is released.

An active subprogram is one for which this space (activation record) is currently on the stack.

©SoftMoore Consulting

Slide 19

19

Return Value Part of an Activation Record

- A function call must first allocate space on the stack for the return value. The number of bytes allocated is the number of bytes for the return type of the function.
- The emit() method in class FunctionCall contains the following code.

// allocate space on the stack for the return value
emit("ALLOC " + funcDecl.getType().getSize());

©SoftMoore Consulting

Slide 21

21

Context Part of an Activation Record

- Dynamic Link base address (BP) of the activation record for the calling subprogram
- Return address address of the next instruction following the call to the subprogram

The values for BP and PC relative to the calling subprogram are saved (pushed) onto the stack by the CVM "CALL" instruction, and they are restored by the CVM "RET" instruction.

©SoftMoore Consulting

23

Slide 23

Activation Record (a.k.a. Frame)

 An activation record is a run-time structure for each currently active subprogram. A new activation record is created every time a subprogram is called.

- · Consists of up to five parts
 - return value part (for functions only)
 - parameter part (may be empty if there are no parameters)
 - context part (always 2 words)
 - saved values for PC and BP
 - local variable part (may be empty if there are no local variables)
 - temporary part
 - · holds operands and results as statements are executed
 - is always empty at the beginning and end of every statement of the subprogram

©SoftMoore Consulting

CII.4. 20

Slide 22

20

Parameter Part of an Activation Record

- For each value parameter, a subprogram call must emit code to leave the value of the actual parameter on the top of the stack.
- For each variable (var) parameter, a procedure call must emit code to leave the address of the actual parameter on the top of the stack. The actual parameter must be a named value, not an expression.

©SoftMoore Consulting

22

Local Variable Part of an Activation Record

- If local variables are declared in a subprogram, then space must be allocated on the runtime stack for those variables
- The CVM instruction PROC (procedure) has an integer argument for the variable length of subprogram.
- Example

```
procedure P2 is
   var m, n : Integer;
   var b : Boolean;
begin
   ...
end P2;
```

©SoftMoore Consulting

Slide 26

Local Variable Part of an Activation Record (continued)

- This procedure will need to allocate nine bytes for local variables. The instruction PROC 9 will be emitted to allocate the necessary space on the runtime stack.
- An instruction of the form PROC 0 is emitted whenever a subprogram does not have any local variables.

©SoftMoore Consulting Slide 25

The temporary part of an activation record is analogous to the use of the run-time stack to hold temporary values as described in Section 10.4. As machine instructions for a subprogram are executed, the temporary part grows and shrinks. The temporary part of an activation record is empty at the start and end of each CPRL statement in the subprogram.

©SoftMoore Consulting

Temporary Part of an Activation Record

25 26

Example: Temporary Part of an Activation Record

- Assume
 - register BP has the value 200
 - local integer variable x has relative address 8
 - local integer variable y has value 6 and relative address 12
- The CPRL assignment statement

x := y + 1;

will compile to the following CVM instructions:


LDLADDR 8 LDLADDR 12 LOADW

LDCINT 1 \leftarrow will be optimized to LDCINT1 ADD


STOREW


©SoftMoore Consulting Slide 27

27 28




29 30





31 32

Example: Temporary Part of an Activation Record (continued) After execution of ADD BP → 200 dynamic link 204 return address 208 212 6 216 208 (address of x) **220** 7 (sum) @SoftMoore Consulting Slide 33




33 34

Example: Subprogram with Parameters

var x : Integer;

procedure P3(a : Integer, b : Integer) is
 var n : Integer;
begin
...
end P3;
begin
...
P3(2, 5);
...
end.



35 36

Supporting Recursion

- Since a new activation record is created every time a subprogram is called, CPRL supports recursive calls.
- To illustrate, suppose that a program calls procedure P3, and then P3 makes a recursive call to itself. Each call to P3 has its own activation record, which means each call has its own copy of parameters, locally declared variables, etc.
- The diagram on the next page illustrates this situation.

37

Supporting Recursion (continued) memory address 0 program subprogram instructions PC SB program block runtime stack act. record grows call to P3 act. record BP for second call to P3 SP higher numbered memory addresses @SoftMoore Consulting Slide 38

38

©SoftMoore Consulting

Loading a Program

- The object code is loaded into the beginning of memory starting at address 0.
- Register PC is initialized to 0, the address of the first instruction
- Register SB is initialized to the address following the last instruction (i.e., the first free byte in memory).
- Register BP is initialized to the address of the byte following the last instruction (i.e., the same as SB).
- Register SP is initialized to BP 1 since the runtime stack is empty.

©SoftMoore Consulting

Slide 39

General Discussion of Parameters

- Functions can have only value parameters, but procedures can have both variable (var) and value parameters.
- The code to handle the passing of these two kinds of parameters as part of a procedure call is somewhat analogous to how you handle an assignment statement of the form "x := y", where you generate different code for the left and right sides.
 - Left side: generate code to leave the address on the stack.
 - Right side: generate code to leave the value on the stack.

40

©SoftMoore Consulting

39

General Discussion of Parameters (continued)

- Analogy for parameters
 - Variable (var) parameters: Generate code similar to the way you handle the left side of an assignment statement.
 - Value parameters: Generate code similar to the way you handle the right side of the assignment.
- When parsing the code for actual parameters, by default we always call parseExpression().
 - generates code to leave the value of the expression on the stack
 - correct for a value parameter but not for a variable parameter
- Note that the code for class Variable contains a constructor that takes a single NamedValue object and uses it to construct a Variable object.

©SoftMoore Consulting

Slide 41

Converting NamedValue to Variable

- When you have a NamedValue expression corresponding to a variable parameter, you need to convert it to a Variable.
- One possible approach: In the checkConstraints()
 method of class ProcedureCall, when iterating through
 and comparing the list of formal parameters and actual
 parameters,
 - If the formal parameter is a variable parameter and the actual parameter is not a NamedValue, generate an error message (can't pass an arbitrary expression to a variable parameter).
 - If the formal parameter is a variable parameter and the actual parameter is a NamedValue, convert the NamedValue to a Variable.

©SoftMoore Consulting

Slide 42

41

Converting NamedValue to Variable (continued)

43

Calling a Subprogram

When a subprogram is called

@SoftMoore Consulting

- For a function, space is allocated on the stack for the return value.
- The actual parameters are pushed onto the stack.
 - expression values for value parameters
 - addresses for variable parameters
- The CALL instruction pushes the context part onto the stack
- The PROC instruction of the subprogram allocates space on the stack for the subprogram's local variables.

©SoftMoore Consulting

45

Slide 45

Return Instruction

- The CVM return instruction indicates the number of bytes used by the subprogram parameters so that they can be removed from the stack
- Example ret 8

©SoftMoore Consulting Slide 47

Converting NamedValue to Variable (continued)

44

PROC Instruction versus ALLOC Instruction

- For CVM, the PROC instruction and the ALLOC instruction are equivalent and can be used interchangeably.
- Both instructions simply move SP to allocate space on the stack; e.g., for a function return value or a subprogram's local variable.

46

©SoftMoore Consulting

Returning from a Subprogram

Slide 46

When a return instruction is executed

- BP is set to the dynamic link.
 - restores BP to the caller's activation record
- · PC is set to the return address.
 - restores PC to the caller's instructions
- SP is set so as to restore the stack to its state before the call instruction was executed.
 - For procedures, SP is set to the memory address before the activation record.
 - For functions, SP is set to the memory address of the last byte of the return value. The return value remains on the stack.

©SoftMoore Consulting

Referencing Local Variables and Parameters

The LDLADDR instruction is used to reference subprogram parameters and variables that are local to the subprogram.

- Computes the absolute address of a local variable from its relative address with respect to BP and pushes the absolute address onto the stack
- Use with subprograms is similar to the use of LDGADDR for program variables except that the relative address of the first local variable is 8 instead of 0 since there are 8 bytes in the context part of the activation record.
- Relative addresses can be negative to load the address of a parameter.

@SoftMoore Consulting

49

```
Example: Activation Record
var x : Integer;
procedure P3(a : Integer, b : Integer) is
   var n : Integer;
begin
end P3;
begin
   P3(2, 5);
end.
©SoftMoore Consulting
                                                          Slide 51
```

51

Referencing Variables and Parameters for P3

- LDLADDR -8 loads (pushes) the address of parameter a onto the stack
- LDLADDR -4 loads (pushes) the address of parameter b onto the stack
- LDLADDR 8 loads (pushes) the address of local variable n onto the stack
- LDGADDR 0 loads (pushes) the address of global variable x onto the stack

©SoftMoore Consulting

53 54


Referencing Global Variables

The LDGADDR instruction is used within a subprogram to reference global variables; i.e., variables declared at the

- Computes the absolute address of a global variable from its relative address with respect to SB and pushes the absolute address onto the stack.
- Note that LDGADDR is used the same way in subprograms as it is in the main program.

@SoftMoore Consulting

50





52

Variable (var) Parameters

- For variable (var) parameters, the address of the actual parameter is passed; i.e., the value contained in the formal parameter is the address of the actual parameter.
- We need to use two instructions to load (push) the address of actual parameter onto the stack.

©SoftMoore Consulting





55

Referencing Variables and Parameters for P4 • LDLADDR -8 loads (pushes) the address contained in parameter a (the address of x) onto the stack LOADW loads (pushes) the address of • LDLADDR -4 parameter b onto the stack • LDLADDR 8 loads (pushes) the address of local variable n onto the stack • LDGADDR 0 loads (pushes) the address of global variable x onto the stack @SoftMoore Consulting Slide 57

Method emit() for Class Variable
(Loads the address of the variable onto the stack)

@Override
public void emit() throws CodeGenException, IOException
{
 if (decl instanceof ParameterDecl
 && ((ParameterDecl)decl).isVarParam())
 {
 emit("LDLADDR " + decl.getRelAddr());
 emit("LOADW");
 }
 else if (decl.getScopeLevel() == ScopeLevel.PROGRAM)
 emit("LDGADDR " + decl.getRelAddr());
 else
 emit("LDLADDR " + decl.getRelAddr());
}

We will extend this method again when
 we consider the topic of arrays in CPRL.