# MODULE 3

# **SYLLABUS**

Assembler Design Options: Machine Independent Assembler Features – Program Blocks, Control Sections, Assembler Design Options- Algorithm for Single Pass Assembler, Multi pass Assembler, Implementation Example of

MASM Assembler


# 3.1 MACHINE INDEPENDENT ASSEMBLER FEATURES

The features which are NOT closely dependent to machine architecture are called machine independent assembler features. The machine independent assembler features includes:

- 1. Literals
- 2. Symbol Defining Statements
- 3. Expressions
- 4. Program Blocks
- 5. Control Sections and Program Linking

#### 3.1.1 LITERALS

- It is convenient for the programmer to be able to write the value of a constant operand as part of the instruction that uses it.
- This avoids having to define the constant elsewhere in the program and make a label for it.
- Such an operand is called a Literal because the value is literally in the instruction.
- A literal is defined with a prefix '=' followed by a specification of the literal value.
- Consider the following example:



Using the concept of literal we can rewrite the above code as:

. LDA =X'05'

# Difference between literal operands and immediate operands

• For literals prefix is =, and for immediate addressing prefix is #.

• In immediate addressing, the operand value is assembled as part of the machine instruction, ie there is no memory reference.

Line no	Location Counter			
55	0020	LDA	#03	010 <b>003</b>

In the above example the last 12 bits of the machine code corresponds to 003 which is equal to the immediate value.

 With a literal, the assembler generates the specified value as a constant at some other memory location. The address of this generated constant is used as the target address (TA) for the machine instruction (using PC-relative or base-relative addressing with memory reference.)

45	001A	ENDFIL	LDA	=C'EOF'		0320	10
					000000	nixbpe 110010	disp 010
93				LTORG			
	002D	*		=C'EOF'		454F	46
215	1062	WLOOP	TD	=X'05'		E320	11
230	106B		WD	=X'05'		DF20	80
	1076	*		=X'05'		05	

# **Literal Pool**

- All the literal operands used in a program are gathered together into one or more literal pools. This is usually placed at the end of the program.
- In some cases, it is desirable to place literals into a pool at some other location in the object program. To allow this an assembler directive **LTORG** is used.
- When the assembler encounters a LTORG statement, it generates a *literal pool* containing all literal operands used since previous LTORG or the beginning of the program

• Literals placed in a pool by LTORG will not be repeated in a pool at the end of the program.

• Reason for using LTORG is to keep the literal operand close to the instruction (otherwise PC-relative addressing may not be allowed)

#### **Literal Table (LITTAB)**

- A literal table(**LITTAB**) is created for storing the literals which are used in the program.
- The literal table contains the literal name, operand value and length.
- The literal table is usually created as a hash table on the literal name.

#### **Duplicate literals**

- The same literal used more than once in the program, then it can be consider as a duplicate literal.
- In such cases, only one copy of the specified value needs to be stored
- To recognize the duplicate literals, two methods are there
- 1. Compare the character strings defining them

Easier to implement e.g. =X'05'. But not possible to handle the literals like =C'EOF' and =X'454F46'.

Here both literals are same in the form of their data value.

2. Compare the generated data value

Possible to handle the literals like =C'EOF' and =X'454F46'. Here both literals are same in the form of their generated data value. So comparison based on generated data value is needed to identify duplicate literals or not. But this is difficult to implement compared to the first method.

# **Implementation of Literals** During

#### Pass-1:

The literal encountered is searched in the literal table. If the literal already exists, no action is taken; if it is not present, the literal is added to the LITTAB and for the address value it waits till it encounters LTORG or END statement for literal definition.

When Pass 1 encounters a LTORG statement or the end of the program, the

assembler makes a scan of the literal table. At this time each literal currently in the table is assigned an address. As addresses are assigned, the location counter is updated to reflect the number of bytes occupied by each literal.

# **During Pass-2:**

The assembler searches the LITTAB for each literal encountered in the instruction and replaces it with its equivalent value as if these values are generated by BYTE or WORD.

The following figure shows the difference between the SYMTAB and LITTAB

C 1		T 4	
C.V	IVI.	1 //	н.
SY	1.1	17	D

Name	Value
COPY	0
FIRST	0
CLOOP	6
ENDFIL	1A
RETADR	30
LENGTH	33
BUFFER	36
BUFEND	1036
MAXLEN	1000
RDREC	1036
RLOOP	1040
EXIT	1056
INPUT	105C
WREC	105D
WLOOP	1062

LITTAB			
Literal	Hex Value	Length	Address
C'EOF'	454F46	3	002D
X'05'	05	1	1076

# **3.1.2 SYMBOL DEFINING STATEMENTS AND EXPRESSIONS <u>EQU</u> Statement:**

- Most assemblers provide an assembler directive that allows the programmer to define symbols and specify their values.
- The directive used for this EQU (Equate).
- The general form of the statement is

# Symbol EQU value

- This statement defines the given symbol (i.e., entering in the SYMTAB) and assigns the value specified to that symbol.
- The value can be a constant or an expression involving constants and any other symbol which is already defined.
- One common usage is to define symbolic names that can be used to improve readability in place of numeric values. For example

#### LDA #100

This loads the register A with immediate value 100, this does not clearly mention what exactly this value indicates. If a statement is included as:

# MAXLEN EQU 100

and then LDA #MAXLEN then it clearly indicates that the value of MAXLEN is some maximum length value and it is to be loaded in A register.

- When the assembler encounters EQU statement, it enters the symbol MAXLEN along with
  its value in the symbol table. During LDA the assembler searches the SYMTAB for its
  entry and its equivalent value as the operand in the instruction.
- The object code generated is the same for both the options discussed, but is easier to understand.
- If the maximum length is changed from 100 to 500, it is difficult to change if it is mentioned as an immediate value wherever required in the instructions. We have to scan the whole program and make changes wherever 100 is used.
- If we mention this value in the instruction through the symbol defined by EQU, we may not have to search the whole program but change only the value of MAXLENGTH in the EQU statement.

# **ORG Statement:**

- This directive can be used to indirectly assign values to the symbols. The directive is usually called ORG (means origin).
- Its general format is:
  - **ORG value** where value is a constant or an expression involving constants and previously defined symbols.
- When this statement is encountered during assembly of a program, the assembler resets its location counter (LOCCTR) to the specified value.
- Since the values of symbols used as labels are taken from LOCCTR, the ORG statement will affect the values of all labels defined until the next ORG is encountered.

# Eg: ORG AlPHA

When this statement is encountered during assembly of a program, the assembler resets its location counter (LOCCTR) to the value of ALPHA.

#### 3.1.3 EXPRESSIONS

- The assemblers allow the use of expressions as operand
- The assembler evaluates the expressions and produces a single operand address or value.
- Assemblers generally allow arithmetic expressions as operands formed according to the normal rules using arithmetic operators +, - \*, /. (Division is usually defined to produce an integer result.)
- Individual terms may be constants, user-defined symbols, or special terms.
- The only special term used is \* ( the current value of location counter) which indicates the value of the next unassigned memory location.

Thus the statement

**BUFFEND EQU \*** 

Assigns the value of LOCCTR to BUFFEND, which is the address of the next byte following the buffer area.

Some values in the object program are relative to the beginning of the program and some
are absolute (independent of the program location, like constants). Hence, expressions are
classified as either absolute expression or relative expressions depending on the type of
value they produce.

#### Absolute Expressions:

- The expression that uses only absolute terms is absolute expression. Absolute expression may contain relative term provided the relative terms occur in pairs with opposite signs for each pair.
- Example:

#### MAXLEN EQU BUFEND-BUFFER

In the above instruction the difference in the expression BUFEND-BUFFER gives a value that does not depend on the location of the program and hence gives an absolute value

# • Relative Expressions:

• The expression that uses the values relative to the program are called relative expression.

 Absolute expression may contain relative term provided the relative terms occur in pairs with opposite signs for each pair.

# • Example:

# MAXLEN EQU ALPHA + BUFEND-BUFFER

In the above instruction the difference in the expression BUFEND-BUFFER gives a value that does not depend on the location of the program but it is added to the value of ALPHA which is program relative. Hence this expression is relative.

#### 3.1.4 PROGRAM BLOCKS

- Program blocks allow the generated machine instructions and data to appear in the object program in a different order by separating blocks for storing code, data, stack, and larger data block.
- To implement the program block the Assembler Directive used is **USE**
- Syntax is

# **USE** [block name]

- At the beginning, statements are assumed to be part of the unnamed (or default) block.
- Whenever a USE CDATA statement is encountered, statements upto next USE belongs to the program block named CDATA.
- If no USE statements are included, the entire program belongs to this single block.
- Each program block may actually contain several separate segments of the source program. Assemblers rearrange these segments to gather together the pieces of each block and assign address.
- Consider the following example:

COPY	START 0	
	LDA	LENGTH
••	• • • • • • • • • • • • • • • • • • • •	
	USE	CDATA

MAX **RESW** 1 LENGTH **RESW** USE **CBLOCKS BUFFER RESB** 00 //Subroutine to read record into buffer USE **RDREC CLEAR** X LDA **INPUT** . . . . . . . . . . . . . USE **CDATA INPUT BYTE** X'F1' . . . . . . . . . . . . //Subroutine to write record from buffer USE WRREC STA MAX . . . . . . . . . **USE CDATA** MIN **RESW RESW BUFEND** 

• In the example give above three program blocks are used:

DEFAULT: executable instructions.

CDATA: all data areas that are less in length.

CBLOCKS: all data areas that consists of larger blocks of memory.

DEFAULT
CDATA
CBLOCKS

# **Arranging code into program blocks:**

# **During Pass 1 assembler performs the following operations:**

- A separate location counter for each program block is maintained.
  - At the beginning of a block, LOCCTR is set to 0.
  - Save and restore LOCCTR when switching between blocks.
- Assign each label an address relative to the start of the block.

• Store the block name or number in the SYMTAB along with the assigned relative address of the label

- Indicate the block length as the latest value of LOCCTR for each block at the end of Pass1
- Assign to each block a starting address in the object program by concatenating the program blocks in a particular order
- At the end of pass 1 a block table is generated.

#### **Block Table**


Block Name	Block	Starting	Ending	Length of
	Number	Address	Address	Block
Default	0	0000	0065	0066
CDATA	1	0066	0070	000B
CBLKS	2	0071	1070	1000

# **During Pass 2 assembler performs the following operations:**

Calculate the address for each symbol relative to the start of the object program by adding
 The location of the symbol relative to the start of its block
 The starting address of this block

# **Program Blocks Loaded in Memory**

Separation of program into blocks results in the movement of the large buffer (CBLKS) to the end of the object program. As a result extended format, base register addressing etc are no longer needed. Modification records are also not needed. This improves program readability.



#### 3.1.5 CONTROL SECTIONS

- A control section is a part of the program that maintains its identity after assembly; each control section can be loaded and relocated independently of the others. Different control sections are most often used for subroutines or other logical subdivisions.
- The programmer can assemble, load, and manipulate each of these control sections separately. Because of this, there should be some means for linking control sections together.
- For example, instructions in one control section may refer to the data or instructions of
  other control sections. Since control sections are independently loaded and relocated, the
  assembler is unable to process these references in the usual way. Such references between
  different control sections are called external references.
- The assembler generates the information about each of the external references that will allow the loader to perform the required linking. When a program is written

using multiple control sections, the beginning of each of the control section is indicated by an assembler directive: **CSECT** 

- The syntax **secname CSECT**
- The assembler maintain separate LOCCTR beginning at 0 for each control sections.
- Control sections differ from program blocks in that they are handled separately by the assembler.

# **Handling of External References**

Instructions in one control section may need to refer to instructions or data located in another section. This is called as **external references**. The external references are indicated by two assembler directives: **EXTDEF and EXTREF** 

# **EXTDEF (External Definition)**

- It defines the symbols that are defined in this control section and may be used by other sections
- Syntax EXTDEF name [, name]
- Ex: EXTDEF BUFFER, BUFEND, LENGTH which means the symbols BUFFER, BUFFEND and LENGTH are defined in this control section and may be used by some other control sections.

# **EXTREF** (External Reference)

- It names symbols that are used in this section but are defined in some other control section.
- Syntax EXTREF name [,name]
- Ex: EXTREF A,B which means the symbols A and B are used in this control section but are defined in some other control section.

The assembler must include information in the object program that will cause the loader to handle external references properly. For this three types of records are used in object program: **Define, Refer and Modification Record.** 

	Define Record
Col. 1	D
Col. 2-7	Name of external symbol defined in this control section
Col. 8-13	Relative address of symbol within this control section (hex
Col. 14-73	Repeat information in Col 2-13 for other external symbols

	Refer record
Col. 1	R
Col. 2-7	Name of external symbol referred in this control section
Col. 8-73	Name of other external reference symbols
Col. 1	M
Col. 1	Modification Record (revised) M
Col. 2-7	Starting location of the target address to be modified, relative to the beginning of the program (not relative to the first text record)
	Length of this record in half-byte
Col. 8-9	
Col. 8-9 Col. 10	Modification flag (+ or -)

The format of modification record which we studied in Module 2 is revised to support the handling of external references.

subtracted from the indicated field

Consider the following code segments:

COPY	START 0			
	EXTDEF BUFFER, BUFFEND, LENGTH			
	EXTREF A,B			
	LDA	ALPHA		
BUFFER	WORD 3			
BUFFEND	EQU	*		
LENGTH	EQU	BUFFEND-BUFFER		
	RDREC CSECT			
	EXTREF BUFFE	R, BUFFEND, LENGTH		

LDA	BUFFER
END	

The object program generated for the above code segment is:

H^ COPY ^ 000000^001033
D^BUFFER^000033^BUFEND^001033^LENGTH^00002D
R^A ^B T^
Γ^
 E^000000

# 3.2 ASSEMBLER DESIGN OPTIONS

In this section, two alternatives to the standard two-pass assembler logic is discussed. They are:

Single Pass Assembler Multipass Assembler

# 3.2.1 SINGLE PASS ASSEMBLER

These assemblers are used when it is necessary or desirable to avoid a second pass over the source program. The main problem in designing the assembler using single pass was to resolve forward references.

One-pass assemblers could produce object codes either in memory or to external storage. One-pass assemblers usually need to modify object code already generated, so whether object code is stored in memory or external storage imposes different considerations on assembler design. Based on this one-pass assemblers can be classified into two types:

1. One that produces object code directly in memory for immediate execution (**Loadand-go assemblers**).

2. One pass assembler generating object code for later execution.

#### 1. Load-and-Go Assembler

Load-and-go assembler generates their object code in memory for immediate execution. Since no object program is written out, no loader is needed. It is useful in a system with frequent program development and testing. Since the object program is produced in memory, the handling of forward references becomes less difficult.

# **Working of One pass assembler (Load and Go Assembler)**

In load-and-Go assemblers when a forward reference is encountered:

- Omits the operand address if the symbol has not yet been defined(placess 000 at the operand addresses position)
- Enters this undefined symbol into SYMTAB and indicates that it is undefined
- Adds the location at which the operand is referenced to a list of forward references associated with the SYMTAB entry
- When the definition for the symbol is encountered, scans the reference list and inserts the address.
- At the end of the program, reports the error if there are still SYMTAB entries indicated undefined symbols(\* indicates undefined).
- When the END statement is encountered, search SYMTAB for the symbol named in the END statement and jumps to this location to begin execution if there is no error.

In short, whenever any undefined symbol is encountered it will insert into SYMTAB as a new entry and indicate that it is undefined and also adds the location at which the operand is referenced as a linked list associated with that SYMTAB entry. When the definition for the symbol is encountered, scans the reference list and inserts the address in proper location.

# Algorithm for Single Pass Assembler (Load and Go Assembler)

begin

read first input line

if OPCODE = 'START' then


```
{
                    save #[OPERAND] as starting address
           initialize LOCCTR as starting address
   } //end of if OPCODE = 'START'
else
           initialize LOCCTR to 0
   write Header record to object program
read next input line
   while OPCODE ≠ 'END'
           if this is not a comment line
           if there is a symbol in the LABEL field
   {
                    search SYMTAB for LABEL
            {
                    if found
                             if symbol value as null
                    {
                                     set symbol value as LOCCTR
                                           search the attached forward reference list(if exist) and the address of
                                           the symbol is inserted into any instructions previously generated
                                           delete the forward reference list attached to that symbol
                             }
                    }
                    else
                             insert (LABEL, LOCCTR) into SYMTAB
                 } //end of if there is a symbol in the LABEL field
           search OPTAB for OPCODE
           if found
                    search SYMTAB for OPERAND ADDRESS
                    if found
                                           if symbol value not equal to null
                          {
```

store symbol value as operand address


```
else
                                                  insert a node with address LOCCTR at the end of
                                                  the forward reference list of that symbol
                         }
                         else
                                          insert (symbol name, null)
                                          insert a node with address LOCCTR at the end of the forward
                                          reference list of that symbol
                    }
                         add 3 to LOCCTR
           else if OPCODE ='WORD'
           add 3 to LOCCTR
 else if OPCODE ='RESW' add 3 #[OPERAND] to
LOCCTR
                else if OPCODE ='RESB'
 add #[OPERAND] to LOCCTR else if OPCODE = 'BYTE'
           {
                    find length of constant in bytes
                    add length to LOCCTR
                    convert constant to object code
           }
           if object code will not fit into current text record
 { write Text record to object program initialize new text record
           }
           add object code to Text record
   read next input line
   }
  }//end of while OPCODE ≠ 'END'
write last Text record to object program
write End record to object program end
```

# **Example:**

The following figure shows the status upto this point. The symbol RREC is referred once at location 2013, ENDFIL at 201C and WRREC at location 201F. None of these symbols are defined. The figure shows that how the pending definitions along with their addresses are included in the symbol table.



When the definition for the symbols RDREC and ENDFILL are encountered, the reference list associated with the symbols is scanned and the address is inserted at proper location. It is gioven in following figure:



# 2. One pass assembler generating object code for later execution.

In this type of one pass assembler, the generated object program is stored in external storage (e.g., files on disks). So random updates to operands target addresses(as in load-andgo load-and- assemblers do) are not permitted.

For any symbol involved in forward references, once the target address of the symbol is identified, additional text records must be generated to overwrite those previously omitted target addresses. Records must be loaded in the same order as they appear in the object program. Actually, the handling of forward references are jointly done by the assembler and the linking loader.

One pass assembler which generates object code unlike load and go assembler operates in the following fashion:

- If the operand contains an undefined symbol, use 0 as the address and write the Text record to the object program.
- Forward references are entered into lists as in the load-and-go assembler.

• When the definition of a symbol is encountered, the assembler generates another Text record with the correct operand address of each entry in the reference list.

• When loaded, the incorrect address 0 will be updated by the latter Text record containing the symbol definition.

# **Example:**

```
HCOPY 00100000107A

T00100009454F4600000300000

T00200F151410094800000010062810063000004800003c2012

T00201C022024

T00201302203D

T00201302203D

T00203D1E041006001006E02039302043D8203928100630000054900F2C203A382043

T00205002205B

T00205B0710100C4C000005

T00201F022062

T002031022062

T00206218041006E0206130206550900FDC20612C100C3820654C0000

E00200F
```

#### 3.2.1 MULTI PASS ASSEMBLER

• For a two pass assembler, forward references in symbol definition are not allowed:

ALPHA EQU BETA
BETA EQU DELTA
DELTA RESW 1

- Here the problem is, the symbol BETA cannot be assigned a value when it is encountered during Pass 1 because DELTA has not yet been defined. Hence ALPHA cannot be evaluated during Pass 2. So that the symbol definition must be completed in pass 1.
- The general solution for this type of forward references is to use a multi-pass assembler that can make as many passes as are needed to process the definitions of symbols.
- It is not necessary for such an assembler to make more than 2 passes over the entire program.
- The portions of the program that involve forward references in symbol definition are saved during Pass 1.Additional passes through these stored definitions are made as the assembly progresses. This process is followed by a normal Pass 2.


# Implementation of Multipass Assembler

For a forward reference in symbol definition, we store in the SYMTAB: 

 The symbol name
 The defining expression
 The number of undefined symbols in the defining expression

- The undefined symbol (marked as \*) associated with a list of symbols depend on this undefined symbol.
- When a symbol is defined, we can recursively evaluate the symbol expressions depending on the newly defined symbol.
- The portions of the program that involve forward references in symbol definition are saved during Pass 1.Additional passes through these stored definitions are made as the assembly progresses. This process is followed by a normal Pass 2.

# **Example:**



- Consider the symbol table entries from Pass 1 processing of the statement. HALFS2 EQU MAXLEN/2
- Since MAXLEN has not yet been defined, no value for HALFS2 can be computed. The defining expression for HALFS2 is stored in the symbol table in place of its value.
- The entry &1 indicates that 1 symbol in the defining expression undefined.
- SYMTAB simply contain a pointer to the defining expression.

• The symbol MAXLEN is also entered in the symbol table, with the flag \* identifying it as undefined. Associated with this entry is a list of the symbols whose values depend on MAXLEN.

# If possible study the portion given below

