

# SCE-RT SDK Medius API Release 2.10

## Overview

March 2005

© 2005 Sony Computer Entertainment Inc.

Publication date: March 2005

Sony Computer Entertainment Inc. 2-6-21, Minami-Aoyama, Minato-ku Tokyo 107-0062, Japan

Sony Computer Entertainment America 919 E. Hillsdale Blvd. Foster City, CA 94404, U.S.A.

Sony Computer Entertainment Europe 30 Golden Square London W1F 9LD, U.K.

The SCE-RT SDK Medius API Release 2.10 – Overview is supplied pursuant to and subject to the terms of the Sony Computer Entertainment PlayStation® license agreements.

The SCE-RT SDK Medius API Release 2.10 – Overview is intended for distribution to and use by only Sony Computer Entertainment licensed Developers and Publishers in accordance with the PlayStation® license agreements.

Unauthorized reproduction, distribution, lending, rental or disclosure of this book to any third party, in whole or in part, is expressly prohibited by law and by the terms of the Sony Computer Entertainment PlayStation® license agreements.

Ownership of the physical property of the book is retained by and reserved by Sony Computer Entertainment. Alteration to or deletion of the book, in whole or in part, its presentation, or its contents is prohibited.

The information in the SCE-RT SDK Medius API Release 2.10 – Overview is subject to change without notice. The content of this book is Confidential Information of Sony Computer Entertainment.

" and "PlayStation" are registered trademarks of Sony Computer Entertainment Inc. All other trademarks are property of their respective owners and/or their licensors.

## **Table of Contents**

About This Manual	vii
Introduction	1
General Steps in Executing Medius API Function Calls	3
Connecting to the Medius Platform	6
Initializing the Medius Client Library	
MediusInitialize() vs. MediusInitializeBare()	7 7 7 7
MediusInitializeInParams	7
MediusInitializeOutParams	
MediusClose() vs. MediusCloseBare()	8
Sample – Initializing the Medius API	8
Connecting to the MAS	8
Making the Initial Connection to the MAS	9
Sample – Connecting to the MAS Starting a Session	12
Sample – Starting a Session	12
Version Information and Build Timestamps	13
Sample – Version Information and Build Timestamps	14
Establishing an Authenticated State	15
Registering a New Account	15
Account Login	16
Sample - Account Login and Registering a New Account	17
Anonymous Logins	19
Reconnecting to the MLS	20
Sample - Connecting to the MLS	21
Disconnecting From the Medius Platform	23
Graceful Disconnects	23
Ungraceful Disconnects	23
Server Time	25
What is a 'World'?	26
Reporting (Maintaining Medius Platform Connections and Objects)	27
Understanding MUM Game World Objects and DME Game Worlds	28
If a Client/Server Game	28
If a Peer-to-Peer Game	29
Report Intervals	29
Special Notes about Peer-to-Peer Host Migration and MediusWorldID	30
How and When a MediusWorldID Can Change	30
Maintaining the Medius Connection	30
Additional Notes About MediusUpdate()	30
Sending World Reports (Maintaining Game World Objects)	31
Additional Notes About MediusSendWorldReport()	31
The Sequence for Sending a 'World Report'	32
Sample – Sending a World Report	33
Sending an End Game Report (Closing Game World Objects)  Coordinating the Sending of End Game Reports	34 34
Additional Notes About MediusSendEndGameReport()	35
The Sequence for Sending an 'End Game Report'	36
Sample – Sending an End Game Report	36
Sending Player Reports (Maintaining Player Objects)	37

Additional Notes About MediusSendPlayerReport()	37
Special Note About a Player's Stats Field	38
Sequence for Sending a 'Player Report'	38
Sample - Sending a Player Report	38
Maintaining the MGCL Connection	39
Additional Notes about MGCLUpdate()	39
Sending Server Reports (Maintaining Game Server Objects)	39
Additional Notes About MGCLSendServerReport()	39
Sequence for Sending a 'Server Report'	40
Sample – Sending a Server Report	40
Leaving a Game World	41
Chat Channel Management	43
Preventing a Player from Joining a Chat Channel	43
Disabling or Enabling Medius Chat	44
Creating a Chat Channel	44
Searching for a Player	44
Searching for a Chat Channel	44
Getting Chat Channel Information	44
Retrieving a List of Chat Channels	44
Controlling the Number of Chat Channels Returned	45
Retrieving a List of Players in a Chat Channel	45
Getting Player Object Information	45
Getting the Total Chat Channel Count	45
Getting the Total Player Count	46
Chat Channel Security	46
Joining a Chat Channel	46
Sending a Chat Message (Broadcast or Instant Messaging)	46
Receiving a Chat Message	47
Chat Message History	47
Filtering Chat Channels	47
Game Management	49
Preventing a Player from Joining a Game	49
Searching for a Player	49
Searching for a Game	49
Getting Game World Object Information	50
Retrieving a List of Players in a Game World Object	50
Retrieving a List of Game World Objects	50
Controlling the Number of 'Game World Objects' Returned	51
Getting Player Object Information	51
Getting the Total Game World Object Count	51
Getting the Total Player Count	51
Game World Object Security	51
Creating a Game	52
If Creating a Client/Server Game	52
If Creating a Peer-to-Peer Game	52
Joining a Game	53
Joining Either a Client/Server Game or a Peer-to-Peer Game	53
Vote Player Out of a Game	53
Design Considerations	53
Account Management	55
Deleting an Account	55

	Table of Contents
Getting an Account ID Getting an Account Profile Updating an Account Password Updating an Account Profile Updating Account Stats	55 55 55 55 55
Buddy Lists  Retrieving a Player's Buddy List  Adding a User to a Player's Buddy List  Removing a User From a Player's Buddy List  Buddy List Permissions  Requesting Permission  Responding to a Request for Permission	<b>56</b> 56 56 56 56 57
Ignore Lists Retrieving a Player's Ignore List Adding a User to a Player's Ignore List Removing a User From a Player's Ignore List	<b>58</b> 58 58 58
Medius Dynamic List System Introduction Interface Type System Callbacks Tailoring the Subscription Subscribing Setting an Interest Callback Associating an Interest Callback Usage Service Levels Game List Row Object Declaration Field Specification Definition Field Map Definition DType Declaration DType Creation DType Destruction	59 59 59 59 60 62 62 62 63 63 63 63 64 64 64 64 65 65
Platform Requirement Functionality  Retrieving the Usage Policy and the Privacy Policy Retrieving Announcements	<b>66</b> 66 66
Co-location Co-location Example Co-location Process	<b>67</b> 67 68
Ladder Management Getting a Player's Current Ladder Stats and Updating Total Number of Players in a Ladder Ranking Getting a List of Player's in a Ladder Ranking Controlling the Number of 'Ladder Ranks' Returned Getting a Player's Current Ladder Ranking	<b>69</b> 69 69 70 70
Token Management	71
Clan Management Creating a Clan Disbanding a Clan	<b>72</b> 73 73

Getting a List of Clan Memberships	73
Getting Clan Information	74
Transferring Clan Leadership	74
Adding Members to a Clan	74
Removing Members from a Clan	75
Getting a List of Members in a Clan	75
Clan Invitations Management	75
Clan Messages Management	76
Clan Team Challenges Management	76
Clan Ladder Management	77
Medius File Services (MFS)	79
The Client Perspective	79
MFS Back End Overview	80
Medius File Services API	80
Initialization	80
Uploading a File	80
Downloading a File	81
Canceling a Upload or Download	81
Listing Files Deleting a File	81 81
MediusFileServices Sample	81
Vulgarity Filtering	82
Vulgarity Filtering Process	82
AntiCheat	83
Overview	83
Trigger Events	83
Cheat Challenges	84
Cheat Policies	84
Cheat Messages	84
Examples of MsgText in a Cheat Message	84
What AntiCheat Can and Cannot Do	85
Internationalization (Multi-Byte Language Support)	86
Example of Internationalization	86
The Process for Setting Internationalization Parameters:	87
Medius Universe Information Server (MUIS)	88
Connecting to the MUIS	88
The Process for Requesting Universe Information:	89
Running the Medius Servers	90
Operating the Medius Server Executables	90

#### **About This Manual**

The SCE-RT SDK Medius API Release 2.10 – Overview manual provides a description of the various functionalities of the Medius API. This API is part of the SCE-RT SDK, provided by Sony Computer Entertainment America (SCEA).

Please forward any questions about this document to scert-support@scea.com.

#### **Changes Since Last Release**

Several changes/additions were made to various sections throughout the document, including:

- Introduction
- Connecting to the MAS
- Registering a New Account
- Reconnecting to the MLS
- Sample Connecting to the MLS
- Graceful Disconnects
- Additional Notes About MediusSendEndGameReport()
- Medius Universe Information Server (MUIS)
- Running the Medius Servers

In addition, the following new sections were added:

- Medius File Services (MFS)
- Medius Dynamic List System
- AntiCheat

#### **Typographic Conventions**

Certain typographic conventions are used throughout this manual to clarify the meaning of the text:

Convention	Meaning
courier	Indicates literal program code.
italic	Indicates names of arguments and structure members (in structure/function definitions only).
medium bold	Indicates data types and structure/function names (in structure/function definitions only).
blue	Indicates a hyperlink.

#### **Developer Support**

#### Sony Computer Entertainment America (SCEA)

SCEA developer support is available to licensees in North America only. You may obtain developer support or additional copies of this documentation by contacting the following addresses:

Order Information	Developer Support
Attn: Developer Tools Coordinator Sony Computer Entertainment America 919 East Hillsdale Blvd. Foster City, CA 94404, U.S.A. Tel: (650) 655-8000	E-mail: scert-support@scea.com scea_support@ps2-pro.com Web: https://www.ps2-pro.com/ https://psp.scedev.net Developer Support Hotline: (650) 655-5566 (Call Monday through Friday, 8 a.m. to 5 p.m., PST/PDT)

#### **Sony Computer Entertainment Europe (SCEE)**

SCEE developer support is available to licensees only in the PAL television territories (including Europe and Australasia). You may obtain developer support or additional copies of this documentation by contacting the following addresses:

Order Information	Developer Support
Attn: Production Coordinator Sony Computer Entertainment Europe 13 Great Marlborough Street London W1F 7HP, U.K. Tel: +44 (0) 20 7859-5000	E-mail: scee_support@ps2-pro.com  Web: https://www.ps2-pro.com/ https://psp.scedev.net  Developer Support Hotline: +44 (0) 20 7911-7711 (Call Monday through Friday, 9 a.m. to 6 p.m., GMT/BST)

#### Introduction

The SCE-RT SDK includes the Medius API, DME (Distributed Memory Engine) API, and MGCL (Medius Game Communication Library) API. The Medius API, through corresponding client protocols, targets "lobby" technology and data issues, while the DME API is specific to in-game, real-time networking technology. The DME facilitates communication between game clients, game servers, and the Medius platform. In addition, included in the SCE-RT SDK is the SCE-RT++ Wrapper. If you are developing in C++ it is highly recommended that you use the SCE-RT++ Wrapper instead of making the raw Medius Calls listed in this document.

**Note:** The SCE-RT 2.10 Client SDK will require SCE-RT 2.10 or higher servers, any other use will result in undetermined behavior.

Use of the MGCL API is optional. The MGCL API provides peer-to-peer application developers the ability to post information about Internet-based 'hosted' peer-to-peer games to the Medius platform. A Medius client then uses this information to join existing games that are either in staging or in progress (late joiners).

Medius "lobby" technology encompasses communication and logic for client match-up, player registration and profiling, chat, clans/teams, ladder ranking lists, instant messaging and other lobby-specific needs.

The Medius platform consists of the following elements:

- Medius Universe Manager (MUM)
- Medius Authentication Server (MAS)
- Medius Lobby Server (MLS)
- Medius Proxy Server (MPS)
- Medius Universe Information Server (MUIS)

The Medius elements of the SCE-RT SDK include the following:

- Linux/Win32 Medius Universe Manager Server executable
- Linux/Win32 Medius Authentication Server executable
- Linux/Win32 Medius Lobby Server executable
- Linux/Win32 Medius Proxy Server executable
- PlayStation<sup>®</sup>2-compatible header files:
  - MediusClient.h
  - mediustypes.h
  - MediusClans.h
  - mgcl.h
  - MediusFileServices.h
  - MediusFileServicesTypes.h
- PlayStation<sup>®</sup>2-compatible library files:
  - librtmclPS2.a (Medius Client Library)
  - librtmgclPS2.a (Medius Game Communication Library)
  - MediusPublicKey\_scei.a
  - General\_Okey\_scei.a (and/or a special title specific security key)
- Sample code for the PlayStation<sup>®</sup>2 (which also requires the DME API in order to run)

#### SCE-RT SDK Medius API Release 2.10

2

- Medius documentation:
  - medius\_overview.pdf
  - medius\_libref.pdf
  - mgcl\_overview.pdf
  - mgcl\_libref.pdf
- The "medius\_readme.txt" document, which provides a brief explanation of how to deploy the various Medius servers.
- The "medius\_changes.txt" document, which lists behavior and API changes since the last release. For example, if upgrading from version 2.7 to version 2.9, you can refer to this file for a quick listing of any changes between the two versions.

Although the Medius Lobby Server executables can be enabled to work with a database versus a "simulated" mode, you must request database setup instructions directly from scert-support@scea.com. This database installation requires a licensed Oracle 9i Database Server (which is currently not offered through SCEA), preferably on a dedicated machine.

## **General Steps in Executing Medius API Function Calls**

The Medius API uses a generalized 'request/response' message protocol when communicating with the Medius platform. The following steps provide an example of how to make a generic Medius function call:

1. Create an instance of a 'request' message data structure and populate the fields (it is recommended that you use memset() to set the structure to '0' and/or initialize each field to some value). All request message data structures are defined in mediustypes.h. Note that every request structure has a MessageID field. This can be populated by calling MediusCreateMessageID() or by using your own numbering scheme.

**Note:** The *MessageID* you assign allows you to match a response message from the Medius platform to a given request message. If your application utilizes a custom internal message queue that may or may not represent 'state' in your application, using your own numbering scheme will help identify and categorize the various messages. The SCE-RT samples usually just set this field to "1". It is up to each application to determine if they need any intrinsic value defined in the *MessageIDs*.

- 2. Call the appropriate Medius API function. Be sure to pass in a populated request message data structure and specify a callback function (if a response message is expected from the Medius platform). If the response is not necessary, NULL can be supplied for the callback function pointer.
- 3. Every Medius API function returns a *MediusErrorCode*. If *MediusErrorNone* is not returned, your application should be prepared to handle the current error condition. 'Common error' results are as follows:
  - a. **MediusErrorNotInitialized (-15)** The Medius client library has not been initialized. Call **MediusInitialize()** before making any other Medius API call.
  - b. **MediusErrorNotConnected (-16)** Either you have not called **MediusConnect()** or your connection to the MLS or MAS has been closed. Your application should go back to a reconnection state.
  - c. **MediusErrorSendingMessage (-5)** Most likely, you have an SCE-RT client library mismatch. Contact SCE-RT developer support (scert-support@scea.com) to get this resolved.

**Note:** If you do receive an error code, the functions described below may help interpret the code's meaning:

- a. **MediusGetErrorCodeString()** Returns a text string description of the *MediusErrorCode* received. This function can help with the application's UI when relaying error conditions back to the online player.
- b. **MediusGetLastNetUpdateError()** Retrieves the most recent DME **NetUpdate()** error. This may provide more low-level error condition information if **MediusUpdate()** failed (because the Medius layer is built upon the DME layer).
- c. MediusGetCallbackStatusString() Returns a text string description of a MediusCallbackStatus error.
- 4. **NetGetNetUpdateErrors()** This function fills out a **NetUpdateErrors** structure with extended error information on a per-connection index basis. When the client receives a 'response' message from the Medius platform, the callback function specified in step #2 above will be invoked. Access to the response message is provided as an input parameter to the callback function. You can extract fields from this response message data structure and process as needed.
- 5. Every response message data structure has a field named *StatusCode*. This field will always be populated with one of the values declared in the **MediusCallbackStatus** enumeration type defined in mediustypes.h. The *StatusCode* will notify the application of the success or failure of a request.

4

Common StatusCode results that any response message may generate are:

- a. MediusSuccess (0) The request was successful.
- MediusPlayerNotPrivileged (-989) The application attempted to call a Medius API function before the player's session has been fully authenticated (see "Establishing an Authenticated State").
- c. **MediusWMError (-991)** This is generally a Medius platform server-side error condition. Contact SCE-RT developer support (scert-support@scea.com) if you experience these (they are usually caused by a server configuration issue).
- d. MediusDBError (-988) The Medius platform you are communicating with has the Medius Database connection disabled, or it is having problems communicating with the Medius database. Contact SCE-RT developer support (scert-support@scea.com) for help resolving this error.

Example: Log in using an existing account with the Medius Authentication Server

```
MediusTypeAccountLoginCallback MyAccountLoginHandler(
 MediusAccountLoginResponse*pThisPacket, // Response Message
 void* pUserData) // Pointer to UserData available during callback
  printf("Response to MessageID %s", pThisPacket->MessageID);
  if (pThisPacket->StatusCode != MediusSuccess)
    printf("Account Login Failed\n");
  }
  else
  {
    printf("Account Login Succeeded\n");
  return;
}
void MyAccountLogin()
  MediusErrorCode retVal;
   // Populate request message data structure
  MediusAccountLoginRequest stAccountLoginRequest;
  memset(&stAccountLoginRequest, 0, sizeof(MediusAccountLoginRequest));
   // We can use either MediusCreateMessageID() or our own
   // numbering scheme.
   strcpy(stAccountLoginRequest.MessageID,"1");
   // Set the Session Key as retrieved from the session begin response
   strcpy(stAccountLoginRequest.SessionKey, g szSessionKey);
      // Set AccountName and AccountPassword
   strcpy(stAccountLoginRequest.AccountName, g szAccountName);
   strcpy(stAccountLoginRequest.Password, g szPassword)
   // Execute and send the Account Login Request
   retVal = MediusAccountLogin(&stAccountLoginRequest,
                                MyAccountLoginHandler,
                                NULL); // No UserData being set
   if (retVal != MediusErrorNone)
   // Return Error Message
```

```
// Call MediusUpdate() until a response message is received via the
// callback handler. Call MediusUpdate() every frame if possible,
// and definitely ASSERT() if it takes longer than 14 seconds
// between MediusUpdate() calls (more information discussed later in
// the Medius Overview documentation).


// If you call MediusUpdate() in a while loop in this function, this will
// block the application from doing other activities (like animating a
// UI); therefore, it is recommended that you build a state machine so
// that the application can do other activities while waiting for a
// pending response message to a given request message.

return;
}
```

## **Connecting to the Medius Platform**

Figure 1 is a high-level view of the sequence of operations that must be performed to initiate a Medius connection. Subsequent sections will refer to this diagram.

Figure 1: Initial Medius Connection Process



#### **Initializing the Medius Client Library**

You must initialize the Medius client library before proceeding with any other Medius API calls. The Medius functions associated with the initialization of Medius resources and the cleaning up/freeing of Medius resources are as follows:

• MediusInitialize() – Initializes Medius client library

MediusInitializeBare()
 Initializes Medius client library (bare version)

MediusClose()
 Uninitializes Medius client library

MediusCloseBare()
 Uninitializes Medius client library (bare version

If you attempt to execute a Medius function before initializing the Medius client library (or after a **MediusClose()**), a **MediusErrorNotInitialized (-15)** *MediusErrorCode* value will be received. .

#### MediusInitialize() vs. MediusInitializeBare()

The Medius client library utilizes the messaging services provided by the DME library. Therefore it is necessary to initialize the DME by calling **NetInitialize()** before connecting to the Medius platform. Perform initialization in one of the following two ways:

- Call **MediusInitialize()** to initialize the Medius client library. An internal call to **NetInitialize()** initializes the DME library as well.
- Call NetInitialize() to initialize the DME library first, then call MediusInitializeBare() to separately
  initialize the Medius client library. SCE-RT recommends this approach because it provides greater
  flexibility.

#### MediusInitializeInParams

Most Medius API calls require the registration of a callback function to handle response messages sent from the Medius platform. Using callback functions gives you total control over how to process the data that is returned. The callback functions you assign as part of the **MediusInitializeInParams** (or **MediusInitializeBareInParams**) structure when calling **MediusInitialize()** (or **MediusInitializeBare()**) can easily be changed later. Simply calling the appropriate **MediusReassign\*()** function will change the callback. If your application does not require a particular callback, set the callback function to NULL.

#### Notes about MediusInitializeInParams:

- MediusTypeGenericChatFwdMessageCallback Callback triggered when another user calls MediusSendGenericChatMessage().
- MediusTypeBinaryFwdMessageCallback Callback triggered when another user calls MediusSendBinaryMessage().
- MediusTypeAddToBuddyListFwdConfirmationRequestCallback Callback triggered when another user calls MediusBuddyAddConfirmation().
- MediusTypeErrorMessageCallback Callback triggered when the Medius platform issues an Error Message. Error messages are rarely issued.
- MediusTypeReassignGameMediusWorldIDCallback Callback triggered when the current game's MediusWorldID has changed (A host migration, for example, will trigger this callback).

#### MediusInitializeOutParams

This is the output response structure for **MediusInitialize()** (or **MediusInitializeBare()**). The *ErrorCode* field indicates whether initializing the Medius client library succeeded or failed.

#### MediusClose() vs. MediusCloseBare()

To clean up/free all Medius resources after initialization, call **MediusClose()**. Typically, you call this before exiting the application and/or when the user has exited an online game and no longer needs Medius functionality.

Match the calls as follows:

- Call MediusClose() if you previously called MediusInitialize().
- Call MediusCloseBare() if you previously called MediusInitializeBare().

#### Sample - Initializing the Medius API

```
void MyGame MediusInitialize()
   // -----
   // Initialize the MEDIUS API
   // -----
   MediusErrorCode result;
   MediusInitializeBareInParams inParams;
   MediusInitializeBareOutParams outParams;
   memset(&inParams, 0, sizeof(MediusInitializeBareInParams));
   memset(&outParams, 0, sizeof(MediusInitializeBareOutParams));
   inParams.MyChatFwdMessageCallback = MyChatFwdMessageCallback;
   inParams.MyBinaryFwdMessageCallback = NULL;
   inParams.MyAddToBuddyListFwdConfirmationRequestCallback = NULL;
   inParams.MyErrorMessageCallback = MyErrorMsgCallback;
   inParams.MyReassignGameMediusWorldIDCallback =
       MyReassignGameMediusWorldIDCallback;
   // -----
   // Medius Initialize Bare
   // -----
   result = MediusInitializeBare(&inParams, &outParams);
   if (result)
       printf("App:[%s][%d]MediusErrorCode:'%d'", __FILE__, __LINE__, result);
   }
   return;
}
```

## Connecting to the MAS

A client must register and authenticate with the Medius platform before it can fully utilize "lobby" technology. To be fully logged onto the Medius platform, the following four steps must be completed:

- 1. Make initial connection to the Medius Authentication Server (MAS).
- 2. Begin a "session" with the Medius platform.
- 3. Establish an authenticated state (account login).
- 4. Disconnect from MAS, and reconnect to the Medius Lobby Server (MLS).

Medius functions used in this section:

- MediusSetDefaultConnectInfo()
- MediusConnect()
- MediusDisconnect()
- MediusSessionBegin()
- MediusSessionEnd()
- MediusVersionClient()
- MediusGetBuildTimeStamp()
- MediusVersionServer()

- MediusConnect() helper function
- Connects to the Medius server
- Disconnects from the Medius server
- Starts a Medius session
- Ends a Medius session
- Retrieves Medius client version information
- Retrieves Medius client build timestamp information
- Requests Medius server version information

#### Making the Initial Connection to the MAS

The sequence for initiating a MAS connection is as follows:

- 1. Call MediusInitialize() or MediusInitializeBare(), as described in the previous section.
- 2. Create an instance of the **MediusConnectInParams** structure:
  - a. memset() the structure to '0'.
  - b. Initialize MediusConnectInParams's ConnectInfo field with MediusSetDefaultConnectInfo(). Note the following about MediusSetDefaultConnectInfo()'s parameters:
    - The first parameter is a returned populated **NetConnectionInfo** needed by the initial **MediusConnect()** call to the MAS.
    - Always set pSessionKey to NULL for initial MAS connections.
    - Set *pServerIP* to the IP address of the MAS (perform a DNS lookup on the URL to obtain the IP address).
    - Set ServerPort to the port number on the MAS server (10075 is default for production MAS servers).
    - Always set WorldID to 1.
  - c. Set *MaxClientsPerConnection* to a number between 0 and 256 (This must be set to *MaxPlayersPerChannel* in medius.txt (256 default). Medius.txt is used by the MLS server to define the max number of clients per chat-channel).
  - d. Set MyConnectCallback to a callback function of type MediusTypeConnectCallback. Doing so ensures that MediusConnect() will operate as a non-blocking function call. Using MediusConnect() in a blocking fashion is no longer supported as of the SCE-RT 2.9 Release.
  - e. Set pfRemoteClientConnectCallback to NULL.
  - f. Set pfRemoteClientDisconnectCallback to NULL.

**Note 1:** Anytime you execute non-blocking function calls (which all Medius API calls are), you will need to define a state-machine to represent your current state (in this case 'lobby state'). This will allow the program to process other application-level tasks while waiting for a response message from the Medius platform indicating the success or failure of your request. Be sure that your state-machine manages calls to **MediusUpdate()** each frame until the callback is received. Based upon the success or failure of the request call, transition through your application's state-machine to determine what to do next. The SCE-RT sample 'DmePoolBalls' attempts to build up one such state-machine, but you probably will define your own based on your application needs. The SCE-RT++ Wrapper SDK, new to the SCE-RT v2.9 official release, is a fully qualified Medius state-machine. The SCE-RT++ Wrapper is included in the samples directory.

3. Call **MediusConnect()**, referencing the appropriate Medius Authentication Server (MAS) *IP/Port/WorldID* address information as described in the **MediusConnectInParams** set above. The client's Medius connection index (*ConnectionIndex*) will be set to a value between (0..n) as seen in **MediusConnectOutParams**.

4. Verify the return code for **MediusConnect()** was set to *MediusErrorNone*. Note that the application's state-machine is responsible for 'timing out' **MediusConnect()**'s pending response callback (30 seconds is a common threshold). Be sure to call **MediusUpdate()** while your application is waiting for the response callback. If a timeout occurs, the application's state-machine should transition to a reconnect state.

**Note 2:** If **MediusConnect()** failed to create a socket and establish a connection with a MAS socket, then **MediusConnect()** will return **MediusErrorConnecting (-2)** immediately upon returning. If *MediusErrorNone* was returned, the application will be in a state where it is waiting for the connect callback to be triggered. The connect callback will occur after a number of synchronizing 'handshakes' have taken place. As stated above, if your connect timeout threshold was exceeded, present the user an error message such as, "Connection timed out and/or failed to connect to this address", then transition to a state where you can attempt to reconnect.

5. Once the connect callback is triggered, verify that the *Connection* pointer (*HDME* handle to the *DME*) is != NULL. If the *Connection* pointer is == NULL, then there was an error connecting to the MAS (that is, the synchronizing handshakes with the MAS did not resolve into a connected state). Set "success" or "failure" to your state-machine here. If the result is "success", there is now a connection to the MAS and you are ready to start a Medius session.

**Note 3:** Currently, there is no descriptive information (response message data structure) associated with **MediusTypeConnectCallback**. Nonetheless, you can still determine why a connection failed by calling **MediusGetLastNetUpdateError()** and/or by looking at MAS log files. If **MediusConnect()** returns *MediusErrorNone*, you know that at least a socket connection was made. If the *Connection* pointer is == NULL in the connect callback, it may be associated with a condition such as "trying to connect to a secure server while having no client security key setup". If you receive errors such as this, call SCE-RT developer support.

#### Sample - Connecting to the MAS

```
{
   MediusErrorCode result;
   MediusConnectInParams inParams;
   MediusConnectOutParams outParams;
   memset(&inParams, 0, sizeof(MediusConnectInParams));
   memset(&outParams, 0, sizeof(MediusConnectOutParams));
   // -----
   // Set MediusConnectInParams
   MediusSetDefaultConnectInParams(&inParams.ConnectInfo, // NetConnectInfo (Out)
       NULL, // For initial connection pass in NULL for pSessionKey
       "www.mygame.com", // Authentication ServerIP
       10075,
                         // Authentication ServerPort
       1);
                         // Authentication WorldID (1 by default)
   inParams. MaxClientsPerConnection = 256;
                                          // Max Clients per Chat-Channel
   inParams.MyConnectCallback = MyConnectCallback MAS; // Sets as non-blocking
   inParams.pfRemoteClientConnectCallback = NULL;
   inParams.pfRemoteClientDisconnectCallback = NULL;
   memset(&inParams.ConnectInfo.ServerKey,0,sizeof(RSA KEY)); //Security Disabled
   // Medius Connect (MAS)
   // -----
   result = MediusConnect(&inParams, &outParams, NULL);
   if (result != MediusErrorNone)
       printf("App:[%s][%d]MediusError:'%d'\n", __FILE__, __LINE__, result);
   // -- OutParams --
   printf(" OutParams->\n");
   printf(" NetErrorCode:
                                   '%d'\n", outParams.ErrorCode);
   // Wait for MediusConnect to complete
   // =============
   do
   {
       // Need timeout logic
       MediusUpdate();
   } while (g RtLobby.m bConnectCallbackComplete MAS == FALSE);
   return;
```

SCE Confidential March 2005

}

#### Starting a Session

Once there is a connected state with the MAS, begin a "session" with the Medius platform by calling **MediusSessionBegin()**. The MAS will then manage the creation of a 'player object' with the Medius Universe Manager (MUM). If the transaction was successful, a unique session key will be generated and returned to the client in the *SessionKey* field of the **MediusSessionBeginResponse** message. This session key associates the client with the 'player object' managed by the MUM. This session key must also be used in all subsequent Medius 'request' messages until the user entirely disconnects from the Medius platform.

**Note:** A session may end by either calling **MediusSessionEnd()** (usually followed by **MediusDisconnect()**) or by a case where the client had not called **MediusUpdate()** within a timely fashion. The Medius platform typically will end a 'player object' if **MediusUpdate()** had not been called for 30 seconds (though this 30 second interval is configurable the Medius servers). **MediusUpdate()** (even if no data is being transmitted) services the connection to the Medius platform. If a client's 'player object' ends or times out, the client will need to reconnect to the MAS and re-authenticate.

The sequence for initiating a "session" is as follows:

- 1. Create an instance of the **MediusSessionBeginRequest** structure.
  - a. memset() the structure to '0'.
  - b. Set MessageID to a value of your numbering scheme (if needed).
  - c. Set ConnectionClass to a MediusConnectionType.

**Note:** Based on whatever network hardware device configuration you selected during the network combination screen, match that type with **MediusConnectionType**. This information is valuable when determining "how many Modem users are there versus Broadband users?" This information is available on the MUM server.

- 2. Call MediusSessionBegin() with the respective request message and callback.
- 3. When the **MediusSessionBeginResponse** message is received, if *StatusCode*=**MediusSuccess** then save off the *SessionKey* for later use.

If *StatusCode!*=**MediusSuccess**, be sure to transition through your lobby state-machine to handle the current error condition. Possible error conditions (additional to the common set):

a. **MediusBeginSessionFailed (-1000)** – The Medius platform could not create a session for the current player. Be sure you are connected to the MAS server.

#### Sample - Starting a Session

```
// -----
// Starting a Session
// -----
// (Warning) - This code sample is not production quality. It does not manage
// an application level lobby 'State-Machine'. See SCE-RT samples for a more
// complete sample
void MySessionBeginCallback(MediusSessionBeginResponse* pResponse,
                          void* pUserData)
{
   switch (pResponse->StatusCode)
   case MediusSuccess:
       // Save of the 'player object's SessionKey
       strncpy(g RtLobby.m SessionKey,
               pResponse->SessionKey,
               SESSIONKEY MAXLEN-1);
       g RtLobby.m SessionKey[SESSIONKEY MAXLEN-1]='\0';
       break:
    default:
       break;
```

```
}
   g RtLobby.m bSessionBeginComplete = TRUE;
}
void MyGame SessionBegin()
   MediusErrorCode result;
   MediusSessionBeginRequest request;
   memset(&request, 0, sizeof(MediusSessionBeginRequest));
   // -----
   // Set MediusSessionBeginRequest
   // -----
   strcpy(request.MessageID, "1");
   request.ConnectionClass = Ethernet; // Todo: set based on "eznetcfg"
   // -----
   // Medius Session Begin
   // -----
   result = MediusSessionBegin(&request, MySessionBeginCallback, NULL);
   if (result != MediusErrorNone)
      printf("App:[%s][%d]MediusError:'%d'\n", FILE , LINE , result);
   }
   // ===========
   // Wait for SessionBegin to complete
   do
      // Need timeout logic
      MediusUpdate();
   } while (g RtLobby.m bSessionBeginComplete == FALSE);
   return:
}
```

#### **Version Information and Build Timestamps**

The Medius API provides methods to gain access to the following information:

- Medius client library version
- Medius client library build time stamp
- Currently connected MAS version or MLS version

This information is very helpful when contacting SCE-RT developer support (scert-support@scea.com) and it is highly recommended that you integrate it in your application's code base.

To retrieve the version of the Medius client library, pass in a string of 64 characters to **MediusVersionClient()** that will then be populated with the version string.

To retrieve the build timestamp of the Medius client library, pass in a string of 64 characters to **MediusGetBuildTimeStamp()** that will then be populated with the build timestamp string.

To retrieve the currently connected version of the MAS or MLS, instantiate and populate a **MediusVersionServerRequest** structure for use with **MediusVersionServer()**. The Medius platform (MAS or MLS) will then send a **MediusVersionServerResponse** message to the client with populated server version information.

#### Sample - Version Information and Build Timestamps

```
// -----
// Version Information and Build Timestamps
// -----
MediusVersionClient(g_RtLobby.m_MediusVersion);
MediusGetBuildTimeStamp(g RtLobby.m MediusBuildInfo);
NetGetClientVersion(g RtLobby.m DmeVersion);
NetGetBuildTimeStamp(g RtLobby.m DmeBuildInfo);
printf("->Medius Client Version: '%s'\n", g_RtLobby.m_MediusVersion);
void MyGetMediusServerVersionCallback (MediusVersionServerResponse* pResponse,
                             void* pUserData)
{
   switch (pResponse->StatusCode)
   case MediusSuccess:
      // -----
      // Get Medius Server Version was a Success
      // -----
      printf("->MAS or MLS Server Version: '%s'\n", pResonse->VersionServer);
      break:
   default:
     break;
   g RtLobby.m bGetMediusServerVersionComplete = TRUE;
   return:
}
void MyGame GetMediusServerVersion()
   MediusErrorCode result;
  MediusVersionServerRequest request;
   memset(&request, 0, sizeof(MediusVersionServerRequest));
   // -----
   // Set MediusVersionServerRequest
   // -----
   strcpy(request.MessageID, "1");
   strcpy(request.SessionKey, g RtLobby.m SessionKey);
   // -----
   // Medius Server Version
   // -----
   result = MediusServerVersion(&request, MyGetMediusServerVersionCallback, NULL);
   if (result != MediusErrorNone)
      printf("App:[%s][%d]MediusError:'%d'\n", __FILE__, __LINE__, result);
```

## **Establishing an Authenticated State**

Before establishing an Authenticated State (account login), first refer to both the "Platform Requirement Functionality" section (discussing usage policy, privacy policy, and announcements) and the "Co-location" section (discussing Medius platform deployment strategies). Your application may bypass this functionality during early development, but you will need to take these items into consideration before your application is submitted to QA/Format and Production.

Once a 'session' (player object) is created, the session needs to be in an authenticated state. You can register a new account (or log in with an existing account) or have the client establish an anonymous login (applications will typically do one or the other). If the account login (or anonymous login) is successful, the session will then be in an authenticated state.

The Medius functions associated with establishing an authenticated state are as follows:

- MediusAccountRegistration()
- MediusAccountLogin()
- MediusAnonymousLogin()
- MediusAccountLogout()
- Creates a new account
- Logs into an account
- Anonymous login (account exists for the lifetime of the session)
- Logouts out of account

#### Registering a New Account

Populate the **MediusAccountRegistrationRequest** structure and call **MediusAccountRegistration()**. Currently only *AccountName* and *Password* are required fields. Account names must be unique. It is possible that some game applications will hide much of the registration process from the player. When registering a new Medius Account, it is required that the username and password be Unified Community (UC) compliant.

#### **Unified Community**

The Unified Community feature set for SCE-RT was born out of the necessity to bring online titles into compliance with the efforts and mandate of the SCEI Corporate Initiative Identity Federation (IDF) for unifying accounts across all game universes, and ultimately providing a central lobby for gamers that will provide community, news, etc.

The key to any unified community comes down to a simple core requirement – a standardized account name and password specification.

All titles that adhere to the specification for a UC-compatible account name and password will ultimately be compliant with the SCE-RT UC, and eventually the IDF. SCE-RT has created this requirement without changing any of the existing APIs for online game integration.

In addition, having a centralized account, SCE-RT now provides for a central buddy list, ignore list and cross-title instant messaging. Again, there are no API changes required to implement these features, however there will be some UI considerations for your development teams. You should

consult closely with SCE-RT (scert-support@scea.com) to discuss how to implement these features from a UI perspective.

#### **Encoding**

UTF-8 – In this instance, the printable subset of UTF-8 commonly known as US-ASCII with certain exclusions

#### **Account Name Specification**

```
Character Set – A-Z, a-z, 0-9, (dash) -, (period) ., (underscore) _
Length – 5 characters min. (5 + NULL), 16 characters max. (15 + NULL)
Case – Account names are case insensitive
```

#### **Password Specification**

```
Character Set – A-Z, a-z, 0-9, (dash) -, (period) ., (underscore) _
Length – 4 characters min. (4 + NULL), 16 characters max. (15 + NULL)
Case – Passwords are case insensitive
```

All other characters are restricted. If *AccountName* and *Password* specifications are not met when connecting to a 2.10 SCE-RT server, **MediusAccountRegistrationRequest** will fail.

The sequence for registering a new account is as follows:

- 1. Create an instance of the MediusAccountRegistrationRequest structure.
  - a. memset() the structure to '0'.
  - b. Set MessageID to a value of your numbering scheme (if needed).
  - c. Set SessionKey to the value you saved from MediusSessionBeginResponse.
  - d. Set AccountType to a MediusAccountType (currently only MediusMasterAccount is supported).
  - e. Set AccountName to the string provided by the client.
  - f. Set Password to the string provided by the client.
- 2. Call MediusAccountRegistration() with the respective request message and callback.
- 3. If StatusCode=MediusSuccess when the MediusAccountRegistrationResponse message is received, the account has been created and you can proceed to call MediusAccountLogin().

Other notes about MediusAccountRegistrationResponse:

- a. AccountID Primary key associated with player's account information in the Medius database. Numerous Medius API calls use the AccountID to direct messages to other clients and request client information (search for AccountID in the Medius API for further uses). AccountID will always be > 0 for accounts that are persisted in the Medius database.
- 4. If StatusCode!=MediusSuccess, be sure to transition through your lobby state-machine to handle the current error condition. If you are having trouble registering, be sure that your AccountName and Password are Unified Community-compliant. Possible error conditions (in addition to the common set):
  - a. MediusAccountAlreadyExists (-999) AccountName was not unique.

#### **Account Login**

A player must log into an account (thus setting the user's session to an authenticated state) to play online. Any player that does not have an existing account must register a new account. A player that already has an account can bypass registration and call **MediusAccountLogin()** directly.

The sequence for performing an account login is as follows:

- 1. Create an instance of the **MediusAccountLoginRequest** structure.
  - a. **memset()** the structure to '0'.
  - b. Set MessageID to a value of your numbering scheme (if needed).

17

- c. Set SessionKey to the value you saved from MediusSessionBeginResponse.
- d. Set *AccountName* to the string provided by the client.
- e. Set Password to the string provided by the client.
- 2. Call **MediusAccountLogin()** with the respective request message and callback.
- 3. If StatusCode=MediusSuccess when the MediusAccountLoginResponse message is received, the login to the Medius platform is successful and the session will be in an authenticated state. Other notes about MediusAccountLoginResponse:
  - a. AccountID (Value > 0) Same value from MediusAccountRegistrationResponse.
  - b. **AccountType** As set from **MediusAccountRegistrationRequest**.
  - c. MediusWorldID This is the default 'Chat Channel' ID reserved upon the pending connection to the MLS. After the connection to the MLS is complete, you can call MediusGetChannelInfo() to get information about the currently connected chat channel.
  - d. ConnectInfo (Very Important) This is the NetConnectionInfo needed to connect to the MLS, which is the next step.
- 4. If StatusCode!=MediusSuccess, be sure to transition through your lobby state-machine to handle the current error condition. Possible error conditions (in addition to the common set):
  - a. MediusLoginFailed (-995) General account login failure.
  - b. MediusAccountNotFound (-998) The account name was invalid. User should be prompted to either register a new account or to attempt to log in with a new account name.
  - c. MediusInvalidPassword (-978) The password was invalid to a valid account name.
  - d. MediusAccountLoggedIn (-997) Either someone has already logged in with this account or the player ungracefully disconnected from the Medius platform and must wait approximately two minutes for the authenticated session (player object) to completely timeout.
  - e. MediusFilterFailed (-967) Login failed because the AccountName did not pass the automatic vulgarity filter check.

If a user decides to log in with a different account or wishes to create a new account after their session has already been authenticated, they will need to call MediusAccountLogout() to set the session back to an unauthenticated state. Once back in an unauthenticated state, the application should disconnect from the MLS and reconnect to the MAS (if not already connected to the MAS). However, when gracefully disconnecting from the Medius platform (in general), you do not need to worry about calling MediusAccountLogout() because the MediusSessionEnd() call will fully log out the player (see "Disconnecting From the Medius Platform").

#### Sample - Account Login and Registering a New Account

```
// -----
// Account Login and Registering a New Account if 'AccountNotFound'
// -----
// (Warning) - This code sample is not production quality. It does not manage
// an application-level lobby 'State-Machine'. See SCE-RT samples for a more
// complete sample
void MyAccountCreateCallback (MediusAccountRegistrationResponse* pResponse,
                       void* pUserData)
   switch (pResponse->StatusCode)
   case MediusSuccess:
      // Account registration was a success
      break;
   default:
      break;
```

```
g RtLobby.m bAccountCreateComplete = TRUE;
}
void MyGame AccountCreate()
   MediusErrorCode result;
   MediusAccountRegistrationRequest request;
   memset(&request, 0, sizeof(MediusAccountRegistrationRequest));
   // -----
   // Set MediusAccountRegistrationRequest
   // -----
   strcpy(request.MessageID, "1");
   strcpy(request.SessionKey, g RtLobby.m SessionKey);
   request.AccountType = MediusMasterAccount;
   strcpy(request.AccountName, "MyAccountName");
   strcpy(request.Password, "MyAccountPassword");
   // -----
   // Medius Account Registration
   // -----
   result = MediusAccountRegistration(&request, MyAccountCreateCallback, NULL);
   if (result != MediusErrorNone)
      printf("App:[%s][%d]MediusError:'%d'\n", __FILE__, __LINE__, result);
   }
   // Wait for Account Registration to complete
   do
      // Need timeout logic
      MediusUpdate();
   } while (g RtLobby.m bAccountCreateComplete == FALSE);
void MyAccountLoginCallback(MediusAccountLoginResponse* pResponse,
                       void* pUserData)
   switch (pResponse->StatusCode)
   case MediusSuccess:
      // -----
      // Account login was a success; therefore, save the
      // NetConnectInfo to the MLS for the upcoming redirected
      // MediusConnect() call to the MLS.
      // You may want to save the MediusWorldID here also - this is
      // the MediusWorldID of the default chat channel that has been
      // reserved for you upon a successful connection to the MLS.
      // -----
      memcpy( &(g RtLobby.m LobbyConnectInfo),
             & (pResponse->ConnectInfo),
             sizeof(g RtLobby.m LobbyConnectInfo));
      break;
   case AccountNotFound:
```

```
// -----
       // Account Create Request
       // -----
      MyGame AccountCreate();
   default:
      break;
   g RtLobby.m bAccountLoginComplete = TRUE;
   return;
}
void MyGame AccountLogin()
   MediusErrorCode result;
   MediusAccountLoginRequest request;
   memset(&request, 0, sizeof(MediusAccountLoginRequest));
   // -----
   // Set MediusAccountLoginRequest
   // -----
   strcpy(request.MessageID, "1");
   strcpy(request.SessionKey, g RtLobby.m SessionKey);
   strcpy(request.AccountName, "MyAccountName");
   strcpy(request.Password, "MyAccountPassword");
   // -----
   // Medius Account Login
   // -----
   result = MediusAccountLogin(@request, MyAccountLoginCallback, NULL);
   if (result != MediusErrorNone)
      printf("App:[%s][%d]MediusError:'%d'\n", FILE , LINE , result);
   }
   // ===========
   // Wait for Account Login to complete
   // ==========
   do
   {
      // Need timeout logic
      MediusUpdate();
   } while (g RtLobby.m bAccountLoginComplete == FALSE);
   return:
}
```

#### **Anonymous Logins**

There is an alternative to the traditional "register/login" method. Many game applications will not perform any type of data collection. These applications will instead use "anonymous" logins. An anonymous login does not require the above-mentioned **MediusAccountRegistration()** process. Rather, the **MediusAnonymousLogin()** should be performed after **MediusSessionBegin()**. The response will be very similar to that of a normal **MediusAccountLogin()**. Connection details for the Medius Lobby Server are provided, along with a temporary *AccountID* (< 0) that can be used for the life of the session.

There are several key limitations with anonymous logins:

- No database storage
- All account information lasts only for the client session
- No ladder support

- No buddy list support
- No clan support

The sequence for performing an anonymous account login is as follows:

- 1. Create an instance of the **MediusAnonymousLoginRequest** structure.
  - a. memset() the structure to '0'.
  - b. Set MessageID to a value of your numbering scheme (if needed).
  - c. Set SessionKey to the value you saved from MediusSessionBeginResponse.
  - d. Set SessionDisplayName to the string provided by the client. This will be the anonymous player's name for as long as they are connected. Does not need to be unique; therefore, you may potentially see other players with the same screen name.
  - e. Set SessionDisplayStats to an (optional) string provided by the application. Each application will decide if and how they wish to use this field. For example, if your application has custom avatars that represent each client in the lobby, you could encode that information here
- 2. Call MediusAnonymousLogin() with the respective request message and callback.
- 3. If StatusCode=MediusSuccess when the MediusAccountLoginResponse message is received (note that MediusAnonymousLogin() shares the same callback and response message type as MediusAccountLogin()), the login to the Medius platform is successful and the session will be in an authenticated state.

Other notes about MediusAccountLoginResponse:

- a. AccountID (Value < 0) Temporary value that exists for the lifetime of the player's session.
- b. AccountType Ignore (set to MediusMasterAccount).
- c. MediusWorldID This is the default 'Chat Channel' ID reserved upon the pending connection to the MLS. After the connection to the MLS is complete, you can call **MediusGetChannelInfo()** to get information about the currently connected chat channel.
- d. ConnectInfo (Very Important) This is the NetConnectionInfo needed to connect to the MLS, which is the next major step.
- 4. If *StatusCode!*=**MediusSuccess**, be sure to transition through your lobby state-machine to handle the current error condition. Possible error conditions (in addition to the common set):
  - a. MediusLoginFailed (-995) General anonymous login failure.
  - b. **MediusFilterFailed (-967)** Login failed because the *SessionDisplayName* did not pass the automatic vulgarity filter check.

#### **Reconnecting to the MLS**

Once the 'session' (player object) is in an authenticated state you can disconnect from the MAS, reconnect to the MLS, and fully utilize the "lobby" technology that Medius provides.

All **Notes (1–4)** in the 'Connecting to the MAS' section also apply to establishing a connection to the MLS. The sequence for reconnecting to the MLS is as follows:

- 1. Call MediusDisconnect() to disconnect from the MAS (this disconnects the Medius connection).
- 2. Create an instance of the **MediusConnectInParams** structure:
  - a. memset() the structure to '0'.
  - b. Set ConnectInfo to the NetConnectionInfo you saved from MediusAccountLoginResponse.
  - c. Set MaxClientsPerConnection to a number between 0 and 256 (This must be set to MaxPlayersPerChannel in medius.txt (256 default). Medius.txt is used by the MLS server to define the max number of clients per chat-channel).
  - d. Set *MyConnectCallback* to a callback function of type **MediusTypeConnectCallback**. By doing so, **MediusConnect()** will operate as a non-blocking function call. Using **MediusConnect()** in a blocking fashion is no longer supported as of the SCE-RT 2.9 Release.

- e. Set pfRemoteClientConnectCallback to NULL.
- f. Set pfRemoreClientDisconnectCallback to NULL.
- 3. Call **MediusConnect()** referencing the appropriate Medius Lobby Server (MLS) *IP/Port/WorldID* address information as described in the *MediusConnectInParams* set above.
- 4. Verify the return code for **MediusConnect()** was set to *MediusErrorNone*. The application's statemachine is responsible for 'timing out' **MediusConnect()** pending response callback (30 seconds is common). Be sure to call **MediusUpdate()** while your application is waiting for the response callback. If a timeout occurs, the application's state-machine should transition to a reconnect state.
- 5. Once the connect callback is triggered, verify that the *Connection* pointer (*HDME* handle to the *DME*) is != NULL. If the *Connection* pointer is == NULL, then there was an error connecting to the MLS (that is, the synchronizing handshakes with the MLS did not resolve into a connected state). Set "success" or "failure" to your state-machine here. If the result is "success", there is a connection to the MLS and you are ready to fully utilize Medius' "lobby" technology.
- 6. **Very Important:** A **MediusConnect()** call to the MLS will place a player in a default 'chat channel'; therefore, the first thing you should do after a connect callback to the MLS returns success is call **MediusUpdateClientState()** with *UserAction* set to the *MediusUserAction* type '**JoinedChatWorld**'. You need to do this even if your application is not aware of chat channels.

**Summary:** At this point the player is fully logged in with the MLS, connected to a default lobby chat channel (whether your application utilizes chat functionality or not), and can proceed to use the full suite of Medius functions. The next section discusses the issues involved with both disconnecting and being disconnected from the Medius platform. A following section illustrates managing Medius reports to ensure connection to the Medius platform is maintained.

#### Sample - Connecting to the MLS

```
// -----
// Connecting to the MLS
// (Warning) - This code sample is not production quality. It does not manage
// an application-level lobby 'State-Machine'. See SCE-RT samples for a more
// complete sample
void MyConnectCallback MLS(HDME Connection, void* pUserData)
{
   if (Connection != NULL)
       // (Success)
       // As a design note, pUserData could set state in your state-machine that
       // flagged success or failure
    }
   g RtLobby.m bConnectCallbackComplete_MLS = TRUE;
   return:
}
MyGame ConnectTo MLS()
   MediusErrorCode result;
   MediusConnectInParams inParams;
   MediusConnectOutParams outParams;
   MediusDisconnectParams dp;
   MediusUpdateUserState state;
   memset(&inParams, 0, sizeof(MediusConnectInParams));
   memset(&outParams, 0, sizeof(MediusConnectOutParams));
   memset(&state, 0, sizeof(MediusUpdateUserState));
```

```
// Disconnect from MAS
   result = MediusSetDefaultDisconnectParams(&dp);
   dp.MyDisconnectCallback = NULL; // NULL is the blocking version
   dp.DisconnectReason = NetDisconnectNormal; //Reason for disconnect
   result = MediusDisconnect( &dp, NULL );
   // -----
   // Set MediusConnectInParams
   // -----
   inParams.ConnectInfo = g_RtLobby.m_LobbyConnectInfo; // Set from
                                                  // AccountLoginReponse
   inParams.MaxClientsPerConnection = 256;
   inParams.MyConnectCallback = MyConnectCallback MLS; // Sets as non-blocking
   inParams.pfRemoteClientConnectCallback = NULL;
   inParams.pfRemoteClientDisconnectCallback = NULL;
   // -----
   // Medius Connect (MLS)
   // -----
   result = MediusConnect(&inParams, &outParams, NULL);
   if (result != MediusErrorNone)
      printf("App:[%s][%d]MediusError:'%d'\n", __FILE__, __LINE__, result);
   // -- OutParams --
   printf(" OutParams->\n");
   printf(" NetErrorCode:
                                 '%d'\n", outParams.ErrorCode);
   // ============
   // Wait for MediusConnect to complete
   do
      // Need timeout logic
      MediusUpdate();
   } while (g_RtLobby.m_bConnectCallbackComplete_MLS == FALSE);
   // *********
   // Note: VERY IMPORTANT TO DO THIS
   // **********
   // Set 'player object' to a state where it is ready to perform 'lobby'
   // functionality.
   strncpy(state.SessionKey, g RtLobby.m SessionKey, SESSIONKEY MAXLEN-1);
   state.SessionKey[SESSIONKEY MAXLEN-1]='\0';
   state.UserAction = JoinedChatWorld; // <</pre>
   MediusUpdateClientState(&state);
   return;
}
```

## **Disconnecting From the Medius Platform**

A client can disconnect gracefully or ungracefully from the Medius platform. Disconnection may be necessary and/or may occur for a number of reasons, including:

- Conclusion of the online game (and possibly returning to the application's offline features)
- Logon with a different account
- The occurrence of a fatal network error
- The need for a PlayStation®2 power cycle

#### **Graceful Disconnects**

The sequence for initiating a graceful Medius platform disconnect is:

- 1. Call **MediusSessionEnd()** to remove the server-side 'player object'.
- 2. Call **MediusDisconnect()** to disconnect from the MLS or MAS. Be sure to specify the **NetDisconnectReason**.

A graceful disconnect from the Medius platform is recommended whenever possible, especially when a client encounters a fatal network error. Instead of requiring the user to power cycle the PlayStation®2, the application should gracefully disconnect (if possible) and allow the user to reconnect with the same information provided initially.

**Note:** A player who disconnects ungracefully (for example, a power cycle due to application lock-up), then attempts to reconnect and perform a **MediusAccountLogin()** will receive a status code indicating *MediusPlayerAlreadyLoggedIn*. The player's account will timeout in approximately 60–90 seconds.

## **Ungraceful Disconnects**

If you are new to the Medius API, you may find that detecting the cause of ungraceful disconnects is sometimes challenging.

After a connection to the MAS or the MLS has been established, you must call **MediusUpdate()** (every frame if possible) to update/service the Medius connection and determine if incoming or outgoing messages need processing. If for some reason you do not call **MediusUpdate()** within 30–45 seconds of a previous call, the MLS or MAS will automatically close your Medius connection.

**Special Note:** SCE-RT client libraries are built for a number of platforms. If you are developing for the PlayStation®2 you must consider that the PlayStation®2 DME client library utilizes a 'high performance counter' on the PlayStation®2 (the MIPS5900 294Mhz timer 'register c0'). This timer utilizes a 32-bit value that fills up within approximately 14 seconds; the software needs the opportunity to reset the timer before it rolls over (that is, calls **NetUpdate()**). Thus, a PlayStation®2 online client must call **MediusUpdate()** within 14 seconds to ensure all internal timing calculations are correct; if not, internal timing functions may become ineffective and undefined behavior may result. Although your application may appear fine, the server-side timeout will occur in 30-45 seconds. For debugging builds, you may have those 30–45 seconds to work with. However, Format/QA release builds must adhere to the14-second rule. It is highly recommended that you wrap/encapsulate the **MediusUpdate()** and **NetUpdate()** functions and let your application keep track of the elapsed time between these calls (with either **NetGetLocalTime()** or your own timing function). If your application detects an elapsed time > 14 seconds then **ASSERT()**.

The following are common reasons why **MediusUpdate()** may not have been called within 14 seconds on a client PlayStation<sup>®</sup>2:

- Hit a break point in the debugger. You have 14 seconds to resume before a disconnect takes place. You may need to devise a creative way to interpret network data in real-time (perhaps visually or in a log file).
- The application is blocking due to a long load time off the DVD. If you find such long load times occurring, you may want to either place MediusUpdate() calls between resource loads or spin off a separate thread during these heavy loads and call MediusUpdate() from there.
   Note: If you end up with two threads that call Medius API (or DME API) functions, note that these APIs are not thread-safe; therefore, it is recommended that your second thread only calls MediusUpdate(). You may need your own semaphore (or state) in your application that prevents Medius or DME API calls from being made in the first thread while the second thread is running.
- Somehow your application reached a state where it is no longer calling MediusUpdate(). As long as your game is online, you must call MediusUpdate(). If your application is "In Game", but you failed to call MediusUpdate(), you may still play your game but your Medius connection will be severed and you will not be able to return to the application's Lobby when the current game has finished.
- If the MLS or MAS has closed your connection (the Medius connection always being a 'TCP socket'), and you call MediusUpdate(), you will see this TTY error message reported from the DME's messaging layer:

RECV/IP: sceInetRecv() failed, error -508, sceINETE\_CONNECTION\_DOES\_NOT\_EXIST, no connection was established or connection has been closed

**MediusUpdate()** will return –10 (*MediusErrorGeneral*) while MLS or MAS log files will report this disconnect as:

00:00:00 TIME\_CHECK World 1, Client 0, timeout value 30000, elapsed time 30 00:00:00 RT\_MSG\_SERVER rt\_msg\_server\_client\_disconnect message: world 1, client 0, reason 4

#### **Server Time**

The **MediusGetServerTime()** function returns the server's local time and time zone from any production server. This includes the Linux versions of the Medius Authentication Server (MAS), Medius Lobby Server (MLS), and the Medius Universe Information Server (MUIS). Getting the server time is currently not available for the Win32 versions of the Medius servers. The time returned is in seconds starting with Jan 1, 1970.

The server time is also sent to the client application via the *TimeStamp* field of a **MediusGenericChatFwdMessage**. This means that any time a chat message is received by the client application, the server time will be available.

#### What is a 'World'?

The SCE-RT SDK is focused on the partition of 'worlds' on any given server (MUM, MAS, MLS, MPS, GS, and peer-to-peer 'hosts'). This allows more optimized bandwidth loading and cost-effective use of server hardware, as multiple applications can run multiple game instances on a single set of servers, depending on the demands of the applications.

An SCE-RT server operates multiple 'worlds' simultaneously, and generally polls each world for activity one-at-a-time. Every world is given equal priority, whether for two users/connections or 256 users/connections.

The Medius API refers to different *WorldID* types, sometimes within the same function, which may cause confusion. The major types of *WorldID*s that you should know about are:

- **MediusWorldID** (lobby world objects "chat channels") This is an index number that refers to a chat channel that is unique across the entire Medius platform infrastructure. No two chat channels can have the same *MediusWorldID*, whether or not they're on the same MLS.
- MediusWorldID (game world objects) This is the same concept as chat channel MediusWorldIDs.
  No two 'game world objects' will ever have the same MediusWorldID, as this is a unique identifier
  for that game's instance represented on the Medius platform. A chat channel and a 'game world
  object' instance may have matching MediusWorldIDs, but this does not reflect any correlation
  between the two worlds, as they are kept and managed in two separate sets of indexes.
- WorldID (DME 'game world') This is the "physical" WorldID a player is actually connected to on either a GS or peer-to-peer 'host'. Traditionally, a server is thought of as having an IP Address and a Port Number. This has been extended into a third dimension with WorldID, where you connect to a discrete 'game world' on the given IP/Port, and cannot directly interact with any other 'game worlds' on the same server.

The next section discusses the various SCE-RT Network Topologies and should help you visualize the concept of 'world' management.

## **Reporting (Maintaining Medius Platform Connections and Objects)**

There are four types of reports: Server Reports, World Reports, Player Reports, and End Game Reports. Each report type is discussed in detail in this section.

The Medius platform relies on a variety of periodic report messages to manage its in-memory object collection database (MUM Object Collections) of online *game server objects*, *game world objects*, and *player objects*. To stress the importance of reporting (because failure to make these update calls and/or reports may result in the Medius platform closing your connections) this section touches upon a number of topics before officially introducing them (such as creating/joining a game, and the MGCL API).


The Medius (and MGCL) functions detailed in this section are:

- MediusUpdate()
- MediusSendWorldReport()
- MediusSendEndGameReport()
- MediusSendPlayerReport()
- MediusUpdateClientState()
- MGCLUpdate()
- MGCLSendServerReport()

- Maintains Medius connection
- Updates game information
- Informs Medius that the game has ended
- Updates player information
- Updates player state
- Maintains MGCL connection
- Updates host information

Depending on whether your application uses a "Client/Server" or a "Peer-to-Peer" network topology, refer to the appropriate diagrams (Figure 2 and/or Figure 3) to help understand the discussion of "Maintaining Medius Platform Connections and Objects":

Figure 2: Maintaining Medius Platform Connections and Objects for "Client/Server" Games



MUM Object Collections (w/ Primary Key) Peer-to-Peer Game Network Topology Game Server Objects (SK) -- (ex. This shows 1 'Host' connected) Game World Objects (MediusWorldID) -- (ex. This shows 1 Game World listed) DΒ MUM Player Objects (SK) -- (ex. This shows 2 users logged in) Lobby World Objects "Chat Channels" (MediusWorldID) MAS MLS MPS -- (ex. This shows 4 default Chat Channels) (CID) ConnectionIndex A = Medius Connection B = MGCL Connection C = DME Peer-to-Peer Connection CID=A CID=B CID=A <u>Sends</u> Server Report Sends PS2 PS<sub>2</sub> World Report Player Report Player Report Client 0 Client 1 P2PHost Session Master DME Game World Collection DME Game World (WorldID) -- (exp. This shows 1 active game running on the "Host") -- (Note: A P2P 'Host' sill only have 1 active game (Game World) running on it)

Figure 3: Maintaining Medius Platform Connections and Objects for "Peer-to-Peer" Games

## **Understanding MUM Game World Objects and DME Game Worlds**

It is important to understand the difference between MUM 'game world objects' and DME 'game worlds'.

#### If a Client/Server Game

- 1. A DME 'game world' is a single instance of a game that resides on a DME Game Server (GS). Thus, a client can only be connected to a single DME 'game world' on a GS at any one time.
- 2. A GS hosts a collection of DME 'game worlds' that are indexed by "WorldID".
- 3. A call to **MediusCreateGame()** causes the MUM to manage the transaction of creating/starting a 'game world' on a GS.
- 4. If the transaction was successful, a corresponding 'game world object' is created on the MUM and a "MediusWorldID" is generated to index this object.
- 5. If no players join this game within 120 seconds, the 'game world object' will automatically timeout. The user who called **MediusCreateGame()** must still call **MediusJoinGame()** to join the DME 'game world' they just created.
- 6. A MUM 'game world object' encapsulates three things: Information about an active DME 'game world' running on a GS; connection information to the 'game world'; and a list of players connected to the 'game world'. The accuracy of the data encapsulated within a 'game world object' is dependent on the various report messages coming from all the clients connected to the corresponding active 'game world'.

7. A player in the application's lobby can get a list of games (via MediusGetGames(), which enumerates all the current 'game world objects') then request to join a given 'game world' (via MediusJoinGame(), using the respective MediusWorldID). If the join request is successful, the DME 'game world's connection information (NetConnectionInfo) will be returned so that a NetConnect() to this 'game world' can take place.

#### If a Peer-to-Peer Game

- A DME 'game world' is a single instance of a game that resides on a peer-to-peer 'host'. This
  'game world' is created with a call to NetHostPeerToPeer() (which is used for both Online and LAN
  peer-to-peer games).
- 2. A peer-to-peer 'host' theoretically can host a collection of DME 'game worlds' that are indexed by "WorldID"; but in practice, a peer-to-peer 'host' will only ever have one active 'game world' running (with WorldID set to 1).
- 3. A call to **MGCLCreateGameOnMeRequest()** causes the MUM to manage the transaction of registering/posting a peer-to-peer host's 'game world' with the Medius platform.
- 4. If the transaction is successful, a corresponding 'game world object' will be created on the MUM and a "MediusWorldID" will be generated to index this object.
- 5. Unlike a Client/Server game, the player that called **NetHostPeerToPeer()** will not need to call **MediusJoinGame()** to connect to the DME 'game world' created on the host (since the hosting player is assumed to be already connected to itself).
- 6. A MUM 'game world object' encapsulates three things: Information about an active DME 'game world' running on a peer-to-peer 'host'; connection information to this 'game world'; and a list of players connected to this 'game world'. The accuracy of the data encapsulated within a 'game world object' is dependent on the various report messages coming from all the clients connected to the corresponding active 'game world'.
- 7. A player in the application's lobby can get a list of games (via MediusGetGames(), which enumerates all the current 'game world objects'), then request to join a given 'game world' (via MediusJoinGame(), using the respective MediusWorldID). If the join request is successful, the DME 'game world's connection information (NetConnectionInfo) will be returned so that a NetConnect() to this 'game world' can take place.

### **Report Intervals**

It is up to you to schedule the transmission of all reports, as well as to populate the message structure that will be sent with each report. It is recommended that all reports be sent every 25–30 seconds. Failure to send a specified report will cause the respective server-side object to timeout (the exact duration depends on the MUM Object Collection type; most are set to 60–120 seconds).

As discussed in the previous section "Ungraceful Disconnects", you need to consider the same situations that may prevent the sending of Medius reports and calling **MediusUpdate()** (such as hitting compiler breakpoints, blocking application function calls > x amount of time, and so forth).

The accuracy of the application's lobby data is based entirely on the frequency of these reports. Shorter report intervals (and manual report sends) increase the accuracy of the data presented to players in the lobby. Common Medius functions that depend on fresh report information are:

- **MediusGetGames()** Sends request for list of game worlds (that is, it enumerates all or a range of 'game world objects').
- **MediusGetGameInfo()** Sends request for information about a specific game world (that is, it retrieves information about a specific 'game world object').
- **MediusGetGamePlayers()** Sends request for a list of players connected to a specific game world (that is, it retrieves the 'game world object's list of players connected to the given 'game world' accuracy is dependent on player reports).

- MediusGetPlayerInfo() Sends request for information about a specific player (that is, retrieves 'player object' information).
- MediusGetTotalGames() Retrieves the total number of games for a given ApplicationID.

### Special Notes about Peer-to-Peer Host Migration and MediusWorldID

The SCE-RT SDK Medius Game Communication Library (MGCL) Release 2.10 – Overview has more information about how to handle Peer-to-Peer Host Migration but a special mention must be made about the MediusWorldID used for Medius platform reports due to the host migrating.

### How and When a MediusWorldID Can Change

In a client/server game, the *MediusWorldID* (needed for reports) will never change. However, if the host migrates in a peer-to-peer game (as detected by the callback **NetTypePeerToPeerHostChangeCallback** set within *NetConnectInParams*), **MGCLMoveGameWorldOnMe()** must be called when a given client is identified as the new host.

If successful, a new MUM 'game world object' is created on the Medius platform to reference the new DME 'game world' on the new host's machine. A new *MediusWorldID* is then specified in the **MediusServerMoveGameWorldOnMeResponse** message.

**MediusTypeReassignGameMediusWorldIDCallback** will be triggered (as set in *MediusInitializeInParams*) for all other clients. The new *MediusWorldID* is specified in the **MediusReassignGameMediusWorldID** message. Each player should immediately send a (forced/manual) report (based on reporting responsibilities) upon receipt of a new *MediusWorldID*.

## **Maintaining the Medius Connection**

Once a player is fully logged in with the Medius platform, calling **MediusUpdate()** is necessary to ensure that the user's session (player object) and connection (socket) are maintained (with a 30–45 second timeout threshold).

#### Additional Notes About MediusUpdate()

- 1. **MediusUpdate()** manages the processing of sending and receiving Medius messages.
- 2. The previous section, 'Ungraceful Disconnects', describes what happens if you fail to call MediusUpdate() within a fixed amount of time. It is highly recommended that you wrap/encapsulate the MediusUpdate() function and let your application keep track of the elapsed time between calls (with either NetGetLocalTime() or your own timing function). If your application detects an elapsed time > 14 seconds then ASSERT().
- 3. If **MediusUpdate()** does not return MediusErrorNone, then your application should attempt to handle the current error condition (if possible). The only other *MediusErrorCode* results that this function may generate are:
  - a. **MediusErrorNotInitialized MediusInitialize()** or **MediusInitializeBare()** have not been called yet.
  - MediusErrorGeneral An internal call to NetUpdate() to service/update the Medius connection returned an error code (call MediusGetLastNetUpdateError() for more information).

31

## Sending World Reports (Maintaining Game World Objects)

MediusSendWorldReport() is the Medius API function used to send 'world reports'. The PlayStation®2 client designated as the game's session master is responsible for periodically sending a 'world report' over its Medius connection via MediusSendWorldReport(). This report message should be sent every 25–30 seconds, primarily to act as a MUM 'game world object' heartbeat.

The MLS uses world report messages to update the state of the respective 'game world object' residing on the MUM. This report can be used to change attributes (on-the-fly) of a 'game world object', such as the game name, current game level, game password, minimum skill level, and so forth.

#### Additional Notes About MediusSendWorldReport()

- 1. You only send 'world reports' after successful creation of (and connection to) a game (that is, a DME 'game world'). You can create a new game (and its associated 'game world object', represented with a MediusWorldID on the Medius platform) in one of two ways (see "Understanding MUM Game World Objects and DME Game Worlds" for more information):
  - a. If you are creating a client/server game, call **MediusCreateGame()** to create a DME 'game world' on a standalone DME game server (which will then trigger the creation of a 'game world object' on the Medius platform). The player that created the game will then call MediusJoinGame() using the MediusWorldID in the MediusCreateGameResponse message. Other players call MediusGetGames() to get a list of 'game world objects' and call MediusJoinGame() using the MediusWorldID in a given MediusGameListResponse message.

Note: It is recommended that the player that created the game call NetJoin() as soon as possible so that a session master can be designated and all players will know who is responsible for sending 'world reports'. After MediusCreateGame(), you have about 120 seconds to send a 'world report' before the 'game world object' will timeout; nonetheless, you should target (for example) < 10 seconds, being mindful of issues such as a long DVD load

b. If you are the host of a peer-to-peer game, call MGCLCreateGameOnMeRequest() to trigger the creation of a 'game world object' on the Medius platform. Calling NetHostPeerToPeer() automatically creates a DME 'game world' on the host, so the host will not need to call MediusJoinGame(). As above, other players call MediusGetGames() to get a list of 'game world objects' and call MediusJoinGame() using the MediusWorldID in the MediusGameListResponse message.

Note: The host should be responsible for sending 'world reports' until a session master is designated with a call to NetJoin(). If a NetTypeSMChangeCallback (part of **NetJoinInParams**) gets triggered (because the SessionMaster migrated to another client), the new session master should then be responsible for 'world reports'. After a MGCLCreateGameOnMeRequest() you have about 120 seconds to send a 'world report' before the 'game world object' will timeout; nonetheless, you should target (for example) < 10 seconds - being mindful of issues such as a long DVD load time.

2. If you stop sending 'world reports', the Medius platform will end/close the 'game world object', thus preventing any new players from finding and joining the game. Nonetheless, the game will continue to be playable on the standalone DME game server or peer-to-peer host's machine until everyone has disconnected and/or returned to the Medius lobby.

3. If a 'game world object' times outs (due to a 'world report' stoppage), the log files will record this as (for example):

```
(MPS Log)

12:15:10 END_WORLD_ON_GAME_SE Destroy Game Message received from MUM -fwd to Proxy Server

(MUM Log)

12:15:10 MUM_TIMER GameWorld IP 208.236.15.245 PORT 41031 World 1 time out event

12:15:10 MUM TIMER Success sending fwd End Game msg to ConnWorldID 1

ConnClientIndex 2
```

4. If for some reason the sending of 'world reports' resumes after the 'game world object' timed out, they essentially will be ignored by the Medius platform; nonetheless, the log files will still record this as (for example):

```
(MUM Log)

12:20:00 XML_BASE UpdateGameWorldByIDStart

12:20:00 WORLD MediusWorldID 1 Game Name PB-P2P-5408

12:20:00 WORLD WMUpdateGameWorldByID error -404
```

5. One way to verify a 'world report' was successfully processed by the Medius platform is to call **MediusGetGames()**. This will enumerate and return all games listed on the Medius platform with the given *ApplicationID*. If you see your game listed, you're assured that the 'world report' is functioning properly and maintaining the 'game world object' on the Medius platform.

#### The Sequence for Sending a 'World Report'

- 1. Create an instance of the MediusWorldReport structure.
  - a. memset() the structure to '0'.
  - b. Set SessionKey to the value you saved from MediusSessionBeginResponse.
  - c. Set MediusWorldID to the value you saved from:

```
(If client/server game creator) MediusCreateGameResponse (If peer-to-peer host) MediusServerCreateGameOnMeResponse
```

(If joining) The value passed in for MediusJoinGame() (for both client/server and peer-to-peer)

**Note:** Be mindful of whom the current SessionMaster is and/or if a peer-to-peer 'host' migration took place (causing a new MediusWorldID to be assigned).

d. Set *PlayerCount* to the current DME player count. Use **NetGetValidClientCount()** with either your GS connection index or your peer-to-peer connection index.

**Note:** Currently, the report's *PlayerCount* field no longer updates the 'game world object's *PlayerCount*. This count is now managed by the various incoming 'player reports'. However, for verification purposes, it is recommended that you still set this field.

- e. Set *GameName* to either the same name used during game creation or a new name. (It is possible to pack additional string information in the *GameName* if your application has any special UI display needs).
- f. Set *GameStats* to an (optional) string provided by the application. Each application will decide if and how they wish to use this field.
- g. Set *MinPlayers* to the same value used during game creation. (For simplicity's sake, do not change).
- h. Set *MaxPlayers* to the same value used during game creation. (For simplicity's sake, do not change).
- i. Set *GameLevel* to an arbitrary value. (Possible usage may be to represent a given map or difficulty setting).

- j. Set PlayerSkillLevel to an arbitrary value.
- k. Set RulesSet to an arbitrary value.
- I. Set *GenericField1* to n (optional) string provided by the application. Each application will decide if and how they wish to use this field.
- m. Set GenericField2 to an (optional) string provided by the application.
- n. Set GenericField3 to an (optional) string provided by the application.
- Set WorldStatus to any MediusWorldStatus type. This represents the state that the DME 'game world' is in: Inactive, Staging, Active, or Closed. Your application may handle each state differently.
- 2. Call **MediusSendWorldReport()** with the respective report message and verify that *MediusErrorNone* was returned (if this function fails you should only expect 'common errors', as declared in 'General Steps in Executing Medius API Function Calls').

#### Sample - Sending a World Report

```
void MyGame IssueWorldReport(MediusWorldStatus eWorldStatus)
    MediusWorldReport report;
    char szWorldStatus[50];
    MediusErrorCode result;
   memset(&report, 0, sizeof(MediusWorldReport));
    switch (eWorldStatus)
    case WorldInactive:
       strcpy(szWorldStatus, "WorldInactive");
       break:
    case WorldStaging:
        strcpy(szWorldStatus, "WorldStaging");
    case WorldActive:
       strcpy(szWorldStatus, "WorldActive");
        break:
    case WorldClosed:
        strcpy(szWorldStatus, "WorldClosed");
        break;
    default:
        strcpy(szWorldStatus, "Error");
        break:
    } // End SWITCH
    printf("(Time: '%0.2ld: %0.2ld: %0.2ld')",
        (long) ((g iTimeOfLastUpdate / 1000 / 60 / 60)),
        (long) ((g iTimeOfLastUpdate / 1000 / 60) % 60),
        (long) ((g iTimeOfLastUpdate / 1000) % 60));
    printf("Sending World Report: (%s) (MWID: %d) (SK: %s) (%d-%s) \n",
        g RtLobby.m GameName,
        g RtLobby.m iMediusWorldID,
        g RtLobby.m SessionKey,
       eWorldStatus.
       szWorldStatus);
// -----
    // Set World Report
    // -----
```

```
strncpy(report.SessionKey, g RtLobby.m SessionKey, SESSIONKEY MAXLEN-1);
report.SessionKey[SESSIONKEY MAXLEN-1]='\0';
strncpy(report.GameName, g_RtLobby.m_GameName, GAMENAME_MAXLEN-1);
report.GameName[GAMENAME MAXLEN-1]='\0';
strncpy(report.GameStats, "", GAMESTATS MAXLEN-1);
report.GameStats[GAMESTATS MAXLEN-1]=' \setminus \overline{0}';
report.MinPlayers = 1; // Use same value from create game report.MaxPlayers = 8; // Use same value from create game report.GameLevel = 1;
report.PlayerSkillLevel = 1;
report RulesSet = 1;
report.RulesSet
report.GenericField1 = 0;
report.GenericField2 = 0;
report.GenericField3 = 0;
report.WorldStatus = eWorldStatus;
// -----
// Medius Send World Report
// -----
result = MediusSendWorldReport(&report);
if (result)
{
    printf("App:[%s][%d]MediusErrorCode:'%d'", FILE, LINE, result);
return;
```

# Sending an End Game Report (Closing Game World Objects)

**MediusSendEndGameReport()** is the Medius API function to send an 'end game report'. There are only two ways for a 'game world object' to end/close:

1. timeout, or

}

2. 'end game report' was received.

When a game has determined that it is time to end (that is, the DME 'game world' should be closed/shutdown), the client acting as the game's session master is responsible for sending an 'end game report' over its Medius Connection. The MLS will then save the statistics of each player (player object) associated with the given 'game world object' to the Medius database and remove the 'game world object' from the MUM.

#### Coordinating the Sending of End Game Reports

You must consider a player's (player object's) *Stats* field at the time an 'end game report' is received – the last received *Stats* field will be persisted (that is, the last 'player report' x-amount of time ago); therefore, if *Stats* are an important aspect of your application you must have the session master coordinate the process of having every client send one last 'player report' or **MediusAccountUpdateStats()** call. This process may look something like this:

1. An application level 'end-game-event' is triggered to indicate that the current game has ended (because someone crossed the finish line in a race, all hostages have been rescued, the enemy team was eliminated, or some other game-specific condition was reached). This may or may not have occurred on the session master's machine. A client is then responsible for sending a message (either with a DME message or a field change in a DME NetObject that represented the game's current state) to the session master and the other clients.

- 2. Upon receiving this 'end-game-event', every client takes a snapshot of the data necessary to store in their *Stats* field.
- 3. After the session master has taken a snapshot of their own *Stats* field, the session master then must coordinate directly with each and every client the responsibility of sending one last *'Stats'* update. This would most likely look like an application-defined DME message that says, "Client-x send your final *Stats* update". A client receiving this message would say, "Okay SM, I just finished sending my final *Stats* update" and send a DME message back to the session master indicating as such.
- 4. Once the session master has received the final *Stats* update from each and every client, s/he is ready to send an 'end game report'.
- 5. If a client never responds to the session master's request to send one last *Stats* update (perhaps they disconnected), the session master should timeout (ignore) that particular request to that client (with, say, a 10-second timeout threshold) and proceed with the 'end game report'.

**Note:** If you record 'Player Disconnects' (in regards to Wins, Losses, and Disconnects), it is recommend that after x-amount of time into a game, you manually update (increment) the 'Disconnect' section of a player's *Stats* field; therefore, when step #2 takes place, you must increment the Wins or Losses section and set *Disconnects* to its value prior to the game starting. See the "Ladder Management" section for more information. Be careful of the usage of **MediusAccountUpdateStats()** and recording "Wins, Losses, and Disconnects", because this will immediately persist the player's *Stats* field to the database.

### Additional Notes About MediusSendEndGameReport()

- 1. When the Medius platform receives this report message, all the player's *Stats* fields will be persisted to the Medius database (similar to the functionality of a manual **MediusAccountUpdateStats()** call).
- 2. In a peer-to-peer game: When a 'game world object' closes on the Medius platform, a MGCLServerEndGameCallback will be triggered on the 'host' (as declared in MGCLInitializeInParams). This callback will not automatically close the DME 'game world' (basically, you should ignore MGCLServerEndGameCallback because it only indicates that the 'game world object' has closed; ignore MGCLEndGameResponse() at this point also). You do, however, need to provide additional shutdown logic that involves (for example) the 'host' client sending to all players an application-specific NetSendMessage() that indicates, "Disconnect now and return to the Lobby". This way you can coordinate all players leaving at the same time. Otherwise, the 'end game report' will only set every user's 'player object' on the Medius platform to "JoinedChatWorld" (just as if you called a MediusUpdateClientState()), even though all the clients may still be connected to the DME 'game world' on the peer-to-peer 'host'.
- 3. In a client/server game: Similar to above, an 'end game report' will not automatically close the DME 'game world' on the GS. The session master should send an application-specific **NetSendMessage()** to all players that indicates, "Disconnect now and return to the Lobby". This way you can coordinate all players leaving at the same time. Otherwise, the 'end game report' will only set every user's 'player object' on the Medius platform to "**JoinedChatWorld**" (just as if you called **MediusUpdateClientState()**), even though all the clients may still be connected to the DME 'game world' on the GS.
- 4. After the given 'game world object' has been closed, subsequent 'player reports' will eventually log (-404) errors on the MUM (which are essentially ignored by the Medius platform).
- 5. The normal process when a player exits a game is as follows:
  - a. Call MediusUpdateClientState(), with UserAction set to LeftGameWorld.
  - b. Call MediusUpdateClientState(), with UserAction set to JoinedChatWorld.
  - c. Call NetLeave() on the DME 'game world's connection.
  - d. Call **NetDisconnect()** on the DME 'game world's connection. Be sure to specify the **NetDisconnectReason**.

6. Setting WinningTeam, WinningPlayer, and FinalScore (of the **MediusEndGameReport** type) requires special components to be built that describe how to manage "tournament logic". Custom fields may be added to this report. Contact SCE-RT developer support (scert-support@scea.com) for more information.

### The Sequence for Sending an 'End Game Report'

- 1. Create an instance of the *MediusEndGameReport* structure.
  - a. **memset()** the structure to '0'.
  - b. Set SessionKey to the value you saved from MediusSessionBeginResponse.
  - c. Set MediusWorldID to the value you saved from:

```
(If client/server game creator) MediusCreateGameResponse.
```

(If peer-to-peer host) MediusServerCreateGameOnMeResponse.

(If joining) The value passed in for MediusJoinGame() (for both C/S and P2P).

**Note:** Be aware of who the current *SessionMaster* is and/or (if peer-to-peer) if a peer-to-peer 'host' migration occurred (and thus a new *MediusWorldID* has been assigned).

- d. WinningTeam (Not implemented by default).
- e. WinningPlayer (Not implemented by default).
- f. FinalScore (Not implemented by default).
- 2. Call **MediusSendWorldReport()** with the proper report message and verify that *MediusErrorNone* was returned (if this function fails, you should only expect 'common errors', as declared in 'General Steps in Executing Medius API Function Calls').

#### Sample - Sending an End Game Report

```
void MyGame_IssueEndGameReport()
{
    MediusEndGameReport report;
    MediusErrorCode result;

    memset(&report, 0, sizeof(MediusEndGameReport));

    printf("(Time:'%0.2ld:%0.2ld:%0.2ld')",
        (long) ((g_iTimeOfLastUpdate / 1000 / 60 / 60)),
        (long) ((g_iTimeOfLastUpdate / 1000 / 60) % 60),
        (long) ((g_iTimeOfLastUpdate / 1000) % 60));
```

```
printf("Sending End Game Report: (MWID:%d) (SK:%s) \n",
       g RtLobby.m iMediusWorldID,
       g RtLobby.m SessionKey);
   // -----
   // Set End Game Report
   // -----
   strncpy(report.SessionKey, g RtLobby.m SessionKey, SESSIONKEY MAXLEN-1);
   report.SessionKey[SESSIONKEY MAXLEN-1]='\0';
   report.MediusWorldID = g RtLobby.m iMediusWorldID;
   // If your application utilizes the following fields, contact SCE-RT developer
   // support for more information.
   report.WinningTeam;
                                    // Currently not implemented
   report.WinningPlayer;
                                   // Currently not implemented
   report.FinalScore;
                                   // Currently not implemented
  // -----
   // Medius Send End Game Report
   // -----
   result = MediusSendEndGameReport(&report);
   if (result.)
       printf("App:[%s][%d]MediusErrorCode:'%d'", FILE, LINE, result);
   }
   return;
}
```

## **Sending Player Reports (Maintaining Player Objects)**

**MediusSendPlayerReport()** is the Medius API function used to send 'player reports'. Every client connected to a DME 'game world' is responsible for periodically sending a 'player report' to the MLS. The MLS uses these report messages to update the state of the corresponding 'player object' residing on the MUM.

**Note:** Not sending 'player reports' will not cause 'player objects' to timeout/close (unlike other server-side objects). Nonetheless, you should still send them periodically to keep the 'player object's data current on the Medius platform (player reports should be sent every 25–30 seconds).

The MUM manages a collection of 'game world objects' and each 'game world object' maintains a list of references (pointers) to 'player objects' that represent clients joined to a particular DME 'game world'. The first time a 'player report' is received (with a given *MediusWorldID*), a reference to that player's 'player object' will be added to the corresponding 'game world object's list of players joined. This 'player report' will additionally increment the *PlayerCount* of the given 'game world object'.

#### Additional Notes About MediusSendPlayerReport()

1. 'Player reports' are sent after successfully joining a game (or creating a game). Upon joining, you should send a 'player report' immediately to keep the Medius platform informed of the current state.

**Note:** If you do not send the first 'player report', the given game can still be played, but the Medius platform will not have an accurate *PlayerCount* for that particular game and will have no idea that you ever 'successfully' joined that game. I.e., *PlayerCount* due to a **MediusJoin()** is not managed because the **NetConnect()** may have failed. This is how it is possible to overcome the particular 'race condition' if, for instance, 5 clients all simultaneously attempted to join a 15- or 16-player game.

One way to verify if a player report was successfully processed by the Medius platform is to call **MediusGetGamePlayers()**. This will enumerate all the players associated/connected with the given game's *MediusWorldID*.

 A player's Stats field is not persisted to the Medius database until either a MediusSendEndGameReport() is received or the application calls MediusAccountUpdateStats().

### Special Note About a Player's Stats Field

A player's *Stats* field (elements 2 through 12) is no longer used in by the Medius platform's "Ladder System". In the past, the Ladder system was limited to only one rankable Ladder. As of version 1.50, the Medius platform has been expanded to support up to 100 rankable Ladders (see the "Ladder Management" section for more information).

#### Sequence for Sending a 'Player Report'

- 1. Create an instance of the MediusPlayerReport structure:
  - a. memset() the structure to '0'.
  - b. Set SessionKey to the value you saved from MediusSessionBeginResponse.
  - c. Set MediusWorldID to the value you saved from:

```
(If client/server game creator) MediusCreateGameResponse.
```

(If peer-to-peer host) MediusServerCreateGameOnMeResponse.

(If joining) The value passed in for **MediusJoinGame()** (for both client/server and peer-to-peer).

**Note:** (If peer-to-peer) Be aware of whether a peer-to-peer 'host' migration occurred (and thus a new *MediusWorldID* has been assigned).

- d. Set Stats (if utilized) as appropriate (see "Special Note About a Player's Stats Field" above).
- 2. Call **MediusSendPlayerReport()** with the proper report message and verify that *MediusErrorNone* was returned (if this function fails, you should only expect 'common errors', as declared in 'General Steps in Executing Medius API Function Calls').

### Sample - Sending a Player Report

```
void MyGame IssuePlayerReport()
   MediusPlayerReport report;
   MediusErrorCode result;
    memset(&report, 0, sizeof(MediusPlayerReport));
    printf("(Time: '%0.2ld: %0.2ld: %0.2ld')",
        (long) ((g iTimeOfLastUpdate / 1000 / 60 / 60)),
        (long) ((g iTimeOfLastUpdate / 1000 / 60) % 60),
        (long) ((g iTimeOfLastUpdate / 1000) % 60));
    printf("Sending Player Report: (MWID:%d) (SK:%s) \n",
        g RtLobby.m iMediusWorldID,
        g RtLobby.m SessionKey);
    // Set Player Report
    // -----
    strncpy(report.SessionKey, g RtLobby.m SessionKey, SESSIONKEY MAXLEN-1);
    report.SessionKey[SESSIONKEY MAXLEN-1]='\0';
    report.MediusWorldID = g RtLobby.m iMediusWorldID;
    // If your application utilizes the Stats field
    report.Stats; // Set appropriately
```

```
// ------
// Medius Send Player Report
// ------
result = MediusSendPlayerReport(&report);
if (result)
{
    printf("App:[%s][%d]MediusErrorCode:'%d'", FILE, LINE, result);
}
return;
```

### Maintaining the MGCL Connection

Once a 'host' of a peer-to-peer game has established their MGCL Connection with the Medius platform, you must calling **MGCLUpdate()** to ensure that the host's session (game server object) and connection (socket) are maintained (with a 30–45 second timeout threshold).

**Note:** Having an MGCL Connection established with the Medius platform does not explicitly indicate that a DME 'game world' has been created on the 'host' machine. It simply means that a 'game server object' has been created on the Medius platform and is ready for a **MGCLCreateGameOnMeRequest()** call that will create and associate a 'game world object' with a DME 'game world'.

#### Additional Notes about MGCLUpdate()

- 1. **MGCLUpdate()** manages the process of sending and receiving 'server-based' messages. (See the "MGCL Overview" for more information about MGCL).
- 2. **MGCLUpdate()** exhibits the same properties as **MediusUpdate()** if you fail to call it within a fixed amount of time; you should **ASSERT()** if > 14 seconds elapsed between update calls.

# Sending Server Reports (Maintaining Game Server Objects)

**MGCLSendServerReport()** is the MGCL API function used to send 'server reports'. This report message is sent by each game server (peer-to-peer host) to the Medius Proxy Server (MPS) to notify the Medius platform of the 'host's current state. Once a host's MGCL connection has been established, 'server' reports' will need to occur regardless of whether a DME 'game world' has been created yet on the host's machine (server reports should be sent every 25–30 seconds). As a backend service (shielding the application developer), 'server reports' keep the 'game server object' current on the Medius platform while **MGCLUpdate()** maintains/services the 'game server object'.

### Additional Notes About MGCLSendServerReport()

- 1. After the MGCL connection has been established, you must send 'server reports' regardless of whether there is currently a DME 'game world' created yet or not. If a game has not yet been created, you set *ActiveWorldCount* and *TotalActivePlayers* to '0'.
- 2. A game is created using MGCLCreateGameOnMeRequest(), which creates a 'game world object' that encapsulates the NetConnectInfo to a NetHostPeerToPeer() game (that is, a DME 'game world') with the Medius platform. After a successful call to MGCLCreateGameOnMeRequest() a 'game world object' is created on the Medius platform that the 'game server object' will reference. You should then set ActiveWorldCount to '1' and enumerate all the players currently connected to the game (using NetGetValidClientCount()) and set this for TotalActivePlayers.
- 3. Just as is the case with 'world reports', if you stop sending 'server reports' the Medius platform will end/close both the 'game world object' and the 'game server object', thus preventing any new players from finding and joining the game. The game will continue to be playable on the peer-topeer host's machine until all current players have disconnected and/or returned to the Medius lobby.
- 4. If a 'game server object' times out (due to a 'server report' stoppage), the log files will record this as (for example):

```
(MUM Log) This is the only log file that will report this event 10:25:48 MUM_TIMER GameServer time out event Skey 3 ID=0 Status=3 IntermedServerID=0 ClientIndex=0 WID=1
```

5. If for some reason the sending of 'server reports' resumes after the 'game server object' timed out (causing the 'game world object' to close), they essentially will be ignored by the Medius platform; nonetheless, the log files will record this as (for example):

```
(MUM Log)
// Server Report will cause this error message
10:30:37 WORLD WMGetGameServerInfoBySessionKey error -405
// World Report will cause this error message
10:30:39 XML_BASE UpdateGameWorldByIDStart
10:30:39 WORLD MediusWorldID 1 GameName PB-P2P-1710
10:30:39 WORLD WMUpdateGameWorldByID error -107
```

### Sequence for Sending a 'Server Report'

- 1. Create an instance of the **MediusServerReportType** structure:
  - a. memset() the structure to '0'.
  - b. Set SessionKey to the value you saved from MediusServerSessionBeginResponse.
  - c. Set MaxWorlds to '1' (this should not change).
  - d. Set *MaxPlayersPerWorld* to the maximum number of clients that may be connected to the DME 'game world' (this will be same value set for *MaxClients* as part of the **NetHostPeerInParams** structure and should not change).
  - e. Set ActiveWorldCount to '0' if no DME 'game world' has been created on the host yet; otherwise, set this to '1' if the host has called **NetHostPeerToPeer()**. It is assumed that only one 'game world' will ever be created on a peer-to-peer host's machine.
  - f. Set TotalActivePlayers to the current DME player count (obtained using NetGetValidClientCount() with the peer-to-peer connection index).
  - g. Set AlertLevel to MGCL\_ALERT\_NONE (this should not change). This field is primarily used by a GS (DME Game Servers also use the MGCL API to communicate with the Medius platform).
- 2. Call MGCLSendServerReport() with the proper report message and verify that MGCL\_SUCCESS was returned.

#### Sample - Sending a Server Report

```
void MyGame IssueServerReport()
{
   MediusServerReportType report;
   MGCL ERROR CODE result;
   int iConnectedToHost = -1;
   memset(&report, 0, sizeof(MediusServerReportType));
   // -----
   // Set Server Report
    // -----
    strncpy(report.SessionKey, q RtMGCL.m MGCLSessionKey, SESSIONKEY MAXLEN-1);
   report.SessionKey[SESSIONKEY_MAXLEN-1]='\0';
    report.MaxWorlds = 1;
                               // P2P host will only ever have 1 'game world'
    report.MaxPlayerPerWorld = MAX CLIENTS;
    if (g GameCreated == TRUE) {
       report.ActiveWorldCount = 1;
    } else{
       report.ActiveWorldCount = 0;
   NetGetValidClientCount(&iConnectedToHost, g P2P pHDME);
```

```
if ((iConnectedToHost < 0) || (iConnectedToHost > MAX CLIENTS))
       ASSERT(0);
   report.TotalActivePlayers = iConnectedToHost;
   printf("(Time:'%0.2ld:%0.2ld:%0.2ld')",
       (long) ((g iTimeOfLastUpdate / 1000 / 60 / 60)),
       (long) ((g iTimeOfLastUpdate / 1000 / 60) % 60),
       (long) ((g iTimeOfLastUpdate / 1000) % 60));
   printf("(MGCL)Sending Server Report:(SSK:%s)(AWC:%d)(TAP:%d)\n",
       report.SessionKey,
                           // Server Session Key
       report.ActiveWorldCount,
       report.TotalActivePlayers);
   // -----
   // MGCL Send Server Report
   // -----
   result = MediusSendPlayerReport(&report);
   if (result.)
       printf("App:[%s][%d]MGCL ERROR CODE:'%d'", FILE, LINE, result);
   return;
}
```

### Leaving a Game World

When a player leaves a 'game world' (either gracefully or ungracefully), the player should inform the Medius platform of their intentions so that the lobby will be up-to-date; otherwise, the Medius platform will be relying on timeout events to update and manage its Object Collections.

If a player wishes to leave a 'game world' and return to a lobby (either by their own will or because of an upcoming 'end game report'), they should:

- 1. Know how to persist their Stats field (if required).
- 2. Call NetLeave() to leave a DME 'game world'.
- 3. Call **NetDisconnect()** to disconnect from either a GS or peer-to-peer host (thus closing the socket). **Note:** peer-to-peer hosts would also call this on themselves.
- 4. Call **MediusUpdateClientState()** with **MediusUpdateUserState**'s *UserAction* set to 'LeftGameWorld'. This will remove the 'player object' reference that the 'game world object' maintained; the *PlayerCount* will also be decremented.
- 5. Call MediusUpdateClientState() with MediusUpdateUserState's *UserAction* set to 'JoinedChatWorld'. This will set the 'player object' on the Medius platform to a state where it is able to carry out Medius 'lobby' functionality.

If a player wishes to leave a 'game world' and shut down online connectivity, they should:

- 1. Know how to persist their Stats field (if required).
- 2. Call NetLeave() to leave a DME 'game world'.
- 3. Call **NetDisconnect()** to disconnect from either a GS or peer-to-peer host (thus closing the socket). **Note:** peer-to-peer hosts would also call this on themselves.
- 4. Call **MediusUpdateClientState()** with **MediusUpdateUserState**'s *UserAction* set to 'LeftGameWorld'. This will remove the 'player object' reference that the 'game world object' maintained; the *PlayerCount* will also be decremented.
- 5. Call **MediusDisconnect()** to close the Medius connection.

- 6. Call MediusClose() (if MediusInitialize() was called earlier) or MediusCloseBare() (if MediusInitializeBare() was called earlier) to clean up/free all connection-related resources in regards to the Medius connection index.
- 7. If you called MediusCloseBare() in step 6, call NetClose().
- 8. The application is now ready to unload IRX modules.

  Note: Not all of the PlayStation®2 network IRX modules may be unloaded; therefore, resetting the IOP may be required. See the PlayStation®2 network documentation for the issues involved with performing this task.
- 9. At this point, the player will (most likely) be back on the application's main selection screen, where they may choose to play either a single player or multiplayer game.

If a player disconnects by turning off their PlayStation<sup>®</sup>2 or by some other disastrous event, the Medius platform will eventually timeout all relevant server-side objects as appropriate and/or automatically migrate hosting responsibilities and NetObject ownership responsibilities. In such a case, note the following:

- 1. Be aware of whether you need to persist a player's *Stats* field.
- 2. A 'player object' will naturally timeout due to a lack of **MediusUpdate()** calls in about 30–40 seconds. If your application uses account logins, players must wait for their corresponding 'player object' to timeout before they will be able to login again..
- 3. A 'game world object' will naturally timeout due to lack of 'world reports' in about 120 seconds.
- 4. If the DME detects that a hosting player has timed out, a **NetTypePeerToPeerHostChangeCallback** will be triggered.

# **Chat Channel Management**

After a user is fully logged into the Medius platform, they will be assigned to a default chat channel from which they can fully utilize "lobby" technology. This includes chatting, sending instant messages, and creating buddy lists. Users can also navigate to different chat channels or create new chat channels. Other basic "lobby" functionality includes getting a list of players on a given chat channel and, of course, finding, creating, and joining games (which will be discussed in the next section, "Game Management").

This "lobby" technology as a whole (if fully integrated into your application) will help build a solid foundation for creating an "Online Community" for your title that can prove vital in the long-term success of your game.

The following Medius functions associated with Chat Channel Management and Chat Messages are described in this section:

- MediusBanPlayer()
- MediusGenericChatSetFilter()
- MediusCreateChannel()
- MediusFindPlayer()
- MediusFindWorldByName()
- MediusGetChannelInfo()
- MediusGetChannels()
- MediusGetChannels\_ExtraInfo()
- MediusGetLobbyPlayerNames()
- MediusGetLobbyPlayerNames ExtraInfo()
- MediusGetLobbyPlayers()
- MediusGetPlayerInfo()
- MediusGetTotalChannels()
- MediusGetTotalUsers()
- MediusGetWorldSecurityLevel()
- MediusJoinChannel()
- MediusSendGenericChatMessage()
- MediusSetAutoChatHistory()
- MediusSetWorldLobbyFilter()
- MediusTextFilter()

- Prevents a player from joining a given chat channel
- Enables or disables a given chat type that can be received by the server
- Creates a chat channel
- Searches for player by AccountID or AccountName
- Searches for a chat channel by name
- Gets detailed chat channel information
- Gets a list of all chat channels
- Gets a list of all chat channels, along with additional information
- Gets a list of player names in a chat channel
- Gets a list of player names in a chat channel, along with additional information
- Gets a list of players in a chat channel
- Gets player information by AccountID
- Gets a total count of chat channels
- Gets a total count of players
- Determines if the chat channel has a password
- Requests to join a chat channel
- Sends a chat message
- Chat message history to receive
- Sets a chat channel filters
- Implements server-side vulgarity checks

# Preventing a Player from Joining a Chat Channel

The **MediusBanPlayer()** function (with *MediusApplicationType* set to 'LobbyChatChannel') allows you to provide logic in your application to prevent a specific player from joining a given chat channel. Setting a 'ban' on a particular player will prevent the player from receiving a successful **MediusJoinChannel()** response for a given chat channel. Currently, there is no "Kick" feature. This 'ban' can be put in place for a specified number of seconds or for the lifetime of the chat channel.

### **Disabling or Enabling Medius Chat**

The **MediusGenericChatSetFilter()** function allows for the disabling or re-enabling of a given chat type that can be received by the server. **MediusChatMessageType** currently lists the various chat types that can individually be enabled or disabled including "broadcast messages, whisper messages, global broadcast messages, clan chat messages, and buddy chat messages".

If the application has a **MediusTypeGenericChatFwdMessageCallback** declared, then all of the given chat types are enabled by default. If a player is in-game, for example, they may consider disabling some of the chat messages (like broadcast) but keep clan chat and buddy chat.

### **Creating a Chat Channel**

Creating a chat channel is accomplished using the MediusCreateChannel() call. The MediusCreateChannelRequest data structure contains chat channel attributes such as chat channel name, minimum number of players, maximum number of players, chat channel password, and so forth. Upon receipt of a MediusCreateChannelRequest message, the MLS will manage the transaction of locating an available chat server (this could be any MLS that is connected to a given MUM) and reserving a 'lobby world object (chat channel)' identifiable by a newly generated MediusWorldID on both the MLS and MUM servers. The Medius platform response to the client will include this new MediusWorldID, which is then used to join the chat channel via MediusJoinChannel().

Filterable attributes for chat channels can be set one time and one time only by setting *GenericField1* to *GenericField4* of **MediusCreateChannelRequest** during creation time. See "Filtering Chat Channels" below for more information.

## Searching for a Player

The **MediusFindPlayer()** function searches for another player using either *AccountID* or *AccountName* (exact string match). The response message will return the *MediusWorldID* and *MediusApplicationType*, from which it can be determined if the other player is in a chat channel or in-game.

# **Searching for a Chat Channel**

The **MediusFindWorldByName()** function (with **MediusFindInWorldType** set to "**FindInLobbyWorld**") searches for a chat channel by Name (exact string match). The response message will return the *MediusWorldID* of the chat channel and other information.

### **Getting Chat Channel Information**

Given a *MediusWorldID*, the **MediusGetChannelInfo()** function will return detailed information about the specified chat channel (such as the current number of people in the chat channel and the maximum number allowed).

### **Retrieving a List of Chat Channels**

Calling **MediusGetChannels()** (and **MediusGetChannels\_ExtraInfo()**) will return a list of chat channels accessible by the current *ApplicationID*. The Medius platform will retrieve the list of chat channels, returning them one-at-a-time to the client. The *EndOfList* field is set to 1 when the last chat channel has been returned.

If more detail is required about individual chat channels, **MediusGetChannelInfo()** can be called to retrieve all available information about the specified channel. Calling **MediusGetChannels\_ExtraInfo()** will return information that otherwise would require calls to both **MediusGetChannels()** and **MediusGetChannelInfo()**.

The Medius platform is capable of hosting chat channels for multiple game applications simultaneously. However, users from one application will not be able to see chat channels from another application.

#### **Controlling the Number of Chat Channels Returned**

In order to manage bandwidth usage, you can regulate the number of chat channels returned to the requesting client by using the *PageID* and *PageSize* fields of the **MediusChannelListRequest** structure.

### Example:

```
Set PageSize = 10 and PageID = 1 to get chat channels (1-10).
Set PageSize = 10 and PageID = 2 to get chat channels (11-20).
Set PageSize = 10 and PageID = 3 to get chat channels (21-30).
```

**Note:** Currently, the chat channel list returned is in no particular order. If you need the list in a particular order, buffer the list into your own collection type and sort it.

## Retrieving a List of Players in a Chat Channel

Calling **MediusGetLobbyPlayers()** will return a list of all of the players connected to a specified chat channel. The Medius platform will retrieve the list of players, returning them one-at-a-time to the client. The *EndOfList* field is set to 1 when the last player has been returned. If more detail is required about individual players, **MediusGetPlayerInfo()** can be called to retrieve all available information about the specified player.

The lighter-weight versions of this function – **MediusGetLobbyPlayerNames()** and **MediusGetLobbyPlayerNames\_ExtraInfo()** – reduce bandwidth by returning only the 'names' of the players connected to a specified chat channel.

**Note:** Currently, the player list returned is in no particular order. If you need the list in a particular order, buffer the list into your own collection type and sort it.

# **Getting Player Object Information**

Given an *AccountID*, the **MediusGetPlayerInfo()** function will return detailed information about the specified player (no personal account profile information is transmitted). Response message information includes:

- AccountName Name of the player with the given AccountID.
- ApplicationID Current game that the player is playing. Your application would need to know other
   ApplicationIDs to use this information. For example, Soccer, Football, and Baseball applications
   may share the same Medius platform but each have their own ApplicationID; thus, an "Online
   Community" is created for these sports titles.
- PlayerStatus Indicates if the specified player is disconnected, in a chat channel, or in-game.
- ConnectionClass Indicates if the given player has a Modem or Broadband connection. This is of the type MediusConnectionType (set during MediusSessionBegin()).
- Stats Current Stats info for the player. Used for keeping track of x-number of score fields, and/or packing special data (perhaps to display lobby avatar information).

## **Getting the Total Chat Channel Count**

The **MediusGetTotalChannels()** function will return the total number of chat channels created for a given *ApplicationID*. This will return all chat channels running on each MLS.

**Note:** The total count of chat channels will only be for a given "region", even if your application supports co-location. Because *LocationID* is stored in the user's 'player object', the location will be calculated automatically.

### **Getting the Total Player Count**

The **MediusGetTotalUsers()** function will return the total number of users connected to the Medius platform for a given *ApplicationID*.

**Note:** The total count of users will only be for a given "region", even if your application supports colocation. Because *LocationID* is stored in the user's 'player object', the location will be calculated automatically.

### **Chat Channel Security**

The **MediusGetWorldSecurityLevel()** function (with *MediusApplicationType* set to "LobbyChatChannel") allows you to determine the security state of the specified chat channel. The response message will return a *MediusWorldSecurityLevelType* field that indicates if the chat channel is:

- Public anyone may join
- PasswordProtected MediusJoinChannel() requires a password "LobbyChannelPassword" to be submitted, or
- Closed no further **MediusJoinChannel()** calls will succeed on this given chat channel.

**Note:** A password can be set on a chat channel only during creation, when calling **MediusCreateChannel()**. Setting *LobbyPassword* to a non-empty string will automatically set the chat channel's security state to *MediusWorldPasswordProtected*.

## Joining a Chat Channel

The MediusJoinChannel() function sends a request to join an existing chat channel.

To join a chat channel, do the following:

- 1. Obtain the *MediusWorldID* of the chat channel to be joined from a previous call to **MediusGetChatChannels()** or **MediusCreateChannel()**.
- 2. Populate the **MediusJoinChannelRequest** structure and call **MediusJoinChannel()**. The server response will include the *NetConnectionInfo* structure to be used when reconnecting to the MLS. Because a single MUM may have x-number of MLSs connected to it, chat channels may span across many machines. This is why you need to disconnect, then reconnect.
- 3. Call **MediusDisconnect()** to disconnect from the current MLS and chat channel.
- 4. Call **MediusConnect()** to reconnect to a specified MLS and chat channel, passing in the *NetConnectionInfo* from the **MediusJoinChannelResponse** message.
- 5. (**Very important**) Populate the **MediusUpdateUserState** structure with *UserAction* set to **JoinedChatWorld**, and call **MediusUpdateClientState()**. (Do this every time you go from one chat channel to another.)

# Sending a Chat Message (Broadcast or Instant Messaging)

The **MediusSendGenericChatMessage()** function allows players to send chat messages to other players. To send a chat message, do the following:

- Populate the MediusGenericChatMessage data structure. Set MessageType = Broadcast to send a message to all players in the same chat channel. Set MessageType = Whisper and TargetAccountID = AccountID of the target player to send a directed message to a single player.
- 2. Call MediusSendGenericChatMessage() to send the chat message.
- 3. The player receiving the chat message will have their **MediusTypeGenericChatFwdMessageCallback** triggered.

**Notes:** If you wish to disable "Whisper" chat messages when a player is in-game, disable "Whisper" chat with **MediusGenericChatSetFilter()** – You can experiment with

**MediusReassignCallbackGenericChatFwdMessageCallback** if you wish to have these chat messages handled differently based on the 'state' of your application (for example, different 'zones' of your application may handle chat differently).

If your application requires server-side vulgarity filter checks on chat messages (using **MediusTextFilter()**), see the "Vulgarity Filtering" section of this document.

## Receiving a Chat Message

The callback function that handles the incoming chat message

(MediusTypeGenericChatFwdMessageCallback) is registered at initialization using MediusInitialize() or MediusInitializeBare(). The MediusGenericChatFwdMessage response message will contain the chat message, the <code>OriginatorAccountID</code> and <code>OriginatorAccountName</code> of the source of the message, and the message type (Broadcast/Whisper). This callback can be changed at any time by calling <code>MediusReassignCallbackGenericChatFwdMessageCallback()</code>.

### **Chat Message History**

The **MediusSetAutoChatHistory()** function sets the number of historical chat messages to automatically receive when joining a chat channel. For example, if **AutoChatHistoryNumMessages** is set to 5, then when the user joins a chat channel, they will see the last 5 chat messages that were posted on that chat channel so that a user would have some idea of what the current conversation entails.

MediusSetAutoChatHistory() should be set after a MediusSessionBegin() and after MediusSetLocalizationParms() so that the application properly receives the chat message history when the application disconnects from the MAS server and connects to the MLS server for the first time.

Only broadcast chat messages within the given chat channel are kept for historical purposes. Whisper chat, buddy chat, and clan chat are not kept in the per-channel history buffers.

The application's design should decide up front what value **AutoChatHistoryNumMessages** will be so that all versions of the application are consistent. Recommend values are between [0..10].

The chat message history is received by the client via the

**MediusTypeGenericChatFwdMessageCallback** (just like normal chat messages). Each **MediusGenericChatFwdMessage** has a *TimeStamp* field; therefore, it is up to the application to decide if it wishes to display a chat message that is older than a given time-frame. The function **MediusGetServerTime()** is called to get the "current time".

### **Filtering Chat Channels**

The **MediusSetLobbyWorldFilters()** function will filter the list of lobby worlds (chat channels) returned by a call to **MediusGetChannels()**. Filterable attributes are set one time and one time only during a **MediusCreateChannel()** call (by setting *GenericField1*, *GenericField2*, *GenericField3*, and *GenericField4*). Filterable attributes can be set for default chat channels in the MLS server's configuration file as well.

In a system with a large number of lobby worlds (1000+), the impact of calling **MediusGetChannels()** in its current implementation not only has a tremendous performance impact on the system but also causes the Medius Client to receive much more information than it really needs. This should be avoided, and result sets for a list of lobby worlds should be more discriminating (that is, the result set returned by a request for a list of lobbies needs to return only those worlds that match specified criteria).

The process for setting a chat channel filter is as follows:

- 1. You must determine what *MediusLobbyFilterMaskLevelType* is to be used. Once set, this can never be changed. It is a contract between the client and the server for the production lifetime of your title. The *FilterMaskLevelType* correlates to which Generic Fields of a Lobby World (chat channel) are used for filterable attributes. The filter takes place by performing binary operations on 32, 64, 96, or 128 bits. If you determine that only one Generic Field is to be used for filtering, then you have 32-bit resolution for our binary operations. If all four Generic Fields are to be used for filtering, then you have 128-bit resolution. Note, however, that a Chat Channel's Generic Fields are just that; thus, some titles may wish to place intrinsic value in these Generic Fields (for example items that trigger special icons on the GUI).
- 2. Populate the MediusSetLobbyWorldFilterRequest structure and call MediusSetLobbyWorldFilters(). The server response will include MediusCallbackStatus.
  - **Note:** You can safely ignore every field of the response message except for *StatusCode* and *MessageID*. The other fields are there to echo back to the client the current filters set. This is done to safely persist internal state in the Medius client library in the event of disconnection/reconnection with the Medius platform during a jump between chat channels.
- 3. Call **MediusGetChannels()** and review the list of lobby worlds (chat channels) returned. Verify that various chat channels did get filtered (in or out is based on **MediusLobbyFilterType**).

Filtering for game lists is done a bit differently than filtering for chat channels because it is based on setting operations that perform searches on a dynamically changing game list. Chat channel filtering, however, is a bit more simplistic – it just passes a bitwise-AND or bitwise-OR operator by comparing each bit of the Chat Channel's *GenericField* specified by *MediusLobbyFilterMaskLevelType* and what is currently set for *FilterMask1*, *FilterMask2*, *FilterMask3*, and/or *FilterMask4* in the **MediusSetLobbyWorldFilterRequest** structure.

# **Game Management**

After a user is fully logged in the Medius platform, they will be assigned to a default chat channel from which they can fully utilize "lobby" technology. Many different actions can be performed within a lobby chat channel. Additional to the features discussed in the "Chat Channel Management" section, players can request a list of players or games and/or search for a particular player or game – from which (perhaps as a result of interacting with the application's "Online Community") they can decide to create a new game or join an existing game.

The following Medius functions associated with 'Game Management' are described in this section:

- MediusBanPlayer()
- MediusCreateGame()
- MGCLCreateGameOnMeRequest()
- MediusFindPlayer()
- MediusFindWorldByName()
- MediusGetGameInfo()
- MediusGetGamePlayers()
- MediusGetGames()
- MediusGetGames ExtraInfo()
- MediusGetPlayerInfo()
- MediusGetTotalGames()
- MediusGetTotalUsers()
- MediusGetWorldSecurityLevel()
- MediusJoinGame()
- MediusVoteToBanPlayer()

- Prevents a player from joining a given 'game world object'
- Creates a 'game world object' for C/S
- Creates a 'game world object' for P2P
- Searches for a player by AccountID or AccountName
- Searches for a 'game world object' by name
- Gets detailed 'game world object' information
- Gets 'game world object's list of players
- Gets a list of 'game world objects'
- Gets a list of 'game world objects'
- Gets player information by AccountID
- Gets a total count of 'game world objects'
- Gets a total count of players
- Does the 'game world object' have a password?
- Requests to join a DME 'game world'
- Vote to ban player out of a game

# Preventing a Player from Joining a Game

The **MediusBanPlayer()** function (with *MediusApplicationType* set to 'Game') allows you to provide logic in your application to prevent a specific player from joining a given game. Setting a 'ban' on a particular player will prevent the player from receiving a successful **MediusJoinGame()** response for a given 'game world object'. Currently, there is no "Kick" feature (although a "Kick" feature can be implemented directly at the DME layer while in-game). This 'ban' can take place for a specified number of seconds or for the lifetime of the 'game world object'.

# Searching for a Player

The **MediusFindPlayer()** function searches for another player by either *AccountID* or by *AccountName* (exact string match). The response message will return the *MediusWorldID* and *MediusApplicationType* to determine if the player is in a chat channel or in-game.

## Searching for a Game

The **MediusFindWorldByName()** function (with *MediusFindInWorldType* set to "FindInGameWorld") searches for a 'game world object' by *Name* (exact string match). The response message will return the *MediusWorldID* of the 'game world object' and other detailed information.

### **Getting Game World Object Information**

Given a *MediusWorldID*, the **MediusGetGameInfo()** function will return detailed information about a 'game world object', which is the Medius platform's representation of an active DME 'game world'. Detailed game information may include the following (which may change at runtime due to 'world reports'):

- 1. The current GameLevel (which can change from, for example, level 1 to level 2)
- 2. The required PlayerSkillLevel (for example, novice or expert)
- 3. The current *PlayerCount* (calculated from the number of incoming 'player reports')
- 4. The current GameStats your application may display special UI graphics based on this field
- 5. The GameName
- 6. The RulesSet (for example, friendly fire enabled/disabled)
- 7. GenericField(1,2,3) use of this information is application-specific
- 8. The WorldStatus indicates that the DME 'game world' is in one of the following states: Inactive, Staging, Active, or Closed
- 9. The GameHostType indicates the type of game: client/server, integrated server, peer-to-peer, or LAN

### Retrieving a List of Players in a Game World Object

Calling **MediusGetGamePlayers()** will return a list of all of the players associated with a specified 'game world object'.

Players connected to a DME 'game world' are required to send 'player reports'; these reports are routed to the 'game world object' (using *MediusWorldID*) residing on the Medius platform. When the 'game world object' receives these reports, the user's 'player object' is added to the 'game world object's list of players in this world. If a player connected to a DME 'game world' never sends a player report, the 'game world object' will never know that the player is connected and the Medius platform (lobby) will not have accurate information about the actively running DME 'game world's state. A 'game world object' will remove a 'player object' from its player list if the user either stops calling **MediusUpdate()** or if **MediusUpdateClientState()** is called with *LeftGameWorld*.

The Medius platform will retrieve the list of players, returning them one-at-a-time to the client. The *EndOfList* field is set to 1 when the last player in the list has been returned.

**Note:** Currently, the player list returned is in no particular order. If you need ordering performed, buffer the list into your own collection type and sort it.

# **Retrieving a List of Game World Objects**

Calling **MediusGetGames()** (and **MediusGetGames\_ExtraInfo()**)will return a list of 'game world objects' accessible by the current *ApplicationID*. The Medius platform is capable of listing 'game world objects' for multiple game applications simultaneously. However, users from one application will not be able to see other 'game world objects' from another application.

The Medius platform will retrieve the list of 'game world objects', returning them one-at-a-time to the client. The *EndOfList* field is set to 1 set to 1 when the last 'game world object' in the list has been returned.

If more detail is required about individual 'game world objects', a **MediusGetGameInfo()** call can be performed to retrieve all available information about the specified 'game world object'. By calling **MediusGetGames\_ExtraInfo()** you can get information that would otherwise calls to both to **MediusGetGames()** and **MediusGetGameInfo()**.

#### Controlling the Number of 'Game World Objects' Returned

You can regulate the number of 'game world objects' returned to the requesting client (to manage bandwidth usage) with the *PageID* and *PageSize* fields of the **MediusGameListRequest** structure.

### Example:

```
Set PageSize = 10 and PageID = 1 to get 'game world objects' (1–10).
Set PageSize = 10 and PageID = 2 to get 'game world objects' (11–20).
Set PageSize = 10 and PageID = 3 to get 'game world objects' (21–30).
And so on...
```

**Note:** Currently, the 'game world object' list returned is in no particular order. If you need some sort of ordering performed, buffer the list into your own collection type and sort.

# **Getting Player Object Information**

The **MediusGetPlayerInfo()** function (via *AccountID*) will return detailed information about a given player (no personal account profile information is ever exposed). Response message information includes:

- 1. AccountName Name of the player with the given AccountID.
- 2. ApplicationID Current game that player is playing (your application would have to know other *ApplicationID*s beforehand. (Example: Soccer, Football, and Baseball applications may share the same Medius platform but each would have their own *ApplicationID*; thus, an "Online Community" is created for these sports titles.)
- 3. PlayerStatus Indicates if a player (via AccountID) is Disconnected, in a chat channel, or in-game.
- 4. ConnectionClass This is of the type MediusConnectionType (set during MediusSessionBegin()) which indicates if the given player has a Modem or Broadband connection.
- 5. Stats Current Stats info for that player. Can be used for keeping track of x-number of score fields, and/or packing special data (perhaps to display lobby avatar information).

# **Getting the Total Game World Object Count**

The **MediusGetTotalGames()** function will return the total number of 'game world objects' created for a given *ApplicationID*. This will return all 'game world objects' running on each MPS.

**Note:** If your application supports co-location, then the total count of 'game world objects' will only be for a given "region" (since *LocationID* is stored in the user's 'player object', this will be calculated automatically).

# **Getting the Total Player Count**

The **MediusGetTotalUsers()** function will return the total number of users connected to the Medius platform for a given *ApplicationID*.

**Note:** If your application supports co-location, then the total count of users will only be for a given "region" (since *LocationID* is stored in the user's 'player object', this will be calculated automatically).

# Game World Object Security

The **MediusGetWorldSecurityLevel()** function (with *MediusApplicationType* set to "Game") will allows us to determine the security state of the given 'game world object'. The response message will return a *MediusWorldSecurityLevelType* field that indicates if the 'game world object' is: *Public* (anyone may join), *PasswordProtected* (**MediusJoinGame()** requires a password "*GamePassword*" to be submitted), or *Closed* (no further **MediusJoinGame()** calls will succeed on this given 'game world object'). A successful

**MediusJoinGame()** response message contains the *NetConnectInfo* of the DME 'game world' you wish to **NetConnect()** with.

**Note:** A 'game world object's password is initially set during creation time via **MediusCreateGame()** or **MGCLCreateGameOnMeRequest()**. A 'game world object's password can change while a game is in progress due to a change of the password field as part of an incoming 'world report'.

## **Creating a Game**

Creating an online game is achieved through the Medius API via either the **MediusCreateGame()** or **MGCLCreateGameOnMeRequest()** calls. Based on whether your application uses either a "Client/Server" or a "Peer-to-Peer" network topology, refer to the following diagrams (Figure 2 and Figure 3) in the "Reporting (Maintaining Medius Platform Connections and Objects)" section to help in the discussion of creating games.

#### If Creating a Client/Server Game

- 1. A DME 'game world' is a single instance of a game that resides on a DME Game Server (GS). Thus, a client can only be connected to a single DME 'game world' on a GS at any one time.
- 2. A GS hosts a collection of DME 'game worlds' that are indexed by "WorldID".
- 3. A call to **MediusCreateGame()** causes the MUM to manage the transaction of creating/starting a 'game world' on a GS.
- 4. If the transaction was successful, a corresponding 'game world object' will be created on the MUM and a "MediusWorldID" will be generated to index this object.
- 5. If no players join this game within 120 seconds, this 'game world object' will automatically timeout. The user that called **MediusCreateGame()** will still need to call **MediusJoinGame()** to join the DME 'game world' they just created.
- 6. A MUM 'game world object' encapsulates three things: Information about an active DME 'game world' running on a GS, connection information to this 'game world', and a list of players connected to this 'game world'. The accuracy of the data encapsulated within a 'game world object' (after being created) is dependent on the various report messages coming from all the clients connected to the corresponding active 'game world'.

#### If Creating a Peer-to-Peer Game

- 1. A DME 'game world' is a single instance of a game that resides on a peer-to-peer 'host'. This 'game world' is created with a call to **NetHostPeerToPeer()** (which is used both for Online and LAN peer-to-peer games).
- 2. A peer-to-peer 'host' theoretically can host a collection of DME 'game worlds' that are indexed by "WorldID"; but in practice, a peer-to-peer 'host' will only ever have 1 active 'game world' running (with WorldID set to 1).
- 3. A call to **MGCLCreateGameOnMeRequest()** causes the MUM to manage the transaction of registering/posting a peer-to-peer host's 'game world' with the Medius platform.
- 4. If the transaction was successful, a corresponding 'game world object' will be created on the MUM and a "MediusWorldID" will be generated to index this object.
- 5. Unlike a Client/Server game, the player that called **NetHostPeerToPeer()** will not need to call **MediusJoinGame()** to connect to the DME 'game world' created on the host (since the hosting player is assumed to be already connected to itself).
- 6. A MUM 'game world object' encapsulates three things: Information about an active DME 'game world' running on a peer-to-peer 'host', connection information to this 'game world', and a list of players connected to this 'game world'. As above, the accuracy of the data encapsulated within a 'game world object' (after being created) is dependent on the various report messages coming from all the clients connected to the corresponding active 'game world'.

### Joining a Game

The **MediusJoinGame()** function is used to request connection information from a 'game world object' (via *MediusWorldID*) to join an existing DME 'game world'.

#### Joining Either a Client/Server Game or a Peer-to-Peer Game

For both client/server games and peer-to-peer games, a player in the application's lobby can get a list of games (via **MediusGetGames()** – which enumerates all the current 'game world objects') then requests to join a given 'game world' (via **MediusJoinGame()** – using the respective *MediusWorldID*). If the join request was successful, the DME 'game world's connection information (*NetConnectionInfo*) will be returned so that a **NetConnect()** to this 'game world' can take place.

**Note:** If the corresponding **NetConnect()** to the DME 'game world' is successful, then the client will have two simultaneous connections established – connected both to an MLS and to a GS (or peer-to-peer 'host').

It is important to note that the Medius Connection is maintained throughout the online session and is used for sending game-related report messages to the Medius platform while a player is in-game.

If the Medius Connection is lost, in-game play may continue, but once that game has completed the user will need to initiate a new connection to the MAS to begin a new session.

### **Vote Player Out of a Game**

The **MediusVoteToBanPlayer()** function provides the client with the ability to vote players out of a game who are observed to be cheating or otherwise undermining the spirit of good game play.

While a game is in progress, players that observe another player cheating or otherwise behaving undesirably can cast a vote with Medius to kick the player out of the game and ban him/her from re-joining the game. A client can only submit one vote per player, i.e., a player cannot submit multiple votes for the same offending player. Vote counts for each player are maintained by Medius. When a vote comes in for a player and his/her vote count is incremented, a check is made if the updated vote count has exceeded a specified threshold. Threshold is a configurable percentage of the current player count in the game. If the threshold is reached, the player will be banned from the game (and added to the game's banned player list). Also, a player disconnect message will be sent from Medius to either the DME Game Server (for client-server games) or to the peer-to-peer Host, which in turn will forcefully close the player's game connection.

### **Design Considerations**

When leveraging MediusVoteToBanPlayer() functionality, take these issues into consideration:

- A client side ban vote tallying system must still be managed by the client application and therefore
  employ whatever voting criteria is valid for the game. When a vote is cast, use a DME Net Message
  to send a message to all the players in a given game. Each application should manage their own tally
  count and it is up the application if they wish to display to the offending player's current ban vote
  count.
- 2. If and when a ban vote count threshold has been reached to ban a player, all clients currently in the game should call **MediusVoteToBanPlayer()** to submit their 'vote' to ban the player from the game. Having ALL clients submit their vote concurrently, 'distributes' the responsibility of kicking a player across all clients instead of a single client which would have all sorts of problems. Thus, in the case of a 20-player game, each client application will have their own tally count, and if (say) 11 votes to ban a player is received (the determined client side threshold) over a period of time, each application will automatically call **MediusVoteToBanPlayer()** (all 20 clients "even the player's client application that is being reported as the offending client" will call this function to ensure the ban takes place). Even if the player has 'hacked' the game with a cheating device to prevent their **MediusVoteToBanPlayer()** to be called, the other 19 clients will still succeed. In practice, this works very well. Even if a number of

- clients disconnected of their own free will right when this happened, the server side ban count threshold will scale due to the active user count.
- 3. The MediusVoteToBanPlayer() function is NOT meant to support allowing players to randomly submit votes to Medius to ban a player for whatever reason they want throughout the life of a game. This is too open to abuse there will always be abusers and we are not signing on to provide the 'perfect, abuse-free, game-generic' solution.
- 4. The **MediusVoteToBanPlayer()** function is a tool to enforce a ban on a player (once the game's vote tally system has been triggered to actually ban a player) and prevent them from being able to rejoin a game once disconnected.
- 5. For client-server applications, if a player has been banned the DME Game Server will auto-disconnect the player from the game.
- 6. For peer-to-peer applications, there is a *DmeClientIndex* as part of MediusServerJoinGameResponse (MGCL API) that the host needs to set for incoming clients attempting to join (this is the index of the reserved player slot as seen by the DME). MGCLInitializeInParams also has a MGCLServerDisconnectPlayerCallback that the peer-to-peer host will get triggered if the Medius servers have declared it is time to ban a player from the game. For peer-to-peer applications, if a player has been banned the peer-to-peer host will have their MGCLServerDisconnectPlayerCallback triggered with the *DmeClientIndex* of the player that needs to be disconnected. The host should then send a DME Net Message to that player telling them to disconnect themselves from the game.

55

# **Account Management**

The following Medius functions associated with 'Account Management' are described in this section:

 MediusAccountDelete() - Requests to delete an existing account MediusAccountGetID() Gets AccountID from AccountName

 MediusAccountGetProfile() - Gets an account profile MediusAccountUpdatePassword() Sets an account password MediusAccountUpdateProfile() - Sets an account profile

 MediusAccountUpdateStats() Sets an account stats

## **Deleting an Account**

The MediusAccountDelete() function is used to request to delete the currently logged-in account.

### Getting an Account ID

The MediusAccountGetID() function is used to determine the AccountID of a player with a given AccountName.

### **Getting an Account Profile**

The MediusAccountGetProfile() function is used to retrieve profile information of the currently logged-in account. Each application decides if they wish to have account profiles persisted for each user. Profiles are nice to have for creating mailing lists, etc.

### Updating an Account Password

The MediusAccountUpdatePassword() function is used to update the password of the currently loggedin account.

### **Updating an Account Profile**

The MediusAccountUpdateProfile() function is used to update the profile of the currently logged-in account. Each application decides if they wish to have account profiles persisted for each user. Profiles are nice to have for creating mailing lists, etc.

### **Updating Account Stats**

The MediusAccountUpdateStats() function is used to update the Stats field of the currently logged-in account. Each application will determine what value the Stats field is used for. For example, Stats can be used to keep track of wins or losses and/or can also be used in the case if you display special "lobby" avatar information.

# **Buddy Lists**

Every user account has a buddy list (anonymous users do not), which is stored in the Medius database and is managed through the following Medius API calls:

MediusAddToBuddyList()

MediusBuddyAddConfirmation()

MediusBuddyGetPermission()

MediusGetBuddyInvitations()

MediusGetBuddyList()

MediusGetBuddyList ExtraInfo()

MediusRemoveFromBuddyList()

Adds a player to buddy list

- If confirmation is required, grants permission - If confirmation is required, asks for permission

Gets buddy invitations

- Gets players in buddy list

- Gets players in buddy list

Removes a player from buddy list

# Retrieving a Player's Buddy List

- 1. Call MediusGetBuddyList() (or MediusGetBuddyList\_ExtraInfo()).
- 2. The Medius platform will guery the database for all buddies associated with the current player. The server will then respond with one or more MediusGetBuddyListResponse messages. The response message for each buddy will indicate if they are:
  - a. Disconnected User is not logged in the Medius platform.
  - b. InAuthWorld User's 'player object' is not yet in an authenticated state.
  - c. InChatWorld User's 'player object' is in a lobby state.
  - d. InGameWorld User's 'player object' is in an in-game state.

### Adding a User to a Player's Buddy List

- 1. Populate the MediusAddToBuddyListRequest structure with the AccountID of the user to be added.
- 2. Call **MediusAddToBuddyList()**. The Medius platform will add the user associated with the AccountID in the request message to the buddy list of the user associated with the SessionKey field in the request message.

## Removing a User From a Player's Buddy List

- 1. Populate the MediusRemoveFromBuddyListRequest structure with the AccountID of the user to be removed.
- 2. Call MediusRemoveFromBuddyList(). The Medius platform will remove the user associated with the AccountID in the request message from the buddy list of the user associated with the SessionKey field in the request message.

# **Buddy List Permissions**

Optionally (as designed by the application developer), a player (source) can be required to obtain permission from another player (target), prior to adding that player to a buddy list (both players must be online). This process consists of sending a request message for permission to the target player who will then accept or deny the request. The MLS forwards the target player's response message to the source player. If the request for permission was accepted, the source player proceeds to call MediusAddToBuddyList() as described above.

### **Requesting Permission**

- 1. Populate the **MediusBuddyGetPermissionRequest** structure with the (target) *AccountID* of the desired user to request permission.
- 2. Call the MediusBuddyGetPermission() function.

### Responding to a Request for Permission

(If currently online) The callback function that handles a forwarded request message for permission (MediusTypeAddToBuddyListFwdConfirmationRequestCallback) is registered at initialization via MediusInitialize() or MediusInitializeBare().

**Note:** It is general practice to reassign the callback function above to NULL when the game starts, unless your game can handle buddy list invitations while in game.

(If offline, then online) Call **MediusGetBuddyInvitations()** to request a list of buddy list invitations while offline. Players that call **MediusBuddyGetPermission()** with account information of a player that is offline will be queued in the Medius Database for the offline user (queue max size is currently 64).

When the request for permission (**MediusAddToBuddyListFwdConfirmationRequest**) message is received by the targeted player, the following message should appear in your application's GUI:

Allow "Player's Name" to add "You" to their buddy list? (Accept/Deny)

The targeted player will then populate the **MediusAddToBuddyListFwdConfirmationResponse** data structure with **MediusCallbackStatus** = RequestAccepted or RequestDenied.

To send the target player's response message, call **MediusBuddyAddConfirmation()**. The server will forward this message to the source player.

# **Ignore Lists**

Every user account has an ignore list (anonymous users do not), which is stored in the Medius database and is managed through the following Medius API calls:

MediusAddTolgnoreList()
 MediusGetIgnoreList()
 Gets players in ignore list

• MediusRemoveFromIgnoreList() – Removes a player from ignore list

A player will not receive Medius chat messages from users in their ignore list.

# Retrieving a Player's Ignore List

- Call MediusGetIgnoreList().
- 2. The Medius platform will query the database for all players ignored associated with the current player. The server will then respond with one or more **MediusGetIgnoreListResponse** messages. The response message for each ignored player will indicate their *AccountID* and *AccountName* as well as if they are:
  - a. Disconnected User is not logged in the Medius platform.
  - b. InAuthWorld User's 'player object' is not yet in an authenticated state.
  - c. InChatWorld User's 'player object' is in a lobby state.
  - d. InGameWorld User's 'player object' is in an in-game state.

## Adding a User to a Player's Ignore List

- Populate the MediusAddTolgnoreListRequest structure with the AccountID of the user to be added.
- 2. Call **MediusAddToIgnoreList()**. The Medius platform will add the user associated with the *AccountID* in the request message to the ignore list of the user associated with the *SessionKey* field in the request message.

## Removing a User From a Player's Ignore List

- 1. Populate the **MediusRemoveFromIgnoreListRequest** structure with the *AccountID* of the user to be removed.
- 2. Call **MediusRemoveFromIgnoreList()**. The Medius platform will remove the user associated with the *AccountID* in the request message from the ignore list of the user associated with the *SessionKey* field in the request message.

# **Medius Dynamic List System**

#### Introduction

The Dynamic List service (DList) is designed to provide an API that allows the game developer a way to subscribe to the various list content available through the Medius server set.

This system is a departure from the style of previous Medius APIs. In order to provide a completely customizable content delivery mechanism, DList was built upon a simple meta-object protocol. This allows the game developer to subscribe to specific lists (e.g., CLAN, BUDDY, etc.) and to choose which data fields and events the game receives.

The DList service delivers events and data from multiple non-synchronized data and event sources. Because of this, there will be times when rows will be partially populated until the data is available.

### Interface

Since DList is a meta-object protocol, the API has been tailored to reflect the nature of the object system. Each object within the protocol is accessed through an interface structure.

```
typedef const struct
{
    ...
    MediusBool (*refresh) (MediusDListSubscription *pSubscription);
    ...
} MediusDListInterface;
```

In order to manipulate an object, the developer must first obtain a pointer to the interface implementation.

```
MediusDListInterface *gpDListInterface;
int main()
{
    gpDListInterface = GetMediusDListInterface();
    ...
}
```

The developer can then utilize the interface to manipulate and interact with the meta-objects and the Medius Dynamic List service.

```
MediusBool doBuddyRefresh()
{ return gpDListInterface->refresh( pMyList ); }
```

# **Type System**

The Dynamic List service (DList) is built upon a simple meta-object protocol. Objects within this protocol are specified and accessed via the MediusDType system (DType).

A DType combines the DMetaType defined by SCE-RT with a field map (MediusDFieldMap) that the developer uses to describe how to access a game object.

After you have created a valid field map, the developer creates a DType that can be used throughout his program to interact with DList objects.

While creation of a DType is relatively efficient, it does involve walking the supplied field map and allocating a DType object. To reduce this overhead, you should allocate types early and re-use them throughout the life of your game.

**Note:** As with all resources that are allocated, a type must be destroyed when it is no longer needed. A type references internal Medius data structures and is therefore only valid AFTER a call to the **MediusInitialize()** and BEFORE the call to **MediusClose()**. Every DType should be freed BEFORE calling **MediusClose()**.

With the created type, you can now subscribe to a list:

```
gpDListInterface->subscribe ( &pSubscription
, &transactionId
, MEDIUS_DLIST_BUDDY
, 0
, 0
, 0
, gpMyBuddyObjDType
, MEDIUS_DLIST_ALL_EVENTS
, pMyUserCallback
, pUserData );
```

Then, update your game object from an argument list:

The following is a more complete example that includes how to define a field map reference.

### Callbacks

After a subscription is established, the game will receive solicited and unsolicited events related to that subscription on the registered callback.

The user callback of the game needs to address several different reactions to events that are delivered from the server.

The following are exceptions that may dictate specific reactions to errors and exceptional events from the server related to this or to all subscriptions.

```
if (pExcept)
{
    Log("Received exception extent %d error %d",pExcept->exceptExtent, pExcept->error);
    switch(pExcept->exceptExtent)
    {
        case MEDIUS_EXCEPT_NONE:
            Log("This should never happen");
            break;
        case MEDIUS_EXCEPT_ABORT_TRANSACTION:
            MyMarkTransactionForRetry(pList, transactionId, pExcept->retryTimeout);
            MymarkTransactionForRetry(pList, transactionId, pExcept->retryTimeout);
            PExcept->retryTimeout);
```

```
break;
case MEDIUS EXCEPT FAIL TRANSACTION:
    MyMarkTransactionFailed(pList, transactionId);
case MEDIUS EXCEPT ABORT CONTEXT:
    MyMarkListBad(pList);
    break;
case MEDIUS EXCEPT FAIL CONTEXT:
   MyMarkListBad(pList);
    MyMarkSessionBad();
    break;
case MEDIUS EXCEPT FAIL SESSION:
   MyMarkListBad(pList);
   MyMarkSessionBad();
   break;
default:
    Log("A new exception that we don't handle");
return;
```

This depicts tracking of transaction lds to ensure request/response time.

```
if (transactionId)
{
    MyStopWating(pList, transactionId);
}
```

The manipulation of the game's list object is related to the MEDIUS\_DACTION enumeration sent from the server. This action dictates how the *pArgList* containing the data sent from the server would be applied to the game's list object.

```
if (rowsLeft > 0)
   MyMarkListInUpdate(pList);
if (pArqList)
   switch (action)
   case MEDIUS DACTION NOEVENT:
       Log("This should never happen!");
       break;
    case MEDIUS DACTION ERROR:
       Log("Recieved error exception handled above");
       break;
    case MEDIUS DACTION STATUS:
        Log("Recieved status %d", status);
        break;
    case MEDIUS DACTION UPDATE:
       pRow = MyFindRow( pList, rowId );
        if (pRow)
            gpMediusDList->popRowData( pArgList, pList->pType, pRow );
       break;
   case MEDIUS DACTION ADD:
        pRow = MyAllocRow( pList, rowId );
        gpMediusDList->popRowData( pArgList, pList->pType, pRow );
        break;
```

```
case MEDIUS_DACTION_DELETE:
    MyDeleteRow( pList, rowId );
    break;
case MEDIUS_DACTION_REFRESH:
    pRow = MyFindRow( pList, rowId );
    if ( ! pRow )
    {
        pRow = MyAllocRow( pList, rowId );
    }
    gpMediusDList->popRowData( pArgList, pList->pType, pRow );
    break;
    default:
        Log("New action %d, we don't handle and ignore", action);
}

if ( rowsLeft == 0 )
    MyMarkListOutOfUpdate( pList );
}
```

## **Tailoring the Subscription**

The DList API provides a customizable content delivery mechanism. The content of a subscription and the events that the game receives are tailored not only through the specified service level but also the fields specified in the DType through the field map.

In addition to controlling which information will trigger a callback, the developer can associate a callback with a specific interest callback, and then he can associate that interest callback with multiple lists.

#### Subscribing

In order to receive events, you must describe which events you want to receive and on which callback you want to receive it.

Each subscription is relative to a single list. A specific list is indicated by its *MediusListId* and it *relationId*. While you may subscribe to multiple lists with the same listId, each must have a unique *relationId*:

```
(e.g. relationId == clanID forMEDIUS DLIST CLAN MEMBER).
```

With a valid list indicated, specify the DType for the subscription. The DType will tell the subscription how to unpack data to your list object. It will also indicate which events you are interested in receiving. See "".

To further specify which events to receive, indicate the service level at which you are interested. See MediusDListServiceLevel.

**Note:** A subscription is only valid while connected as a lobby server. You should unsubscribe before you change from one lobby to another, and re-subscribe when you attach to the new lobby. Since it is impossible to fully guarantee that all list events will be delivered at all times when switching lobby servers, it is necessary to re-create/subscribe to any list whenever you switch lobby servers.

### Setting an Interest Callback

To filter the events and data from multiple lists, the developer can associate a callback (**pUserCallback**) with those lists along with the fields that the callback would like to see through the specified type (*pType*).

One of the most important characteristics of an interest callback is that it receives only one event, regardless of whether there are overlapping members on associated lists. For example, if a player is a member of both you Buddy and ClanMember list, and if his online status changes, an interest callback associated with both the Buddy and ClanMember list will only receive ONE event.

**Note:** The fields specified by *pType* are used to filter callback events rather than actually subscribe to those fields. Only events that contain all of the desired fields trigger the callback.

### Associating an Interest Callback

In order for an interest callback to receive events, it must be associated with at least one subscription. Once it is associated, it allows the developer to select the specific subscriptions (within a common interest) to propagate events to the interest callback.

#### Usage

```
gpDListInterface->associateCB( pMyPlayerInterestCB, pMyBuddyListSubscription );
```

This will associate **pMyPlayerInterestCB** with *pMyBuddyListSubscription*, so that any events that are received by *pMyBuddyListSubscription* match the criteria associated with **pMyPlayerInterestCB**. When it is set, then the associated **pInterestCallback** will be called.

### **Service Levels**

The service level tailors the interaction with the server to the specific events that a game is interested in for a list. If the game is not displaying the buddy list, it may only need to know when a player goes off or on line to display a message. This is accomplished by subscribing with the MEDIUS\_DLIST\_CHANGE\_EVENTS service level.

First, you must have a list to update. To maintain this list on a consistent basis requires MEDIUS\_DLEVEL\_ALL\_EVENTS to receive, add, and delete events. It must complete all of these functions to keep this list up-to-date.

By subscribing to MEDIUS\_DLEVEL\_REFRESHED, a refresh will be requested as part of the subscription process.

## **Game List Row Object Declaration**

List row object contains all currently available interest data members.

Your player row list may have any subset of these data members and also have data members that are not related to DList. The name and order within the structure is also unimportant.

It is expected that you may have a different structure for each list type that you subscribe to (e.g., BUDDY, CLAN\_MEMBER, etc.)

The Type and Size of these fields MUST match these definitions:

```
typedef struct
   int.
                           PlayerID;
                           LobbyID;
   int
                           GameID;
   MediusPlayerStatus PlayerStatus;
                           PlayerName [ACCOUNTNAME MAXLEN];
   char
   char
                           LobbyName[LOBBYNAME MAXLEN];
                           GameName[GAMENAME MAXLEN];
   char
   unsigned char
                           PlayerStats[ACCOUNTSTATS MAXLEN];
                           PlayerOnline;
   unsigned char
} PlayerListRow ;
```

## **Field Specification Definition**

The other way that the developer tailors the content, and to an extent the events that the game receives, is by specifying the fields the game wants to receive. This reduces the bandwidth to only what is necessary to deliver the fields in which the game is interested.

In addition, since some events are tied to specific fields, these events will also be culled, if the field is not required.

The field specification maps individual structure members to the interest fields. The specifications are checked within gpDTypeInterface->create() and an error will return if any specification does not match the one from these definitions.

It is expected that you will not only have a different field map, specification, and DType for each list type (e.g., BUDDY, CLAN\_MEMBER etc.), but that you will also have a different set for each subset of fields for which you want to subscribe. Another example of this is a DType which is used to set an interest callback.

The order of these field definitions is important. You may use any subset of these fields. (Comment out the ones you do not need.).

**Note:** Remember to change the type name of the structure to your structure's type name and the structure member names to your structure's member names.

### **Field Map Definition**

The field map serves as a description of the Field Specification list to feed into gpDTypeInterface->create().

Notice that the type specifier (static) is external to the **DEF\_FIELD\_MAP()** macro so that you may customize the visibility of the map. In practice, there should never be a reason to declare a field map as anything other than static.

```
static DEF_FIELD_MAP(PlayerListRow_FieldMap_, PlayerListRow_Spec_, PlayerListRow_);
```

# **DType Declaration**

The type points to the field map so the field map and field specification should maintain at least the same life expectancy as the type. Usually defining the field map, specification, and static is sufficient since they do not change.

**Note:** Although a type may be declared static, it depends upon values within Medius. Because of this, a type is only valid between **MediusInit()** and **MediusClose()**. A type should be created AFTER **MediusInit()** and should always be destroyed BEFORE **MediusClose()**.

```
static MediusDType *pPlayerListRow DType = NULL;
```

### **DType Creation**

**Note:** Creating a type allocates memory that must be destroyed when no longer useful. In addition, since a type is allocated within Medius, it is advisable to create your types immediately after **MediusInit** to reduce the possibility of fragmentation.

### **DType Destruction**

Although a type may be declared static, it depends upon values within Medius.

Because of this a type is only valid between **MediusInit()** and **MediusClose()**. A type should be created AFTER **MediusInit()** and should always be destroyed BEFORE **MediusClose()**.

```
static void
DestroyPlayerInterestType()
{
    gpDTypeInterface->destroy( pPlayerListRow_DType_ );
    pPlayerListRow_DType_ = 0;
}
```

# **Platform Requirement Functionality**

Certain functions are required and must be used in specific ways, as described in the *Medius Platform Requirements and Guidelines* document. Refer to the *Medius Platform Requirements and Guidelines* document for specific information about these requirements, as well as the appropriate use of the functions.

After a player has created a "session" with the Medius platform (while still connected to the MAS) and before the account login (or anonymous login), the player should first be presented with the 'Usage Policy' then the 'Privacy Policy', and finally with any application specific 'Announcements'.

Medius API functions discussed in this section:

MediusGetPolicy – Gets 'usage policy' and 'privacy policy'

• MediusGetAnnouncements – Gets all unread announcements

MediusGetAllAnnouncements – Gets all announcements

MediusSetMessageAsRead
 Marks a particular announcement as read

### Retrieving the Usage Policy and the Privacy Policy

There are two types of policies that must be present to a user before that are allowed to play online – Usage Policy and Privacy Policy. These policies are entered into the database by production and technology personnel.

Invoking **MediusGetPolicy()** with the desired policy type will return x-number of **MediusGetPolicyResponse** messages (each message is of size POLICY\_MAXLEN). Buffer up these messages until you receive *EndOfText* = 1 and then display to the user.

## **Retrieving Announcements**

Announcements are entered into the database by production and technology personnel, **not** by users. Announcements are retrieved through **MediusGetAnnouncements()** or **MediusGetAllAnnouncements()** API calls.

When a new announcement is stored in the database, it is keyed to be specific to a certain application, or applicable system-wide to all application users.

Calling **MediusGetAnnouncements()** will only retrieve unread announcements keyed to the application the user has logged in with. Alternatively, calling **MediusGetAllAnnouncements()** will return all of the application-specific messages **in addition to** all system-wide announcements (which will also then be marked as "read").

Invoking MediusGetAnnouncements() will return x-number of MediusGetAnnouncementsResponse messages (each message is of size ANNOUNCEMENT\_MAXLEN). Buffer up these messages until you receive *EndOfText* = 1 and then display to the user. This will return all unread announcements.

Invoking MediusGetAllAnnouncements() will return (just like above) x-number of MediusGetAnnouncementsResponse messages – this time, you'll just get more response messages. This will return all announcements regardless of their 'marked-as-read' flags.

Invoking **MediusSetMessageAsRead()** will mark a particular announcement as read (via the *AnnouncementID* returned from **MediusGetAnnouncementsResponse**.

### **Co-location**

Medius platform servers can be deployed in a variety of different ways to help PlayStation®2 clients find lobby servers and game servers (and peer-to-peer hosts) that may be closest to their "region". When a client is presented with a list of "regions" (while connected to a MAS), the client should pick the "region" closest to where he/she is playing in order to (hopefully) minimize Internet traffic and improve performance by minimizing latency. The process of strategically deploying Medius platform servers in this manner is called co-location.

Medius functions that deal with co-location are:

MediusGetLocations()
 Gets a list of locations "regions"

MediusPickLocation()
 Picks a location "region"

### **Co-location Example**

As an example of co-location, you may, for a given application:

- 1. Deploy 1 MUM, 1 (oracle-based) Medius database, and 4 MAS servers in San Diego. A DNS lookup of "mygame.mycompany.com" will return the IP address of the load-balancer that will direct the incoming client to 1 of the 4 MAS servers that have been set up. The application will always initially connect to the MAS servers in San Diego to establish an authenticated state and to retrieve a list of locations "regions" to pick from.
- 2. Deploy three MLS servers in each location; for example, three each in San Diego, Chicago, New York, and San Francisco for a total of 12 MLS servers. Each would connect to the MUM in San Diego. Each of these MLS servers would have their configuration file "medius.txt" set with a "LocationID" from 0-N. You may assign San Diego LocationID=0, Chicago LocationID=1, New York LocationID=2, and San Francisco LocationID=3. (You can of course add and/or remove MLS servers at anytime to or from any geographic location). After you assign LocationIDs, update the co-location table in the Medius database hosted in San Diego.
- 3. Just as above, you would match 1-to-1 an MPS for each MLS (though in practice, you would actually scale this number based on load); therefore, a MPS server would be set up in the same locations as the MLS servers and, of course, each would connect to the MUM in San Diego. Each of the MPS servers would have their configuration file "mps.txt" set with the same "LocationID" that you set up for the MLS servers.
- 4. If the application were a Client/Server game, you would also need to set up DME Game Servers at each of the locations. Each of the GS servers would have their configuration file "DmeMedius.cfg" set with the same "LocationID" that you set up for both the MLS and MPS servers. When the GS servers are brought online, they will initially connect to the MAS, then automatically be redirected to a MPS in that "region".

By choosing a specific location, a request for a game/chat channel list will be limited to games/chat channels hosted by game/lobby servers in the same "region". Similarly when creating a game/chat channel, it will be hosted by a game/lobby server with the same *LocationID* as the player who originated the request.

If the application is a Client/Server game, a user will want to choose a GS that is closest to them, to have the best possible gaming experience. This is also true if you are the 'host' of a peer-to-peer game, and Chicago (for example) is selected for the "region" after you logged in. If other players join the game, you know that they also picked Chicago as their "region". Therefore, it's possible that the round trip latencies to and from each of the peers in the game would be minimal (in contrast to peers spread across the world).

#### Co-location Process

**MediusGetLocations()** and **MediusPickLocation()** allow a client to retrieve a list of locations and select a location respectively. Once a *LocationID* has been 'picked', this will automatically be stored in the player's 'player object' on the Medius platform, and no other Medius API function will ever ask for this *LocationID* again.

Recommend process if using co-location:

- 1. UI prompts user for username and password (saves until actual login at step 8).
- 2. User connects to the MAS.
- 3. User starts a "session" with the Medius platform.
- 4. User retrieves Usage Policy, Privacy Policy, and application's Announcements.
- 5. Application then calls **MediusGetLocations()** to get a list of Locations. The application then would display these locations to the user.
- 6. User will scroll through the available locations and select one. The application would then call **MediusPickLocation()**. If success, that *LocationID* will be stored in the user's 'player object' on the Medius platform. The developer will never have to worry about passing in *LocationID* to any other Medius functions since it is automatically handled from this point on.
- 7. After a location has been selected, the user may now login (MediusAccountLogin() or MediusAnonymousLogin()). The response message to the login will redirect the user to a MLS setup in the "region" they selected. If the account login response message returned a failed status code, either the respective location "regional" Medius servers may not online or somehow the user got disconnected from the network. Contact SCE-RT (scert-support@scea.com) or the respective IT group that upkeeps your SCE-RT Medius servers.
- 8. Call **MediusDisconnect()** (from MAS) then call **MediusConnect()** with the *NetConnectInfo* of the MLS that was returned to you from the **MediusAccountLoginResponse** message.

# **Ladder Management**

To enable Ladders for your title, you must setup a Medius Database Caching Server (MDBCS). The primary purpose of the MDBCS is to unload CPU processing and database transactions from the other Medius platform servers to support Ladder Management.

The following Medius functions associated with 'Ladder Management' are described in this section:

- MediusGetLadderStatsWide()
- MediusGetTotalRankings()
- MediusLadderList ExtraInfo()
- MediusLadderPosition\_ExtraInfo()
- MediusLadderPositionFast()
- MediusUpdateLadderStatsWide()

- Retrieves all ladder stats for given player
- Lists total number of players in ladder ranking
- Retrieves a list of players in a ladder ranking
- Gets a ladder ranking for given player
- Gets the approximate new ladder ranking for a given player
- Sets a player's ladder stats (to be saved to database)

### Getting a Player's Current Ladder Stats and Updating

The **MediusGetLadderStatsWide()** function is used to request for a player's current ladder stats information. Each player has between [0..LADDERSTATSWIDE\_MAXLEN] available ladder categories to save a score to (currently up to 100 categories are available as of the v1.50 release). Each element of the array takes an int value. To set a 'score' for a ladder category, just set a value to the respective element in the array (indexed by *LadderStatIndex*) and call **MediusUpdateLadderStatsWide()** to request to save the new ladder score to the Medius database. Normally, an update to a score is in the form of an addition or subtraction to the current score.

**Note:** A call to **MediusUpdateLadderStatsWide()** will persist the player's ladder stats immediately to the Medius database; however, it will typically take between 1-5 minutes (configurable) for the MDBCS to refresh it's cached ladder rank scores. Therefore, if you need an approximate new ladder ranking score for a player (such as when they finish a game and would like to see how much they may have improved their ladder ranking score) then call **MediusLadderPositionFast()** to get an idea of what their new rank will be. This function will compare the player's old score as seen in the MDBCS cached ladder rank scores and use a sliding window algorithm that will slide up or down looking at neighboring player's raw scores and will return a new position based on this lookup (it will not update the MDBCS's cached ladder ranks).

### **Total Number of Players in a Ladder Ranking**

The **MediusGetTotalRankings()** function is used to request the total number of players in a given ladder ranking. Set the *LadderStatIndex* to get the total number of players that have a non-zero ladder rank score in the respective category.

### Getting a List of Player's in a Ladder Ranking

The **MediusLadderList\_ExtraInfo()** function is used to request a list of player's in a ladder ranking sorted by their rank positions that is calculated by their current rank score. Set *LadderStatIndex* to an index between [0.. LADDERSTATSWIDE\_MAXLEN] to choose which ladder category you wish to get a list of players for. The player with the highest score in the given ladder rank will have a position of 1. Player's that have a rank score of zero will not be returned in this list.

#### Controlling the Number of 'Ladder Ranks' Returned

You can regulate the number of 'ladder ranks' returned to the requesting client (so that you can manage bandwidth usage and GUI lists) with the *StartPosition* and *PageSize* fields of the **MediusLadderList ExtraInfoRequest** structure.

#### Example:

```
Set PageSize = 10 and StartPosition = 1 to get 'ranks' (1–10).

Set PageSize = 10 and StartPosition = 2 to get 'ranks' (11–20).

Set PageSize = 10 and StartPosition = 3 to get 'ranks' (21–30).

And so on...
```

### **Getting a Player's Current Ladder Ranking**

The **MediusLadderPosition\_ExtraInfo()** function is used to determine the ladder ranking of a particular player. Set *LadderStatIndex* to an index between [0.. LADDERSTATSWIDE\_MAXLEN] to choose which ladder category you wish to get a position for. The player with the highest score in the given ladder rank will have a position of 1. If the player has a rank score of zero, MediusNoResult will be returned with position set to zero.

# **Token Management**

The Medius Token Reservation Service provides the application the ability to reserve and release a application-defined ID or "Token" with Medius in order to restrict usage of that Token to a single entity. An entity can be either a Player Account or Clan. The token posted is guaranteed unique within its category. Once a token is reserved, subsequent calls to reserve the same token within the same category will fail until the token is released. Tokens can be added, updated, and deleted. Players can only add account-specific tokens to their own account. Currently, only clan leaders can add clan-specific tokens for their Clan. A Player or Clan leader can reserve multiple tokens.

The following Medius APIs are associated with 'Token Management':

- MediusTokenCategoryType
- MediusTokenActionType
- MediusTokenRequest
- MediusToken()

- Valid token types
- Valid token actions
- MediusToken() request structure
- Request to add/update/remove a token

# Clan Management

Every user account has the ability to manage Clans (anonymous users do not), which is stored in the Medius database and is managed through the following Medius API calls:

#### Clan Management

- MediusCreatClan()
- MediusDisbandClan()
- MediusGetMyClans()
- MediusGetClanByName()
- MediusGetClanByID()
- MediusTransferClanLeadership()

#### Clan Membership Management

- MediusAddPlayerToClan()
- MediusRemovePlayerFromClan()
- MediusGetClanMemberList()
- MediusGetClanMemberList ExtraInfo()

- Gets a list of players in a Clan Gets a list of players in a Clan

- Request to invite player to Clan (by Name)

Request to invite player to Clan (by AccountID)

- Gets Clan information from a given Clan name

- Requests transfer of Clan leadership to another player

- Gets Clan information from a given ClanID

- Requests Clan creation

Requests the disbanding of a Clan

- Requests player addition to a Clan

- Requests player removal from a Clan

- Gets a list of Clan memberships

### Clan Invitations Management

- MediusInvitePlayerToClan()
- MediusInvitePlayerToClan\_ByName()
- MediusCheckMyClanInvitations()
- MediusGetClanInvitationsSent()
- MediusRespondToClanInvitation()
- MediusRevokeClanInvitation()

#### Clan Messages Management

- MediusGetMyClanMessages()
- MediusSendClanMessage()
- MediusModifyClanMessage()
- MediusDeleteClanMessage()
- MediusGetAllClanMessages()
- Get list of Clan messages for given player
- Request to send Clan message

- Get list of Clan invitations

- Respond to Clan invitation

- Revoke Clan invitation

- Get list of Clan invitations sent

- Request to modify Clan message
- Request to delete Clan message
- Get list of all Clan messages

#### Clan Team Challenges Management

- MediusRequestClanTeamChallenge()
- MediusRespondClanTeamChallenge()
- MediusRevokeClanTeamChallenge()
- MediusConfirmClanTeamChallege()
- MediusGetClanTeamChallegeHistory()
- MediusGetClanTeamChalleges()
- Request to perform a Clan team challenge
- Respond to a Clan team challenge
- Revoke Clan team challenge
- Request to confirm Clan team challenge
- Get list of all Clan team challenges ever requested
- Get list of current Clan team challenges

#### Clan Ladder Ranking System Management

- MediusClanLadderList()
- MediusClanLadderPosition()
- MediusGetLadderStatsWide()
- MediusUpdateLadderStatsWide()
- MediusUpdateClanStats()

- Get list of Clan ladder ranks
- Get current Clan ladder rank with given ClanID
- Request to get current Clan ladder stats
- Request to update Clan ladder stats
- Request to update current Clan stats

### Creating a Clan

When a player creates a Clan, they will automatically be designated as the 'Leader' of the newly created Clan. A player can only be the leader of one Clan at a time (i.e. create one Clan), but can have numerous Clan memberships with other Clans. Some applications are designed with the concept of each player having only one Clan membership at a time; nonetheless, this is not a requirement imposed by the Medius architecture.

- 1. Populate the MediusCreateClanRequest structure with the name of the Clan you wish to create.
- 2. Call **MediusCreateClan().** The Medius platform will then attempt to create a Clan for this user. If successful, a response message with a generated *ClanID* will be returned.
- 3. If StatusCode!=MediusSuccess, be sure to transition through your lobby state-machine to handle the current error condition. Possible error conditions (additional to the comment set):
  - a. MediusAlreadyLeaderOfClan (-992) User can only create one Clan per ApplicationID (title).
  - b. **MediusClanNameInUse(-970)** A Clan already exists with the given name.

### Disbanding a Clan

Only the leader of a Clan can disband the Clan.

- 1. Populate the **MediusDisbandClanRequest** structure with the *ClanID* of the Clan you wish to disband.
- 2. Call **MediusDisbandClan()**. The Medius platform will then attempt to disband the given Clan. If successful, a response message with *StatusCode* set to **MediusSuccess** will be returned.
- 3. If *StatusCode!*=**MediusSuccess**, be sure to transition through your lobby state-machine to handle the current error condition. Possible error conditions (additional to the comment set):
  - a. MediusNotClanLeader (-990) User was not the leader of the Clan they requested to disband.

# **Getting a List of Clan Memberships**

A player can only be the leader of one Clan at a time (i.e. create one Clan), but can have numerous Clan memberships with other Clans. The following sequence of events will return a player's current list of Clan memberships.

- 1. Populate the **MediusGetMyClansRequest** structure with a 'Start' number and a 'PageSize' number. Medius lists start with the number '1'. If you set the 'PageSize' to a value of (say) 10 and 'Start' to a value (say) 1, then you will be returned elements 1-10 (thus, setting 'Start' to 2 will return elements 11-20, etc.)
- 2. Call **MediusGetMyClans()**. The Medius platform will then return a **MediusGetMyClansResponse** message for each Clan the player is a member of. If successful, each response message will have the StatusCode set to MediusSuccess. Your application will need to be in a state where it is waiting for a response message with the 'EndOfList' field set to != 0 (thus signaling the end of the list).
- 3. If *StatusCode!*= MediusSuccess, be sure to transition through your lobby state-machine to handle the current error condition. Possible error conditions (additional to the comment set):
  - a. MediusNoResult (1) The user was not a member of any Clan.

### **Getting Clan Information**

Given a ClanID or a Clan's Name, you can request more information about a Clan from the Medius platform. Information returned describes 'Clan Leader', 'Clan Stats', and 'Clan Status' information.

- 1. Given a *ClanID*, call **MediusGetClanByID()**. This will return a **MediusGetClanByIDResponse** message.
- 2. Given a Clan's Name, call **MediusGetClanByName()**. This will return a **MediusGetClanByNameResponse** message.
- 3. If StatusCode!= MediusSuccess, be sure to transition through your lobby state-machine to handle the current error condition. Possible error conditions (additional to the comment set):
  - a. MediusClanNotFound (-971) The Clan was not found.

### **Transferring Clan Leadership**

The leader of a Clan can request to transfer Clan leadership to another player (if this player is not already a leader of a Clan). The old leader will still be a member of the Clan but will no longer be able to perform Clan functions that require Clan Leadership privileges.

- 1. Populate the **MediusTransferClanLeadershipRequest** structure with the *AccountID* of the player you wish to transfer Clan Leadership to. (**Note:** The *NewLeaderAccountName* field is ignored).
- 2. Call **MediusTransferClanLeadership()**. The Medius platform will then attempt to transfer the Clan Leadership status to the given user. If successful, a response message with StatusCode set to MediusSuccess will be returned.
- 3. If *StatusCode!*= MediusSuccess, be sure to transition through your lobby state-machine to handle the current error condition. Possible error conditions (additional to the comment set):
  - a. **MediusNotClanLeader (-990)** The user requesting to transfer Clan Leadership was not the current Clan Leader.

### Adding Members to a Clan

The leader of a Clan can request (from the Medius platform) to add additional members to the Clan. The MediusAddPlayerToClan() call should be used with care because it will add a member to the given Clan without the members consent; therefore, it is recommended to use the MediusInvitePlayerToClan() (or MediusInvitePlayerToClan\_ByName()) (sender) and MediusRespondToClanInvitation() (receiver) calls to manage adding members to a Clan. Nonetheless, a developer may come across the need where MediusAddPlayerToClan() is needed (for example during testing or if a custom application level Clan invitation scheme has been devised).

- 1. Populate the **MediusAddPlayerToClanRequest** structure with the *AccountID* of the player you wish to add to the Clan along with a Welcome message (that will automatically trigger a Medius Clan message to be sent to the new member).
- Call MediusAddPlayerToClan(). The Medius platform will then attempt to add the given user to the leader's Clan. If successful, a response message with StatusCode set to MediusSuccess will be returned.
- 3. If StatusCode!= MediusSuccess, be sure to transition through your lobby state-machine to handle the current error condition. Possible error conditions (additional to the comment set):
  - a. **MediusNotClanLeader (-990)** The user requesting to add a member to the Clan was not the current Clan Leader.

### Removing Members from a Clan

The leader of a Clan can request (from the Medius platform) to remove a member from a Clan. No special messages will be sent to a member that was removed a Clan (this would need to be managed at the application level).

- 1. Populate the **MediusRemovePlayerFromClanRequest** structure with the *AccountID* of the player you wish to remove from the Clan.
- 2. Call **MediusRemovePlayerFromClan()**. The Medius platform will then attempt to remove the given member from the leader's Clan. If successful, a response message with *StatusCode* set to MediusSuccess will be returned.
- 3. If StatusCode!= MediusSuccess, be sure to transition through your lobby state-machine to handle the current error condition. Possible error conditions (additional to the comment set):
  - a. **MediusNotClanLeader (-990)** The user requesting to remove a member from the Clan was not the current Clan Leader.

### Getting a List of Members in a Clan

The following sequence of events will return a list of members (Account Names) in a Clan. Each application must decide if they wish to allow anyone to view a Clan's membership list or if users are only able to view their own Clan's membership list (this is easily managed by *ClanID* utilization).

- Populate the MediusGetClanMemberListRequest (or MediusGetClanMemberListRequest\_ExtraInfo) structure with the ClanID of the Clan you wish to view Clan members with.
- 2. Call MediusGetClanMemberList() (or MediusGetClanMemberList\_ExtraInfo()). The Medius platform will then return a MediusGetClanMemberListResponse (or MediusGetClanMemberListResponse\_ExtraInfo) message for each Clan member. If successful, each response message will have the StatusCode set to MediusSuccess. Your application will need to be in a state where it is waiting for a response message with the 'EndOfList' field set to != 0 (thus signaling the end of the list).
- 3. If StatusCode!= MediusSuccess, be sure to transition through your lobby state-machine to handle the current error condition. Possible error conditions (additional to the comment set):
  - a. MediusNoResult (1) There were no members in the given Clan or the Clan does not exist.

# Clan Invitations Management

The following group of functions facilitates 'Clan Invitations' management. Typically, the workflow is as follows:

- 1. Clan Leader issues a Clan invitation to a target user (**MediusInvitePlayerToClan()** uses a player's *AccountID* while **MediusInvitePlayerToClan()** uses a player's AccountName).
- 2. Target user retrieves their Clan invitations list.
- 3. Target user responds to the Clan invitation they wish to join (by responding with MediusClanInvitationsResponseStatus set to 'ClanInvitationAccept').
- 4. The Medius platform will automatically internally call **MediusAddPlayerToClan()** for a user that responded with a 'ClanInvitationAccept' status.

#### Additional Notes:

- 1. Calling **MediusInvitePlayerToClan()** will send a Clan invitation to target user account (only the Clan Leader can successfully carry out this transaction).
- 2. Calling **MediusGetClanInvitationsSent()** will return a list of Clan invitations sent (only the Clan Leader can retrieve this list). The list returned will only show Clan invitations that target users have not responded to.

- 3. Calling **MediusRevokeClanInvitation()** will revoke a Clan invitation sent (only the Clan Leader can successfully carry out this transaction). If a player has already accepted the Clan invitation, the response message will not be set with a **MediusSuccess** status).
- 4. Calling **MediusCheckMyClanInvitations()** will return a list of Clan invitations sent to 'me' calling user.
- 5. Calling MediusRespondToClanInvitation() allows a user to respond to a Clan invitation that was sent to them. Setting the ResponseStatus field to 'ClanInvitationAccept' will automatically add them to the given Clan. After responding to a Clan invitation, the invitation will be removed from the target client's Clan invitation list. Currently, responding with a 'ClanInvitationDecline' or 'ClanInvitationUndecided' both have the same effect removes the Clan invitation from both the sender and receiver and does not add player to the given Clan. Contact SCE-RT (scert-support@scea.com) if you need a Clan message to be issued to the Clan Leader if a player does not accept a Clan invitation.

### Clan Messages Management

The following group of functions facilitates 'Clan Messages' management. Typically, the workflow is as follows:

- 1. Clan Leader issues a Clan message to their Clan.
- Clan members request a list of all their 'unread' Clan messages. The Medius platform will then
  automatically set each Clan message flagged as 'read' on the Medius platform for each Clan
  message received. A player can still request to re-read Clan messages if needed with the 'GetAll'
  option.

#### **Additional Notes:**

- 1. Calling **MediusSendClanMessage()** will send a Clan message to all Clan members (only the Clan Leader can successfully carry out this transaction). These messages are stored in the Medius Database for each Clan member's account.
- 2. Calling **MediusGetMyClanMessages()** will return a list of all 'unread' Clan messages. Each Clan message received will be marked as 'read' in the Medius Database.
- 3. Calling **MediusGetAllClanMessages()** will return a list of all 'unread' and 'read' Clan messages. This will not flag Clan messages as 'read' in the Medius Database.
- 4. Calling MediusDeleteClanMessage() will delete a Clan message that was sent by the Clan Leader (only the Clan Leader can successfully carry out this transaction. This Clan message will no longer appear when a Clan member calls MediusGetMyClanMessages() or MediusGetAllClanMessages().
- 5. Calling MediusModifyClanMessage() will modify a Clan message that was sent by the Clan Leader (only the Clan Leader can successfully carry out this transaction). Clan members will see the modified Clan message if the call either MediusGetMyClanMessages() or MediusGetAllClanMessages().

# Clan Team Challenges Management

The following group of functions facilitates 'Clan Team Challenges' management. Typically, the workflow is as follows:

- 1. Clan Leader issues a Clan Team Challenge to a target Clan.
- 2. Target Clan retrieves their Clan Team Challenges list.
- 3. Target Clan responds to the Clan Team Challenge.
- 4. Clan Leader (from step 1) retrieves their Clan Team Challenges list.
- 5. Clan Leader (from step 1) confirms Clan Team Challenge.

77

Confirming a Clan Team Challenge just sets the status as 'confirmed'. It is up the application developer on how it wishes to manage 'confirmed' challenges. A custom message can be sent with the 'send' and the 'respond' Clan Team Challenge calls (this should include information on how the Clan Leaders will schedule when to play against each other.)

Design Note: Currently there is no 'Medius Mail System', if so the Clan Leaders could further send correspondence with each other when and how to schedule a time to play.

Additional Notes (only Clan Leaders may successfully carry out these transactions):

- 1. Calling MediusRequestClanTeamChallenge() will send a Clan Team Challenge to the target Clan.
- 2. Calling MediusGetClanTeamChalleges() and MediusGetClanTeamChallegeHistory() will return a list of Clan Team Challenges (both sent and received).
- 3. Calling MediusRespondClanTeamChallenge() will respond to a Clan Team Challenge.
- 4. Calling MediusRevokeClanTeamChallenge() will delete a Clan Team Challenge sent (therefore will no longer show up in a MediusGetClanTeamChalleges() call).
- 5. Calling MediusConfirmClanTeamChallege() allows the Clan Leader that issued the Clan Team Challenge to 'confirm' an 'accepted' Clan Team Challenge.

### Clan Ladder Management

To enable Clan ladders for your title, you must setup a Medius Database Caching Server (MDBCS). The primary purpose of the MDBCS is to unload CPU processing and database transactions from the other Medius platform servers to support Clan ladder management.

The following group of functions facilitates Clan ladder management. Typically, the workflow is as follows:

- 1. After a game is complete, the application calculates a new Clan rank (raw score) to be submitted to the Medius platform. Currently, there are from [0..LADDERSTATS\_MAXLEN] available rankable Clan ladder rank categories to choose from (100 as of v1.50). Typically, the application would save an old Clan rank and increment or decrement the value to create a new Clan rank (possibly scaling the delta based on the other teams Clan rank).
- 2. Any Medius client would then be able to get a sorted list of Clans that indicates which Clan is first place all the way down to last place based on each rankable Clan ladder rank category.

#### **Additional Notes:**

1. Calling MediusUpdateLadderStatsWide() (with the MediusLadderTypeClan enumeration type set) will post a new Clan rank (raw score) to the Medius platform. It is recommended that all necessary rank categories [0..LADDERSTATS\_MAXLEN] are set at once so that only one call to MediusUpdateLadderStatsWide() is needed. Each element of the array takes an int value. To set a 'score' for a Clan ladder category, just set a value to the respective element in the array (indexed by LadderStatIndex).

Note: Currently, only the Clan leader can successfully call this function to post Clan Ladder scores. If the Clan leader dropped out of the game for any reason; unfortunately, there is currently no way for the scores to be posted. Therefore, to ensure players finish the game, you may wish to decrement a Clans score by a few points, and the only way to regain the points is to actually complete a game.

2. Calling MediusGetLadderStatsWide() (with the MediusLadderTypeClan enumeration type set) will request for a Clan's current ladder stats information. Each clan has between [0..LADDERSTATSWIDE\_MAXLEN] available Clan ladder categories to store Clan ladder rank information to.

Note: It is recommended that every player in a game call this function at the beginning of each round so that this information will be available (as noted above) just in case if a player (other than the Clan leader) has been declared as the player responsible for calling MediusUpdateLadderStatsWide().

- 3. Calling **MediusUpdateClanStats()** updates the Clan *Stats* field. Even though Clan stats are not used directly in calculating Clan ladders, it can still store helpful information such as setting formulas and weighted values from which new Clan ranks can be calculated. Additional information such as 'Team Frags', last time guild played as a team, etc. Can be embedded in the Stats string for GUI display and or helping in calculating new Clan ranking raw scores. Call either **MediusGetClanByID()** or **MediusGetClanByName()** to gain access to Clan 'stats' information.
- 4. Calling **MediusClanLadderList()** will return an ascending list of Clans in a ladder system (first place to last place). Setting *ClanLadderStatIndex* between [0..LADDSTATS\_MAXLEN] will determine which ladder category is returned.

**Note:** You can regulate the number of 'clan ladder ranks' returned to the requesting client (so that you can manage bandwidth usage and GUI lists) with the *StartPosition* and *PageSize* fields of the **MediusClanLadderListRequest** structure.

#### Example:


```
Set PageSize = 10 and StartPosition = 1 to get 'ranks' (1–10).
Set PageSize = 10 and StartPosition = 2 to get 'ranks' (11–20).
Set PageSize = 10 and StartPosition = 3 to get 'ranks' (21–30).
And so on...
```

5. Calling **MediusClanLadderPosition()** will return an exact position that a Clan is in a Ladder system. Setting *ClanLadderStatIndex* between [0..LADDERSTATS\_MAXLEN] will determine which ladder category is returned.

# **Medius File Services (MFS)**

As a plugin to the Medius platform, Medius File Services (MFS) is a SCE-RT technology that allows PS2 clients to store persistent game-specific data not already addressed by the Medius or SVO API. Files are created, uploaded, downloaded and destroyed against the user's authenticated account on the Medius servers. By default MFS is not enabled on Medius Servers – be sure to contact scert-support@scea.com to enable MFS for your title before attempting to work with the MFS API. As of the v1.50 release, the MFS API (MediusFileServices.h and MediusFileServicesTypes.h) is available in the standard SCE-RT client library release.

Figure 4: Overall Architecture of MFS



# The Client Perspective

The general concept is that you have PlayStation®2 consoles out on the Internet running MFS-enabled software. The player will, at some point, want to save their game data or share some game-specific data online with other online players. They would create the file, upload the contents and receive confirmation that the file has been posted to the server. Clients can also request a list of available files, select one and download the contents based on Unix-like permissions.

By default the current release caps the FileQuota size a user has to 20 KB. This can be changed on a title-by-title basis. Games with a heavy online community are recommended to keep their file sizes down. It is also recommended that titles keep their file transfer transaction counts low. For example, downloading a file when a user logs in and then again when an online game has completed would be normal usage. It is not recommended to be used by any automatic retrieval methods, such as when a user joins a chat channel he/she will then download everyone's MFS game-specific data that are joined to the same chat room.

#### MFS Back End Overview

All file transfers, sent or received, are tunneled through the Medius Lobby Server. A high number of file requests or large transfers will incur a large hit on the MLS. This will affect all Lobby-related functionality in your title.

Medius File Services, on the server side, works with the Apache web server to manage your game's file repository through Common Gateway Interface (CGI) applications developed by SCE-RT. As clients post data to be saved in the repository or request files from the repository, HTTP is used by the back end to resolve these requests. This is a very scalable architecture, able to be load-balanced with standard off-the-shelf tools to grow to handle any level of demand. As your title's demand on the Medius File Services changes over time, the system can be modified to suit your needs and provide only the level of service required.

Specifically, when a client posts a file to the server, that file is received by the lobby server and transferred into the file repository transparently. Then, when other clients request the file, regardless of which lobby server is hosting their session, a request is made to the back-end Apache-driven repository to retrieve the file. Once retrieved from the back end, the file is then delivered down to the client through the lobby server.

A client begins its file download request by first opening the file. When a client wants to post/upload a file into the repository, it begins by attempting to create the file. Information about the newly created file is first stored into the database for faster lookups in the future. This also gives the server platform a chance to validate the file according to certain rules. Once the file is validated and permissions are verified, the file is actually uploaded into the repository via the Apache-driven back-end.

Each user is given a file quota (20 KB by default), or a maximum amount of space they are allowed to occupy within the repository. This quota information, much like information about files themselves, is stored in the database and associated with the user's online account. When attempting to create any file in the repository, the client's account quota is checked to ensure they have enough free space. Quotas are a virtual concept and are configurable by the system administrator to help balance the consumption of resources within the file repository.

#### Medius File Services API

#### Initialization

Medius File Services does not require any additional initialization steps aside from the normal **NetInitialize()** and **MediusInitializeBare()** or **MediusInitialize()**.

#### Uploading a File

To upload a file using MFS you will need to issue **MediusFileCreate()** to start creation of the file. It is very important to prohibit the player from entering a forward slash or backslash in the Filename. This will create a directory on the file repository. However, you (the programmer) may use directories. Do not allow the player to create directories.

**MediusUploadFile()** starts an upload. Once an upload has begun, the **UploadCallback** will begin to fire. One of the members to the callback struct by UploadCallback is iXferStatus. When

**MediusFileUploadResponse**.iXferStatus=MEDIUS\_FILE\_XFER\_STATUS\_END the upload has completed and you may now issue the command to close the file. You also have the opportunity to cancel the upload before MEDIUS\_FILE\_XFER\_STATUS\_END has been reached.

To tell Medius to close a file you must call **MediusCloseFile()**. It is only after **MediusCloseFile()** that the file will then exist on the file repository and show up with **MediusFileListFiles()**.

#### Downloading a File

To download a file you will need to call **MediusFileDownload()**. The callback to this function will keep firing until the download has completed (**MediusFileDownloadReposnse**.iXferStatus = MEDIUS\_FILE\_XFER\_STATUS\_END). **Note:** On very small downloads this callback will only be called once and the iXferStatus will never equal MEDIUS\_FILE\_XFER\_STATUS\_INITIAL.

#### Canceling a Upload or Download

If a file is currently being downloaded or uploaded, a call to **MediusFileCancelOperation()** will cancel the transaction and the Upload and Download callbacks will cease to fire.

#### **Listing Files**

To retrieve a listing of files that have been previously uploaded and have not yet been deleted, you can call **MediusFileListFiles()**. **MediusFileListFiles()** will allow you to filter the listing of files based on different criteria such as file names or file size. This can be found in the **MediusFileListRequest** struct.

#### **Deleting a File**

Deletion of a file is performed by calling **MediusFileDelete()** and filling out the appropriate **MediusFileDeleteRequest** struct. It is important to note that no file is ever deleted in the file repository. It is however marked as deleted in the database and will not show up when using **MediusFileListFiles()**. If a new file is created with the same name as a previously deleted file, the previously deleted file will then be overwritten with the new file data.

#### MediusFileServices Sample

Please refer to the "MediusFileServices Sample" for more details on how to perform the above tasks.

# **Vulgarity Filtering**

The SCE-RT SDK provides the ability to filter content for vulgarity. All text-based content sent to the Medius platform infrastructure can be filtered for vulgarity based on a server-side dictionary. The software performs both hard matches and soft matches for a wide variety of words, in whatever language the server is set up with.

Filtering is enabled for all SCEA, SCEI and SCEE first party titles. If you would like to enable the filtering capabilities for a third party title, please contact developer support at scert-support@scea.com for further help.

### **Vulgarity Filtering Process**

There is only one API function used for vulgarity filtering, **MediusTextFilter()**. This function will ask the Medius platform if the "Text" field of the **MediusTextFilterRequest** message should "pass/fail" or "search-and-replace" due to server-side vulgarity checks.

Vulgarity checks should normally be placed on the following elements (list may change):

- 1. "AccountName" submitted during MediusAccountRegistration() (use "pass/fail").
- 2. "SessionDisplayName" submitted during MediusAnonymousLogin() (use "pass/fail").
- 3. "Message" submitted during **MediusSendGenericChatMessage()** (use either "pass/fail" or "search-and-replace).
- 4. "GameName" submitted during MediusCreateGame() (use "pass/fail").
- 5. "LobbyName" submitted during MediusCreateChannel() (use "pass/fail").
- 6. "ClanName" submitted during MediusCreateClan() (use "pass/fail")...
- 7. If your application supports in-game chat directly with the DME (via NetSendMessage()) and/or NetSendApplicationMessage()), since your Medius connection will still be open, you may consider (depending on the "Audience Rating" of you game) if you want to call MediusTextFilter() before you send in-game chat messages (of course LAN games will not have a Medius connection established; therefore, take this into account as you code this up) (use either "pass/fail" or "search-and-replace").

Before you execute any of the functions in the list above, call **MediusTextFilter()** to verify that the given text string is appropriate. You may need to experiment with a mini 'state-machine' and/or 'message queue' to get 'non-blocking' behavior to occur while a particular vulgarity check is taking place so as to only call the given function if a successful vulgarity check occurred and/or a "search-and-replace" operation modified the submitted text string.

Typically, if doing a "pass/fail", if a "fail" was received, you should inform the user that the "text" they submitted did not pass the vulgarity check, and ask them to re-enter information. Hopefully our noble and distinguished user will not try to 'outsmart' the server-side vulgarity checks, but if they do, personnel dedicated to monitoring SCE-RT server activity can take correct measures.

### **AntiCheat**

#### Overview

AntiCheat in general is a very broad topic encompassing everything from client-side obfuscation to router Access Control Lists (ACLs). SCE-RT would like to encourage developers to contact us (scert-support@scea.com) regarding client-side defensive programming techniques. Be advised that such things are best adopted rather early in the development cycle. This document, however, covers the AntiCheat service offered by the Medius Lobby Server (MLS).

The MLS uses plug-ins to determine title-specific logic for AntiCheat. These plug-ins are called "Detectives". While it is possible for a developer to create a totally custom Detective for its title-specific logic, SCE-RT recommends using the generic Detective which can be configured on a per-title basis. (Programming a Detective occurs at the C++ level, but reconfiguring the generic Detective takes place in an XML configuration file owned by SCE-RT's production staff.) Using the generic Detective allows developers to gain significant AntiCheat benefit without spending much effort on development.

**Note:** In order for AntiCheat to work, the title must have issued a MediusDnasSignature. This is a TRC requirement for all online titles.

Henceforth, this document discusses decisions the developer may need to make in order to use the generic Detective correctly for a given title.

## **Trigger Events**

The generic Detective issues a series of challenges against each client. Once a particular client has passed all these challenges, the client will not be challenged again. The series of challenges is initiated when a client (which has not yet passed) makes an API call corresponding to one of the events below.

Using the generic Detective, there are nine trigger events that can be used as a Trigger Event. These correspond (roughly) to Medius API calls:

- LobbyConnect
- JoinGame
- LeaveGame
- PlayerReport
- StatsReport
- ChatMessage
- GetChannelList
- GetGameList
- GetMyClans

One or more of these trigger events can be chosen for a given title. For example, the Detective could be configured with both **LobbyConnect** and **GetGameList**. Normally, we assume that a title will not want AntiCheat challenges to begin until after the user has clicked through their End User License Agreement (EULA). This is the primary consideration in choosing your trigger events. Other considerations might include the way the title uses the lobby servers. (For instance, if they rapidly change lobbies before settling down on one for a game, they might not want to use the **LobbyConnect** event.) Ideally, the player will have acknowledged his EULA before ever connecting to the MLS (on the MAS, for instance). All of these decisions should be coordinated with SCE-RT support.

### **Cheat Challenges**

The challenges can be of various types and include: BinaryChallenge, BinarylopChallenge, MatchRawMemory, and ThreadCount. These are usually used to make certain that each player is playing on code that is approved by the developer. Many cheat devices function by modifying the game's instructions in memory.

SCE-RT already has images of many popular cheat devices. These can be seamlessly "dropped in" to any title's MLS configuration. This is by far the simplest way for a title to participate in AntiCheat. The next step involves creating what is known as a "Master Integrity Image" for your title. This is basically a copy of the instructions used by the title. These are obviously title-specific and it is probably best to coordinate the creation of this image with SCE-RT support.

#### **Cheat Policies**

Cheat policies are rules that are applied to the player after a detection (or number of detections) have occurred. In addition to detection events, cheat policies are also applied upon account login after a ban or suspension is instated. Once a detection has occurred, the incident is recorded and the client is "kicked" by the server. A lookup of applicable Cheat Policies occurs for the detected client's *ApplicationID*. There are currently three types of cheat policies:

- 1. DNAS Signature-based ban
- 2. AccountID suspension
- 3. Simple detection and kick from server

Any or a combination of the cheat policies can be applied to detection events. For example, a title may want the following policies applied for cheat detections:

- First detection, no suspension applied. This is considered a warning.
- Second detection, one-hour suspension is applied to the DNAS\_Signature that was detected.
- Third and fourth detection, two-hour suspension is applied to the DNAS\_Signature that was detected.
- Fifth and sixth detection, one-day suspension is applied to DNAS\_Signature that was detected.
- Seventh suspension and on, permanent suspension of AccountID.

#### **Cheat Messages**

Cheat Messages are messages that are sent to the player detected by AntiCheat. They may also be sent upon Account Login when the client has a time-based ban applied. Cheat Messages are configured in the database. For a particular cheat policy there may exist a corresponding cheat message. Cheat Messages are localized based on language ID. For a given title, there may exist a number of cheat messages for each language ID that the title supports per cheat policy. There may only be one cheat message per cheatpolicyid/languageid pair.

### **Examples of MsgText in a Cheat Message**

"You have been detected cheating or using a cheat device CHEAT\_TIMES. Your Player Name has been terminated. For more information please call SCEA Consumer Services at 1-800-345-7669."

"You have been detected cheating or using a cheat device CHEAT\_TIMES. You have been banned from accessing APPLICATIONNAME for BANNED\_TIME and your Player Name has been terminated. You will be able to access APPLICATIONNAME again in PLAY\_AGAIN. For more information please call SCEA Consumer Services at 1-800-345-7669."

Some variables that Cheat Messages may use:

CHEAT\_TIMES – Number of cheat detection events recorded for a particular *AccountID*.

MAX\_CHEATS - Value of maxcheatcount for a particular ApplicationID.

PLAY\_AGAIN - Remaining ban time for DNAS time-based ban.

ACCOUNTNAME - AccountName string for a particular AccountID.

APPLICATIONNAME – Game name for a particular *ApplicationID*.

BANNED\_TIME - Length of ban time for DNAS time-based ban.

#### What AntiCheat Can and Cannot Do

Broadly, what AntiCheat can do is examine the memory and/or state of the PlayStation®2 itself.

AntiCheat cannot examine traffic between clients at the DME layer since it is an MLS-based service. (So, it has no hope of detecting modern lag devices.) Also, please bear in mind that AntiCheat is not foolproof, and indeed cannot be made so. AntiCheat's purpose is to make it difficult for the average user to cheat.

# **Internationalization (Multi-Byte Language Support)**

The SCE-RT SDK supports multi-byte character sets. Applications that need to perform data storage and retrieval with multi-byte character sets will be able to do so by using UTF-8 encoding (Unicode) by reading and writing appropriately into the single byte character related API data structures. Language types currently supported: English, Japanese, Korean, Italian, Spanish, German, and French. If you wish to have additional *MediusLanguageTypes* defined, contact SCE-RT developer support (scert-support@scea.com).

**Note:** This will limit the amount of character data to what would normally be allowed by a single byte character set. For example, "AccountName" is of size ACCOUNTNAME\_MAXLEN (32). Using Extended ASCII you can have a character string of up to 32 characters. However, if you are using Unicode, each Unicode character may need 2-3 bytes for each UTF-8 character (depending on the particular character being used). In this case data is still limited to a 32 byte string.

The Medius function that provides internationalization is:

MediusSetLocalizationParams()
 Sets internationalization parameters

### **Example of Internationalization**

The Medius API function used to support internationalization is **MediusSetLocalizationParams()**. If you do not call this, by default "US English" is set for *MediusLanguageType* (MediusLanguage\_USEnglish) with "Extended ASCII" set as the default *MediusCharacterEncoding* type

(MediusCharacterEncoding\_ISO8859\_1). After calling this function, the 'player object' residing on the Medius platform will be set with the specified localization parameters. The general process is as follows:

- 1. Call **MediusConnect()** to connect to the MAS.
- 2. Start a "Session" with the Medius platform.
- 3. Call MediusSetLocalizationParams() to set our language and encoding type.
- 4. Call **MediusGetPolicy()** to get the specific application's 'usage policy' and 'privacy policy'. Based on the *MediusLanguageType* set for the current user, there will be a policy entry in the Medius database for that language type to be returned. If no 'usage policy' or 'privacy policy' has been set up, an empty string will be returned.
- 5. Call **MediusGetAnnouncements()** or **MediusGetAllAnnouncements()** to retrieve the current announcements for you application. Based on the *MediusLanguageType* set for the current user, there will be various 'announcement' entries in the Medius database for that language type to be returned. If no 'announcements' have been set up, an empty string will be returned.
- 6. Proceed with "establishing an authenticated state" (Account Login).

As you can see, the Medius platform can support many language types for a given application. Even though the application may not properly display character string data (due to different Unicode character sets) as seen with (for example) player names and chat messages, users with different languages can all still play games together. It is the application developer's responsibility to convert character strings for the given language into the respective encoding type. For more information on how to convert your particular language to UTF-8, search the Internet with this keyword (+"UTF-8" conversion library).

If you wish to have your application designed so that players with a particular language only see players with the same language, then you will either need to set up additional Medius servers (with a different URL or IP combinations) or set up Co-Location parameters to your Medius platform (see the "Co-location" section for more information).

### The Process for Setting Internationalization Parameters:

- 1. Create an instance of the **MediusSetLocalizationParamsRequest** structure.
  - a. **memset()** the structure to '0'.
  - b. Set MessageID to a value of your numbering scheme (if needed).
  - c. Set MessageType to a MediusMessageType.
  - d. Set Language to a MediusLanguageType.
- 2. Call **MediusSetLocalizationParams()** with the respective request message and callback.
- 3. When the **MediusStatusResponse** message is received, if *StatusCode*=**MediusSuccess** then your language type and encoding type will be set.

If StatusCode!=MediusSuccess, be sure to transition through your lobby state-machine to handle the current error condition.

# **Medius Universe Information Server (MUIS)**

The SCE-RT SDK supports connection to a (MUIS) Medius Universe Information Server. The MUIS provides the client with a list of Universes available for a particular application. An application may wish to have Universes (Medius platform server sets) spread out geographically around the world, configured with different languages, and strategically deployed closer to locations with a high user base so as to provide users with lower ping times in effect providing an optimal playing experience due to lower latencies; nonetheless, still providing users the option to play against users around the world. This is a step up from co-location – which at any one time has only one MUM managing an entire Medius platform server set. As expected, a user would need to create a new account on each Universe they connect to.

For example, if you have four Medius platform server sets for an application operational and deployed in: San Diego, England, Korea, and Japan (each server set includes 1-MUM, n-MAS, n-MLS, n-MPS, 1-MCS and (n-GS)), a single MUIS will read a list of Universes from a configuration file (which is re-read after a set time, so more Universes can be added later) then will establish a connection to each of the Universe's MUM to obtain current information regarding those Universes. After a client connects to the MUIS and retrieves a list of Universes, they should do a DNS lookup of the selected Universe's DNS name and port number, and then continue with a **MediusConnect()** to the Universe's MAS (The Universe's DNS name and port number will be mapped to a MAS for that server set).

The Medius functions that provides Medius Universe Information from a MUIS are:

MediusGetUniverseInformation()
 Retrieves Medius Universe Information from a MUIS
 MediusUpdateUniverseInformation()
 To be called each frame instead of MediusUpdate()

The MUIS (as of v2.9) will return the following in a list (with multilingual support):

- Universe Name (and ID)
- Fully qualified (DNS) Domain Name
- Port number
- A Universe description
- Status (Available/Unavailable)
- Current User Count as seen by the Universe's MUM
- Universe's Max User count
- (Billing information if enabled)
- Extended Info customizable per title. Usually used for patching by storing patch version and patch URL.
- SVO (SCE-RT View Online) start URL

# Connecting to the MUIS

Connecting to a MUIS is just like connecting to a MAS for the first time (in calling **MediusSetDefaultConnectInParams()** and enabling security) The general process is as follows:

- 1. Call **MediusConnect()** to connect to the MUIS.
- 2. Call **MediusUpdateUniverseInformation()** (instead of **MediusUpdate()**) each frame to process incoming/outgoing messages for the MUIS.
- Call MediusGetUniverseInformation() to retrieve a list of Universes and Universe News
   Be sure to set/mask InfoType (of MediusGetUniverseInformationRequest) with the following standard set of MediusUniverseInformationType values:

INFO\_NEWS | INFO\_ID | INFO\_NAME | INFO\_DNS | INFO\_DESCRIPTION | INFO\_STATUS

- 4. User chooses which Universe to connect to (by selecting a returned DNS string and port combination from one of the response message returned from the **MediusGetUniverseInformation()** call).
- 5. When the EndOfList flag is set to true during a MediusUniverseVariableInformationResponse message, MediusUpdateUniverseInformation() will automatically disconnect from the MUIS with an internal call to MediusDisconnect(). It is safe to still call MediusUpdateUniverseInformation() each frame, but is recommended to not do so (unlike MediusUpdate() which would return 'Not Connected' error return codes –this is why the MUIS has it's own 'update' call).
- 6. Perform a DNS lookup with the selected DNS string.
- 7. Call **MediusConnect()** with the IP returned from the DNS lookup along with the port number to connect to the MAS of the chosen Universe. At this point we should be calling **MediusUpdate()** each frame instead of **MediusUpdateUniverseInformation()**.
- 8. Proceed with "establishing an authenticated state" (Account Login).

#### The Process for Requesting Universe Information:

- 1. Create an instance of the MediusGetUniverseInformationRequest structure.
  - a. memset() the structure to '0'.
  - b. Set MessageID to a value of your numbering scheme (if needed).
  - c. Set *InfoType* to each (masked value of) *MediusUniverseInformationType*. (INFO\_NEWS | INFO\_ID | INFO NAME | INFO DNS | INFO DESCRIPTION | INFO STATUS) are recommended.
  - d. Set CharacterEncoding to a MediusCharacterEncodingType. (MediusCharacterEncoding ISO8859 1 set by default).
  - e. Set Language to a MediusLanguageType (MediusLanguage\_USEnglish set by default).
- 2. Call MediusGetUniverseInformation() with the respective request message and callback.
- 3. If InfoType of **MediusGetUniverseInformationRequest** was set with INFO\_NEWS, a number of News (chunks of data) messages will be returned. *EndOfText* set to != '0' will indicate all News data has been sent.
- 4. For each Medius server set (i.e. Universe) a response message will be sent indicating a DNS name and port of a MAS to connect to. *EndOfList* set to != '0' indicates that all elements (response messages) of the list have been sent.
- 5. User should then select a Universe, call **MediusConnect()** to the Universe's MAS (i.e. with Universe's DNS name and port number after a DNS lookup returned a IP address for the DNS name).

# **Running the Medius Servers**

The Medius Lobby Server, Medius Authentication Server and Medius Universe Manager are currently distributed as Redhat Linux 9 (glibc-2.3.2-27.9.7) and Win32 products. The Linux builds have not been tested on any other Linux distributions.

The following instructions detail how to run the database-disabled versions of the Medius Lobby Server and Medius Authentication Server. Please contact us (scert-support@scea.com) for details if you wish to set up and host your own development database server. Enabling and disabling database, as well as other functionalities, is performed through appropriate configuration files. More details on these configuration files can be found in the associated "readme" file in this release.

### **Operating the Medius Server Executables**

- 1. Copy the desired Medius Universe Manager (MUM) executable file and appropriate configuration file (included within this release) to a folder on the machine that will act as the Medius Universe Manager.
- 2. Copy the desired Medius Lobby Server (MLS) executable file and appropriate configuration file (included within this release) to a folder on the machine that will act as the Medius Lobby Server.
- 3. Copy the desired Medius Authentication Server (MAS) executable file and appropriate configuration file (included within this release) to a folder on the machine that will act as the Medius Authentication Server.
- 4. Copy the desired Medius Proxy Server (MPS) executable file and appropriate configuration file (included within this release) to a folder on the machine that will act as the Medius Proxy Server.
- 5. (If Client/Server) Copy the desired DME Game Server (GS) executable file and appropriate configuration file (included within the DME release) to a folder on the machine that will act as the DME Game Server. This can be the same server as the Medius Lobby Server, Medius Authentication Server or Medius Universe Manager; this will drastically affect the performance of the servers, and is only suitable for basic functionality development.
- 6. Modify the Medius Lobby Server and Medius Authentication Server configuration files. Ensure that the DefaultConfigLobbyPassword value is set to nothing (empty string), unless you wish to enforce a password on all lobby channels. Here you will also find the port that the server will be running on, as well as the IP/Port that the Medius Lobby Server or Medius Authentication Server should use to connect to the Medius Universe Manager.
- 7. Modify the DME Server configuration file. MediusReportIP and Port should be set to the IP and Port address of the machine hosting the Medius Authentication Server. ReportInterval should be set, in milliseconds, to the rate that the server should send Server Reports to the MLS (this is recommended to be 30000). Finally, if running both servers on the same machine, ensure that this is set to a different port.
- 8. Modify the Medius Universe Manager configuration file. The Medius Universe Manager can be configured to run on any port.
- 9. Run the Medius Universe Manager executable file. Wait approximately 10 seconds for the server to initialize.
- 10. Run the Medius Lobby Server executable file. Wait approximately 10 seconds for the server to initialize and establish a connection with the Medius Universe Manager specified in the configuration file.
- 11. Run the Medius Authentication Server executable file. Wait approximately 10 seconds for the server to initialize and establish a connection with the Medius Universe Manager specified in the configuration file.
- 12. Run the DME Game Server executable file. Wait approximately 10 seconds for the server to initialize and begin sending reports to the Medius Authentication Server.

13. Begin making connections and sending requests to the Medius Authentication Server and Medius Lobby Server. Depending on the type of request, certain backend requests and data will flow to the other servers to service each request.

This page intentionally left blank.