



Service

Generated on: 2026-07-01 15:01:24 GMT+0000

SAP S/4HANA | 2025 FPS01 (Feb 2026)

Public

Original content: https://help.sap.com/docs/SAP_S4HANA_ON-PREMISE/c9b5e9de6e674fb99fff88d72c352291?locale=en-US&state=PRODUCTION&version=2025.001

Warning

This document has been generated from SAP Help Portal and is an incomplete version of the official SAP product documentation. The information included in custom documentation may not reflect the arrangement of topics in SAP Help Portal, and may be missing important aspects and/or correlations to other topics. For this reason, it is not for production use.

For more information, please visit <https://help.sap.com/docs/disclaimer>.

Service Monitoring and Analytics

Service Monitoring and Analytics provides monitoring and analytical features for core service business processes. They help you to get an overview of the services being executed by your teams and provide information on a range of key performance indicators for service contracts and service orders. The solution capability also allows you to identify and address issues that are related to the fulfillment of service transactions and to derive insights for future actions.

Using analytical and monitoring apps, you can obtain the following information:

- Incomplete and overdue service orders
- Expired and expiring service contracts
- Service contract revenues and profit margins
- Average service duration for a product or equipment

Analytical Key Figures

The following analytical key figures are currently available in Service Monitoring and Analytics.

You can sort and filter the content of the table.

Business Process	Key Figure	Definition	Global Field Name	Related App	Related CDS View
Service Contract Management	No. of Expired Service Contracts	Number of service contracts that have exceeded the contract validity period	NmbrOfExpiredSrvcContracts	Service Management Overview (F3607)	Service Contract - Cube (I_ServiceContractCube_
Service Contract Management	Net Value of Expired Service Contracts	Net value of service contracts that have exceeded the contract validity period	ServiceDocNetAmount	Service Management Overview (F3607)	Service Contract - Cube (I_ServiceContractCube_
Service Contract Management	No. of Expiring Service Contracts	Number of service contracts due to expire within the next three months (Service Management Overview)	NrOfExprgSrvcContrItmInCurMnth NrOfExprgSrvcContrItmNextMonth NrOfExprgSrvcContrItmIn2Months NrOfExprgSrvcContrItmIn3Months	Expiring Service Contracts Analysis (F3970) Service Management Overview (F3607)	n/a

Business Process	Key Figure	Definition	Global Field Name	Related App	Related CDS View
		and (Expiring Service Contracts Analysis), starting from the current month			
Service Contract Management	Net Value of Expiring Service Contracts	Net value of service contracts due to expire within the next three months (Service Management Overview) and (Expiring Service Contracts Analysis), starting from the current month	ExprgSrvcContrItemNetAmount	Expiring Service Contracts Analysis (F3970) Service Management Overview (F3607)	n/a
Service Contract Management	Total Contract Value	Net value of a service contract	n/a	Service Contracts Analysis (F3942) Service Management Overview (F3607)	n/a
Service Contract Management	Annual Contract Value	Annualized net value of a service contract	n/a	Service Contracts Analysis (F3942)	n/a
Service Contract Management	Service Contract Revenue	Recognized revenue for a service contract from the contract start up to the current date	n/a	Service Contracts Analysis (F3942) Service Management Overview (F3607)	n/a
Service Contract Management	Service Contract Cost	Recognized cost for a service contract from the contract start up to	n/a	Service Contracts Analysis (F3942)	n/a

Business Process	Key Figure	Definition	Global Field Name	Related App	Related CDS View
		the current date		Service Management Overview (F3607)	
Service Contract Management	Service Contract Profit Margin	Recognized profit margin for a service contract from the contract start up to the current date	n/a	Service Contracts Analysis (F3942) Service Management Overview (F3607)	n/a
Service Contract Management	Service Contract Revenue Year to Date	Recognized revenue for a service contract from the beginning of the current calendar year up to the current date	n/a	Service Contracts Analysis (F3942)	n/a
Service Contract Management	Service Contract Cost Year to Date	Recognized cost for a service contract from the beginning of the current calendar year up to the current date	n/a	Service Contracts Analysis (F3942)	n/a
Service Contract Management	Service Contract Profit Margin Year to Date	Recognized profit margin for a service contract from the beginning of the current calendar year up to the current date	n/a	Service Contracts Analysis (F3942)	n/a
Service Order Management	No. of Incoming Service Orders	Number of service orders that have been created in a specific month	NumberOfIncomingServiceOrders	n/a	Service Order - Query (C_ServiceOrderQuery) Service Order - Cube (I_ServiceOrderCube_2)
Service Order Management	No. of Incomplete	Number of service orders that	NmbrOfIncompleteServiceOrders	Service Orders	Service Order - Cube (I_ServiceOrderCube_2)

Business Process	Key Figure	Definition	Global Field Name	Related App	Related CDS View
	Service Orders	haven't been completed		Analysis (F3971)	
Service Order Management	No. of Open Service Orders	Number of service orders that don't have the status Completed in a specific month	NumberOfOpenServiceOrders	n/a	Service Order - Query (C_ServiceOrderQuery) Service Order - Cube (I_ServiceOrderCube_2)
Service Order Management	No. of Overdue Service Orders	Number of service orders that haven't been completed and for which the requested end date has been exceeded	NumberOfOverdueServiceOrders	Overdue Service Orders Analysis (F4166)	Service Order - Cube (I_ServiceOrderCube_2)
Service Order Management	Average Service Duration	The amount of time that was needed to perform a requested service for a product or equipment as reported in a service confirmation. The value is calculated by adding the confirmed hours in all service confirmations that have been completed for a specific product or equipment and dividing the total by the number of confirmations for that product or equipment.	n/a	Service Management Overview (F3607)	n/a

i Note

For the calculation of financial KPIs, you need the following semantic tags:

- Recognized revenue: RECO_REV
- Recognized cost: RECO_COS
- Recognized profit margin: REC_MARGIN

Service Management Overview

With this app, you as a service professional or a service employee can obtain a graphical overview of key service process data and gain insights into the current service situation. You can display detail information that helps you examine and analyze data across various dimensions.

Key Features

You can use this app to:

- Display data on service topics using cards
- Display service data using a variety of charts and lists
- Filter results by sales organization, distribution channel, division, sales office, and sales group
- Specify a preferred currency used to display results
- Navigate to related apps to drill down into the data
- Create personalized views and share them with others

i Note

To use this app, you need to activate the OData service C_SERVICECONTRFINLIST_CDS and the depending OData service C_SRVCONTRFINQUERY_2_CDS.

Cards

Card	Description
Service Contracts By Contract Value	• Displays the top five service contracts by highest or lowest contract value • You can navigate to the Service Contracts Analysis app to obtain additional information
Service Contracts By Profit Margin	• Displays service contracts either by the most profitable or by the least profitable contracts • You can navigate to the Service Contracts Analysis app to obtain additional information

Card	Description
Expired Service Contracts	- Displays the total value and the total number of service contracts that expired in the last six months, excluding the current month - Displays the top five service contracts that expired most recently
Expiring Service Contracts	- Indicates all service contract items that will expire in the next three months including the current month - You can navigate to the Expiring Service Contracts Analysis app to obtain additional information
Incomplete Service Orders	- Displays the total number of incomplete service orders - Displays incomplete service orders by life cycle status - You can navigate to the Service Orders Analysis app to obtain additional information and take appropriate action
Overdue Service Orders	- Displays the total number of overdue service orders - Displays overdue service orders by life cycle status - You can navigate to the Overdue Service Orders Analysis app to obtain additional information
Average Service Duration	Displays the average number of service hours reported in service confirmation items by product or equipment
Quick Links	You can navigate directly to the respective apps that are listed in the quick links cards

→ Tip

If you want only specific cards to be displayed in [Service Management Overview](#), you can hide the cards that you don't need using the [Manage Cards](#) setting in the user actions menu. Your personalized setup stays until you next changes it.

Default Filter Values

If you want the system to display the data for a specific service order type in a specific display currency every time you start the app, you can set default values for the filters [Service Order Type](#) and [Display Currency](#) under [Settings > Default Values](#) in the user actions menu.

i Note

If you don't maintain a default value for [Display Currency](#), the system automatically inserts [EUR](#) because this parameter is mandatory.

i Note

If you set default values for service order type, you also need to set a default value for display currency. Otherwise, the **Display Currency** field is not filled and therefore no data is displayed in **Service Management Overview** when you start the app.

Supported Device Types

- Desktop

Related Information

[Service Orders](#)

[Service Contracts](#)

[Service Orders Analysis](#)

[Service Contracts Analysis](#)

[Overdue Service Orders Analysis](#)

[Expiring Service Contracts Analysis](#)

App Extensibility: Service Management Overview

As a key user, you can extend the **Service Management Overview** app according to your business needs.

Features

You can extend the app in the **Custom Fields** app using the business context **Service Header**. To add a custom field to an app, you must enable the specific views for the field.

You can enable usage of your custom fields in the **UIs and Reports** section of the custom field maintenance for the following data sources:

- C_ServiceMgmt0vPgGlobalFltr
- I_ServiceDocument
- I_ServiceDocumentEnhcd
- C_SrvcOrderListRptAndObjPg
- C_ServiceOrderAnalyticsQry
- I_ServiceOrderCube_2
- CRMS4_SERV_MANGMT_OVP_SRV

After you save and then publish the changes, the field is available in the filter bar in the **Service Management Overview** app.

For more information about how to adapt an SAP Fiori UI at runtime, see [Making UI Changes \(Object Pages\)](#).

Related Information

[Key User Extensibility](#)

[Custom Fields App and Custom Logic App](#)

Expiring Service Contracts Analysis

You can use this app to display expiring service contract items to review them and take appropriate action.

Expiring service contracts are contracts due to expire within the next three months.

You can use filters to display the expiring service contracts for a specific sold-to party or with a specific life cycle status. You can also sort the contracts by the contract end date or focus on contracts with the highest contract value. By choosing an individual contract and navigating to the [Manage Service Contracts](#) app, you can review the contract details and take appropriate action.

🔗 Example

It may be critical for you as a service professional or a service employee to focus on service contracts expiring this month. You can use this app to identify these contracts in order to start the renegotiation process in time or to enable the auto renewal of a particular service contract item.

i Note

You access this app through the [Service Management Overview](#) app by choosing the [Expiring Service Contract Items](#) card.

Key Features

You can use this app to:

- Display expiring service contracts
- Filter the data by currency, service contract ID, service contract start date or end date, involved parties, or life cycle status
- Sort and group service contracts using various sorting criteria, such as sold-to party, contract ID, or contract value
- Navigate to the [Manage Service Contracts](#) app to obtain detail information on a specific service contract and take appropriate action
- Create, save, and share custom views

Supported Device Types

- Desktop
- Tablet

Related Information

[Service Management Overview](#)

[Service Contracts](#)

App Extensibility: Expiring Service Contracts Analysis

As a key user, you can extend the [Expiring Service Contracts Analysis](#) app according to your business needs.

Features

You can extend the app in the **Custom Fields** app using the business context **Service Item**. To add a custom field to an app, you must enable the specific views for the field.

You can enable usage of your custom fields in the **UIs and Reports** section of the custom field maintenance for the following data sources:

- C_ExpiringSrvcContrItmDetails
- I_ServiceContractItemCube
- I_ServiceDocumentItemEnhcd
- I_ServiceDocumentItem

After you save and then publish the changes, the field is available in the compact filter section and in the content table.

For more information about how to adapt an SAP Fiori UI at runtime, see [Making UI Changes \(Object Pages\)](#).

Related Information

[Key User Extensibility](#)

[Custom Fields App and Custom Logic App](#)

Service Contract Issues

With this app, you can monitor and display issues that impede the fulfillment of service contracts. The cockpit highlights issues and provides supporting information. It also enables you to collaborate with internal and external contacts.

Key Features

Using this app, you can display and monitor a variety of issues that may occur in service contracts in real time.

You can use this app to:

- Display issues that may impede the fulfillment of service contracts
- Display detail views for issues
- Display results by issue, country/region, and sales organization
- Employ a variety of chart types to analyze and monitor issues
- Use filters to focus, for instance, on a particular distribution channel, sales organization, or service transaction
- Display mini tiles to obtain additional information on an issue
- Create, save, and share custom tiles
- Save and mail evaluations

The table below shows some of the issue types that you can monitor.

Issue Type	Description
Billing Block	• (03) - Incomplete pricing

Issue Type	Description
	• (04) - Error in payment terms • (06) - Error in billing proposal • (Y8) - Error in credit memo • (Y9) - Error in debit memo
Contains Error	This view displays service contracts that contain a minimum of one error at header and/or item level.
Rejected	This view displays all service contract items that have been rejected as well as the reason for the rejection.

i Note

Issues are reported at header and item level. However, issues at header level are only reported if the same issue does not occur at item level. In this case, the related items are listed as 000000 in report views.

i Note

Currently, it's not possible to set billing blocks in SAP S/4HANA Service.

Information for Key Users

The standard app displays fulfillment issues in SAP S/4HANA Service that exist in your system. In order to avoid performance issues, SAP recommends that you configure the app to users' needs by specifying the characteristics they want to see.

Example: You only want to analyze issues affecting service contracts in Nevada. Therefore, you use a filter to set the appropriate sales organization and transaction types.

Supported Device Types

- Desktop
- Tablet

Service Contracts Analysis

With this app, you can display service contracts by contract value as well as various other key performance indicators. The app enables you to see at a glance whether your profit margin is low for a particular service contract, service organization, or region. The profit margin is an indicator of your company's pricing strategies and how well you control costs.

Key Features

You can use this app to:

- Display a list of released service contracts that includes various key performance indicators
- Display aggregate views for service contract values by sales organization and region
- Display the total revenue, cost, and profit margin of all service contracts by month, week, or quarter for the calendar year

- Display the annual cost as well as revenue, cost, and profit margin of all service contracts by sales organization for the year to date
- Sort the list of service contracts using various sorting criteria, such as profit margin, total cost, or total revenue
- Filter the data by solution order, sales organization, sold-to party, ship-to party and so on
- Create, save, and share custom views
- Save and mail evaluations

i Note

You access this app through the [Service Management Overview](#) app.

i Note

To use this app, you need to activate the OData service C_SERVICECONTRFINLIST_CDS and the depending OData service C_SRVCCONTRFINQUERY_2_CDS.

Key Performance Indicators

The app provides information on the following key performance indicators:

Key Performance Indicators	Description
Total Contract Value	The net value of the contract as defined in the service contract header
Annual Contract Value	The net value of the service contract per year. The value is determined by dividing the total contract value defined in the service contract header by the life of the contract in years
Profit Margin	The difference between total revenue and total cost
Total Cost	The sum total of all costs collected for service confirmation items over the life of the service contract to date
Cost Year To Date	The sum total of all costs collected for service confirmation items related to the service contract for the year to date
Total Revenue	The sum total of billed service confirmation items over the life of the service contract to date
Revenue Year To Date	The sum total of billed service confirmation items for the year to date

i Note

The processes for collecting financial data supported by this app are based on internal orders that are created at contract header level.

Supported Device Types

- Desktop

Related Information

[Service Management Overview](#)

Service Contracts - Flexible Analysis

With this app, you can use a flexible combination of dimensions to analyze service contracts including their billing plan and invoice details.

For example, for your key customers or for your key contracts, you can analyze the billing value of the billing-relevant service contract items that haven't been invoiced yet. You can then drill down into the data to identify the settlement periods for which billing is due and process them with high priority.

Key Features

You can use this app to do the following:

- Analyze key performance indicators related to service contracts in multidimensional reports using the following measures:

Measure	Description
Billing Value of Settlement Period	Net value of a settlement period for which billing is due as of the current date, but for which either a billing document request or a billing document based on an existing billing document request hasn't been created
Billed Value of Settlement Period	Net value of a settlement period that has been billed as of the current date
Net Value of BDR Item	Net value of a billing document request item created for each service contract item that is to be billed within a billing plan
No. of Billing Request Lines Due for Billing	Number of billing request lines for which billing is due as of the current date

- Filter the items according to various criteria, such as sold-to party, sales organization, life cycle status, earliest contract start and latest contract end, cancellation status, or related solution order

i Note


If a custom life cycle is maintained for the service contract item, you can filter the items based on custom life cycle status as well.

- Sort and display the report data as a table or a chart
- Export the report as an Excel or a PDF
- Navigate to the following apps to further analyze the selected service contract data:
 - [Expiring Service Contracts Analysis](#)
 - [Manage Service Contracts](#)

For more information about how to analyze your data, see [Multidimensional Data Grid Apps](#).

Working with Analytical Reports (English Only)

Watch the video to learn more about the general functions offered by this app.



[Open this video in a new window](#)

Supported Device Types

- Desktop
- Tablet

Related Information

[Multidimensional Data Grid Apps](#)

[Analytical Key Figures](#)

Overdue Service Orders Analysis

Using this app, you can display overdue service orders, obtain additional information to perform a deeper analysis and identify service orders that require your attention.

As a service professional or a service employee, you can obtain an overview of services orders that are overdue and analyze them using various dimensions. You can navigate to the **Manage Service Orders** app to obtain additional information and take appropriate action..

i Note

You access this app through the **Service Management Overview** app by choosing the **Overdue Service Orders** card.

Key Features

You can use this app to:

- Display overdue service order items by transaction type and life cycle status
- Filter the list of service order items by service order type, sales organization, requested end date, and order priority
- Sort the list using various sorting criteria, such as error status or net order value
- Navigate to the [Manage Service Orders](#) app to obtain additional information and take appropriate action
- Create, save, and share custom views

Supported Device Types

- Desktop

Related Information

[Service Management Overview](#)

[Service Orders](#)

App Extensibility: Overdue Service Orders Analysis

As a key user, you can extend the [Overdue Service Orders Analysis](#) app according to your business needs.

Features

You can extend the app in the [Custom Fields](#) app using the business context [Service Header](#). To add a custom field to an app, you must enable the specific views for the field.

You can enable usage of your custom fields in the [UIs and Reports](#) section of the custom field maintenance for the following data sources:

- I_ServiceDocument
- I_ServiceDocumentEnhcd
- C_OverdueServiceOrder
- I_ServiceOrderCube_2

After you save and then publish the changes, the field is available in the compact filter section and in the content table.

For more information about how to adapt an SAP Fiori UI at runtime, see [Making UI Changes \(Object Pages\)](#).

Related Information

[Key User Extensibility](#)

[Custom Fields App and Custom Logic App](#)

Service Order Issues

With this app, you can monitor and display issues that may impede the fulfillment of service orders and confirmations. The cockpit highlights issues and provides supporting information. It also enables you to collaborate with internal and external contacts.

Key Features

Using this app, you can display and monitor a variety of issues that can affect service orders and confirmations in real-time.

You can use this app to:

- Display issues that impede the fulfillment of service orders and confirmations
- Display detail views for issues
- Display results by issue, country/region, service transaction, and sales organization
- Employ a variety of chart types to analyze and monitor issues
- Use filters to focus, for instance, on a particular distribution channel, sales organization or service transaction
- Display mini tiles to obtain additional information on an issue
- Create, save, and share custom tiles
- Save and mail evaluations

The table below shows some of the issue types that you can monitor and the transaction types that are relevant to each issue.

Issue Type	Description	Transaction Type
Billing Block	• (03) - Incomplete pricing • (04) - Error in payment terms • (06) - Error in billing proposal • (Y2) - No confirmation defined as the final service confirmation • (Y8) - Error in credit memo • (Y9) - Error in debit memo	Service Order (SRV0)
Not Fully Billed	This view displays all service orders that are billing relevant that have not been fully billed. This includes both service orders that haven't been billed as well as service orders that have been partially billed.	Service Order (SRV0)
Confirmation Issue	• (C002) - A released service order has at least one service confirmation which contains errors. • (C003) - A released service order has at least one service confirmation with life cycle status Open. • (C004) - A released service order has no service confirmation defined as the final confirmation.	Service Order (SRV0)

Issue Type	Description	Transaction Type
	• (C005) - A released service order has more than one service confirmation defined as the final confirmation. • (C006) - A released service order has at least one service confirmation that has been canceled. • (C007) - A released service order item has a completed, billing-relevant service confirmation item that has not been fully billed. • (C008) - A released service order item has a completed, billing-relevant service confirmation item, for which data transfer to a follow-up process, such as billing or procurement, failed or hasn't been completed.	
Contains Error	This view displays service orders that contain a minimum of one error at header and/or item level.	Service Order (SRV0)
No Confirmations	This view displays released service orders for which no service confirmations have been created.	Service Order (SRV0)
Rejected	This view displays service orders that have been rejected. These may be orders that have been, for instance, canceled internally, canceled due to an error or rejected by your customer.	Service Order (SRV0)
SLA Issue	This view displays open service order items whose due date defined in the assigned service and response profiles has expired.	Service Order (SRV0)
Transfer Issue	This view displays service orders, for which the data transfer to a follow-up process, such as billing or procurement, failed or hasn't been completed.	Service Order (SRV0)

i Note

Errors and confirmation issues are reported at header and item level. However, errors and issues at header level are only reported if the same error or issue does not occur at item level, too. In this case, the related items are listed as 000000 in report views.

Information for Key Users

The standard app displays fulfillment issues in Service that exist in your system. In order to avoid performance issues, SAP recommends that you configure the app to users' needs by specifying the characteristics they want to see.

Example: You only want to analyze issues affecting service orders in Nevada. Therefore, you use a filter to set the appropriate sales organization and transaction types.

Supported Device Types

- Desktop
- Tablet

Service Orders Analysis

To ensure that you provide services on time, you require information on the status of service orders. Using this app, you can display and analyze incomplete service orders, identify the most critical ones and speed up the processing of these orders.

Key Features

You can use this app to display a list of incomplete service orders. Incomplete service orders are orders for which no service confirmations exist. This implies that the execution of the service hasn't started yet. Alternatively, one or more completed service confirmations exist, but the service order hasn't been set to status **Completed**. This may be due to the fact that there are still one or more open service confirmations or because no service confirmation has been defined as the final confirmation.

i Note

You access this app through the [Service Management Overview](#) app.

You can use this app to:

- Display a list of incomplete service orders
- Filter the list by such options as:
 - Service order type
 - Life cycle status
 - Item category
 - Sales organization, sales office, or sales group
 - Requested start
 - Requested end
 - Planned start
 - Planned end
 - Order priority
 - Equipment ID

i Note

To ensure optimal system performance, we recommend that you enable only the visual filters that are relevant for your work.

- Sort the list using various sorting criteria, such as error status, sold-to party, net order value, or reference object and reference object type
- Navigate to the [Manage Service Orders](#) app to obtain additional information on a specific service order, identify issues, and take appropriate action
- Use a variety of charts to analyze service processes
- Create, save, and share custom views

In addition, the app supports SAP Jam integration.

Supported Device Types

- Desktop

Related Information

[Service Management Overview](#)

[Service Orders](#)

App Extensibility: Service Orders Analysis

As a key user, you can extend the [Service Orders Analysis](#) app according to your business needs.

Features

You can extend the app in the [Custom Fields](#) app using the business context [Service Item](#). To add a custom field to an app, you must enable the specific views for the field.

You can enable usage of your custom fields in the [UIs and Reports](#) section of the custom field maintenance for the following data sources:

- C_IncmpltSrvOrdAnlys
- I_ServiceOrderItemCube
- I_ServiceDocumentItem
- I_ServiceDocumentItemEnhcd
- CRMS4_SERV_MANGMT_OVP_SRV

After you save and then publish the changes, the field is available in the compact filter section and in the content table.

For more information about how to adapt an SAP Fiori UI at runtime, see [Making UI Changes \(Object Pages\)](#).

Related Information

[Key User Extensibility](#)

[Custom Fields App and Custom Logic App](#)

Service Orders - Flexible Analysis

With this app, you can use a flexible combination of dimensions to analyze service orders, including the service order items that have service contract items assigned.

For example, you can analyze which of your key contracts have open service orders with the highest net value so that you can prioritize and expedite them. Or you can also evaluate the ratio of the contract-based services to the non-contract services delivered by your team, for example, in the last three months. In this way, you can assess the contribution of non-contract services to the overall revenue of your team, analyze these services, and consider bringing them under contract.

Key Features

You can use this app to do the following:

- Analyze key performance indicators related to service orders in multidimensional reports using the following measures:


Measure	Description
Quantity	Amount of provided services
No. of Contract-Based Service Order Items	Number of service order items that are not canceled and are assigned to a specific service contract item
No. of Non-Contract Service Order Items	Number of service order items that are not canceled and are not assigned to a specific service contract item
Net Value of Service Contract Item	Net value of a service contract item
Net Value of Contract-Based Services	Net value of service order items that are not canceled and are assigned to a specific service contract item
Net Value of Non-Contract Services	Net value of service order items that are not canceled and are not assigned to a specific service contract item
Billed Value of Contract-Based Services	Billed value of service order items that are not canceled and are assigned to a specific service contract item
Billed Value of Non-Contract Services	Billed value of service order items that are not canceled and are not assigned to a specific service contract item

- Filter the items according to various criteria, such as sold-to party, sales organization, equipment category, contract start and contract end, the ID of the service contract assigned to a service order item, or a product used in a service order item
- Sort and display the report data as a table or a chart
- Export the report as an Excel or a PDF
- Navigate to the following apps to further analyze the selected service order data:
 - [Manage Service Orders](#)
 - [Overdue Service Orders Analysis](#)
 - [Service Management Overview](#)
 - [Service Orders Analysis](#)
 - [Service Orders - Actuals](#)

For more information about how to analyze your data, see [Multidimensional Data Grid Apps](#).

Working with Analytical Reports (English Only)

Watch the video to learn more about the general functions offered by this app.



[Open this video in a new window](#)

Supported Device Types

- Desktop
- Tablet

Related Information

[Multidimensional Data Grid Apps](#)

[Analytical Key Figures](#)

Monitor Advance Shipment Stock

App ID: F8856

With this app, you can track consignment stock at customer locations, enhancing visibility into stock consumption and returns. This app allows for proactive management of unused stock, ensuring efficient service operations and inventory control.

Key Features

You can use this app to do the following:

- Track the lifecycle of consignment stock sent to customer sites, from shipment to consumption or return.
- Provide real-time visibility into consignment stock at each customer location.
- Identify stock that has been consumed.

Supported Device Types

- Desktop
- Tablet
- Smartphone

Related Information

[Advance Shipment](#)

Warranty Management

Warranty Management involves recording of warranty related information for assets sold and/or installed at customer sites, including equipment, facilities, and software applications. You can use this solution capability to streamline and manage the entire warranty claims process.

[Warranties \(CS-AG-WA/PM-EQM-SF\)](#)

[Warranty Claim Processing \(LO-WTY\)](#)

[Warranty Claim Processing \(Fiori\)](#)

The warranty claim processing has been developed to fulfil the needs of both customers and suppliers.

Warranties (CS-AG-WA/PM-EQM-SF)

Purpose

A warranty defines the scope of the services provided by a company in the event of damages to, or problems with, technical objects.

Integration

You can assign warranties to equipment, functional locations, and serial numbers.

Key Features

You can use this component to cover the following warranties from the point of view of the system user:

- Warrantee (inbound) (for example, manufacturer warranty and vendor warranty)

Example:

You purchase a new piece of equipment and receive a warranty from the manufacturer that covers a certain period of time or usage (manufacturer warranty).

- Warrantor (outbound) (for example, customer warranty)

Example:

You sell or rent a piece of equipment and admit a warranty to your customer.

Warranty

Definition

Promise of manufacturer, supplier, or vendor to a customer to perform services wholly or partly without payment for a certain period of time. A warranty always refers to a technical object. It can refer to an internal object or a customer object.

Use

Many business transactions, such as purchasing, sales, and maintenance of products include a warranty. If, for example, you buy a new product, you receive a guarantee from the manufacturer that covers a particular time frame or a particular use. If, for example, you sell or rent a product, you may be legally required to provide your customers with a warranty for this product. Accordingly, as a provider of services you might possibly have to give a written guarantee on the scope of the services to be provided by you, both to protect yourself as well as to protect the customers.

Before you can issue warranties for individual objects, you must define basic conditions and requirements. These conditions and requirements can refer very specifically to your company, your products, your customers and your customer groups, or differ from country to country or from region to region.

Service provides the following types of warranty:

- Warranty period

A type of warranty that covers an item for a defined period of time. This type of warranty has a start date and an end date. For example, a laptop or a mobile phone.

- [Master warranties](#)

A type of warranty that covers an item based on well defined conditions. This type of warranty has a start date but its validity is based on the realization of its usage. For example, the engine of a car is covered under warranty for either the first five years or for 100,000 km whichever condition is met first.

The system can automatically check the warranty when processing a customer message, a service- or maintenance order, or a billing request.

Master Warranty

Definition

The master warranty is composed of the following parts:

- Warranty header (warranty type, description, classification)
- Warranty service items (including/excluding services)
- Warranty counter (counter, limits)

Structure

Warranty header

The header data refer to the whole data record. You can specify the following data at header level:

- **Warranty type**

In this field you specify which warranty type you would like to define, that is, whether the warranty is used as a manufacturer- or supplier warranty (inbound) or as a customer warranty (outbound).

- **Indicator: Pass on warranty**

This indicator specifies whether the master warranty should be passed on from the technical object to the technical objects on a lower-level of the hierarchy. Then the warranty of the technical object of the higher hierarchy level is also displayed during the warranty check of the lower-level technical objects. For each warranty type a maximum of one higher-level technical object is displayed, if there is one.

- **Sort field warranties**

The freely-definable sort field is mainly for searching for particular warranties.

- **Accounting indicator**

You can set an accounting indicator at header level. When assigning a warranty to an equipment with a warranty start date, and creating a service order for the equipment, the accounting indicator with the warranty information is copied over from the master warranty to the service order as part of the *Service with Advanced Execution* scenario.

You can use Customizing activity [Define Accounting Indicators](#) to define your own accounting indicators in Customizing for [Plant Maintenance and Customer Service](#) under [► Maintenance and Service Processing ► Maintenance and Service Orders ► General Data ►](#).

- **Short text/long text**

In the long text you can list general conditions that affect the validity of the warranty (for example, the warranty services only apply if the device has been used correctly). You can create texts in different languages.

- **Classification**

If you must manage a lot of different warranties, you can assign them to certain classes (for example, classes for the various suppliers, customer groups, and so on). This simplifies search processes, and supports evaluations from particular aspects.

Warranty service items

You can enter as many service items as you want in the master warranty record. You must use one of the following options to describe each item:

- **Service master record**

You can enter a specific service master record as the master warranty item or keep the service column blank to specify that all the services are included in the warranty.

i Note

You can include warranty for all the service items by maintaining a blank entry in the Service column as an item of the master warranty. You do this in the Customizing by selecting the [Enable Inclusion or Exclusion of All Services](#) checkbox under [► Service ► Transactions ► Settings for Service Transactions ► Define Profile for Warranty Check ►](#) to enable this functionality.

- **Short text/long text**

You can create texts in different languages. When you choose a service master record, the system automatically displays the text for this service or activity.

- **Checkboxes**

Depending on the type of service entered, the system uses the **Configured** and **Service is configurable** checkboxes to display whether the service is already configured or whether it can be configured.

- **Including/Excluding services**

You must enter an including/excluding indicator for each service item. You use this indicator to specify whether the service should be included in the warranty or whether it is excluded. Included and excluded items can be combined in a warranty. Only included items are checked.

❖ Example

A warranty for a vehicle includes the following items:

Items	Incl./Excl.
Engine	Included
Body	Included
Corrosion protection	Included
Damages to canopy hood	Excluded
Damages to windscreen	Excluded

Warranty counter

Each service item has one or more counters, which are used to document the time or the counter readings for the validity of the warranty. You generally do not need a counter for items which should be excluded from the general warranty conditions. If you have assigned more than one counter to an item, you must determine

- whether **all** counters must be valid so that the warranty item is valid, or
- whether **at least one** counter must be valid

To define the relationship between the different counters of an item, you must select one of the following radio buttons:

- AND

specifies that all counter readings must be filled for the warranty to be effective

- OR

specifies that at least one of the counter readings must be filled for the warranty to be effective

i Note

Before you create a warranty, you should define all the counters that you need. In the system, warranty counters are displayed with the characteristics of the classification system. For more information, see [Define Warranty Counter](#) .

For each counter you must enter a value for the unit of measurement, for example,

i Note Warranty time	i Note 1 year
--------------------------------	-------------------------

Operating hours	500 hours
Counter reading	9999

The counter unit is displayed by a characteristic unit in the system. This measurement unit can be the connection between the warranty record and the master record of the object for which the warranty was created.

Integration

The warranty can be assigned to equipment, functional locations, or even serial numbers. You can assign two types of warranty (customer/supplier warranty) for each object.

Caution

In doing this, note that one of the two warranty types must be “inbound” and the other must be “outbound”. This means, the warranty types must have **different** warranty categories.

The warranty data is processed using special settings in Customizing of [Plant Maintenance and Customer Service](#) under [Master Data in Plant Maintenance and Customer Service](#) > [Technical Objects](#) > [Basic Settings](#) > [Warranties](#).

Warranty Determination

i Note

The features described here are only available in Service.

Warranty Status

The [Warranty Status](#) field compiles and displays the warranty status of all service items in a transaction as one of the following values:

- **Complete Warranty**: indicates that all service items are covered under warranty
- **Partial Warranty**: indicates that one or more items are out of warranty
- **No Warranty**: indicates that no item is under warranty

Warranty status on item level is indicated by the checkbox [Under Warranty](#).

Warranty Scenarios for Service Items

Service items are covered by one of the following warranty scenarios:

- **Under warranty**

In this scenario, the service item is under warranty and the [Under Warranty](#) checkbox is automatically selected. This checkbox can be manually deselected if you need to remove the warranty for the item. If the service item is of the master warranty type, the warranty ID is automatically populated, and if the item is of warranty period type, the warranty end date is automatically populated.

- **Expired warranty**

In this scenario, the service item isn't in warranty and the **Under Warranty** checkbox is automatically unchecked. This checkbox can be manually selected if you need to add the warranty for the item. If the service item is of the master warranty type, the warranty ID is automatically populated, and if the item is of warranty period type, the warranty end date is automatically populated.

i Note

To manually select **Under Warranty**, you need to ensure that the **Consider Expired Warranty** checkbox has been selected in **Profile for Warranty Checks** in the Customizing activity **Define Profile for Warranty Check**.

• No warranty

In this scenario, no warranty has been assigned to the main reference object of the service item. The **Under Warranty** checkbox is automatically unchecked and disabled for accepting any manual input. The warranty ID and the warranty end date are left blank and non-editable since neither master warranty nor warranty period is associated with the item.

Warranty Type	Warranty Scenario	Under Warranty Checkbox	Warranty ID	End Date
Master Warranty	Under warranty	Checked	Filled	Not applicable
	Expired warranty	Unchecked	Filled	Not applicable
Warranty Period	Under warranty	Checked	Not applicable	Filled
	Expired warranty	Unchecked	Not applicable	Filled
No Warranty Assigned	No warranty	Unchecked and non-editable	Not applicable	Not applicable

Warranty Determination on Item Level

- **Under Warranty:** The system checks if the current counter reading of the main reference object of the service item or the reference date of the service item is within warranty.
- **Warranty ID:** This value is derived from the main reference object of the item in the case of master warranty.
- **Warranty End Date:** This value is derived from the main reference object of the item in the case of warranty period.
- **Accounting Indicator:** This value is copied from the assigned master warranty and can be manually changed.

i Note

If the warranty type is **Warranty Period**, the accounting indicator is left blank.

Warranty Determination on Header Level

- **Warranty Status:** The aggregated warranty of all items is displayed either as complete warranty, partial warranty, or no warranty.
- **Warranty ID:** This value is derived from the main reference object of the header in the case of master warranty.
- **Warranty End Date:** This value is derived from the main reference object of the item in the case of warranty period.

Warranty Assignment Block

The **Warranty** assignment block displays data when the warranty type is master warranty. This block provides information on the conditions surrounding the warranty such as counter readings that indicate current usage, maximum warranty reading, remaining

Defining a Warranty Counter

Use

There are time-dependent and performance-dependent warranty counters:

- If the indicator for time-dependence is set in Customizing, then the warranty counter is **time-dependent**. In this case, you must create a characteristic of the same name, which has a unit of the “time” dimension, in the class system.

The system can use this to determine from the warranty start date and the value that was stored in the master warranty for this counter, whether the counter check is still valid for the key date.

- If the indicator for time-dependence is not set in Customizing, then the warranty counter is **performance-dependent**. In this case, the following prerequisites must be fulfilled so that the system can perform a check:
 - For this warranty counter, a measuring point must exist at the technical object.
 - At least one measurement document must have been recorded since warranty start for this measuring point.

Prerequisites

Warranty counters are normally defined by your system administrator when he or she is configuring the system. If you have the necessary authorizations, you can use the classification system to create warranty counters.

Procedure

1. Create warranty counters as a characteristic in the classification system.

To do this, choose **Logistics > Central Functions > Class System > Master Data > Characteristics Management.**

2. Enter the name of the characteristic and choose **Create**.

The **Create Characteristic** screen appears.

3. Enter a short text for the characteristic in the **Basic Data** section .

Enter a numerical data type in the **Format Details** section.

4. Choose **Continue**.

5. Enter the number of places, the decimal places, and the unit of measurement for the warranty counter (for example, the unit **Year** for the **Warranty Time** characteristic).

6. Save the characteristic.

For more information, see Characteristics (CA-CLCHR).

7. Define the warranty counter in Customizing under **Plant Maintenance and Customer Service > Master Data in Plant Maintenance and Customer Service > Basic Settings > Warranties > Define Warranty Counters**

i Note

Only warranty counters which are specified in Customizing are recognized by the system as valid counter types.

Creating a Master Warranty

1. Choose ► [Logistics](#) ► [Customer Service](#) ► [Service agreements](#) ► [Warranties](#) ► [Master warranty](#) ► [Create](#) ►.

The initial screen [Create master warranty](#) is displayed, where you can enter the warranty number if your company uses external number assignment.

2. Choose [Continue](#). The initial master warranty screen is displayed.

Enter the short text for the warranty header. If necessary, you can add a more detailed description using the long text function.

3. Enter the warranty type.

The warranty type specifies what sort of warranty is involved. For more information, see [Warranty Management](#)

4. Enter a service in the block [Service](#). Depending on the type of service entered, the system displays whether the service is already configured or whether it is configurable in the checkboxes [Configured](#) and [Service is configurable](#). You can change the configuration of the service by choosing [Configuration](#). You must enter an inclusive/exclusive indicator for each service item. You use this indicator to define whether the item should be included in the warranty, or whether it is excluded from it. Inclusive and exclusive items can be combined in a warranty.

5. Select one of the following radio buttons to define the relationship between the different counters for an item:

AND specifies that all counter readings must be valid in order for the warranty to be valid

OR specifies that at least one of the counter readings must be valid, in order for the warranty to be valid

6. Enter one or more warranty counters together with the appropriate value for each service item.

The counters record the time or the counter readings for the validity of the warranty. The value entered, together with the unit of measure, equals the maximum amount (time or counter reading) for which the warranty is valid (for example, up to 1 year, or up to a reading of 9999).

For more information, see [Defining a Warranty Counter](#)

i Note

You can classify master warranties by choosing [Classification](#). In order to do this, you must have already created the classes for the master warranties in the Classification System. The advantage of this is that you can then search for master warranties by class. For more information, see [CA-Classification](#).

Warranty Management

Use

Before you create a warranty record, you must specify how the warranty should be used. For this you need the **warranty type**.

The warranty type specifies what type of warranty is concerned, that is, how it is used. The warranty type is assigned to an internal warranty category, which specifies whether the system user's company is the guarantor or the warrantee.

Prerequisites

The standard system differentiates between the following types of warranty from the system user's perspective:

Warranty type	Warranty category
Manufacturer- and supplier warranty	Warrantee (inbound)
Customer warranty	Guarantor (outbound)

In Customizing you can define the various warranty types that are used in your company and assign each warranty type to one of the two warranty categories. If you, as a system user, [create a master warranty](#) you must use of the existing warranty types for that.

Features

Every warranty type is assigned to a **warranty category** within the system. In the system there are two warranty categories, which specify the system user's view of the warranty. The warranty categories have a fixed definition in the system and cannot be changed. The warranty category has the following two specifications:

- Warrantee (inbound)

The warranty is issued externally, for example, from a supplier or a manufacturer. The observer is the warrantee.

- Guarantor (outbound)

The warranty is issued by your own company and goes to a customer. The observer is the guarantor.

i Note

The warranty category is set internally in the system and cannot be changed on a company-specific basis.

❖ Example

A photocopier supplier sells you a device. The supplier gives you a warranty for the device. This warranty is noted in the system as a **received warranty (inbound)** under the **Warrantee** warranty type. (In this case the warranty type is **Supplier Warranty**.)

You then sell or rent the device to a customer and give this customer a warranty for the device. This warranty is noted in the system as an **issued warranty (outbound)** under the **Warrantee** warranty type. (In this case the warranty type is **Customer Warranty**.)

Warranty Check

Use

You can use the warranty check to determine whether a warranty still exists for a technical object. If certain prerequisites have been met, you also have the option of displaying the warranty data of the superordinate technical objects (warranty inheritance).

Prerequisites

In Customizing for Plant Maintenance and Customer Service, under **Define Warranty Types** you can stipulate when the warranty check is processed: whether an automatic dialog box should appear if the warranty check is positive when you create a notification, an order, and for the flexible billing.

The following prerequisites must be met for the **warranty inheritance**:

- The superordinate technical object and the subordinate technical object must be assigned to a warranty.

- In the **superordinate** technical object, the indicator **Bequeath Warranty** must be set.
- In the **subordinate** technical object, the indicator **Inherit Warranty** must be set.

Features

Warranty Check

A warranty can begin at different time points, such as the following:

- Purchase date (for example, in the case of a machine)
- Installment date (for example, in the case of a computer)
- Operating start date and time
- Combination of the above

The validity period is calculated from that point in time, based on the time or counter readings specified.

When a claim is made for a warranty service, each counter must be checked to determine whether the warranty is still valid for that counter. Depending on the counters involved, this check is either performed automatically by the system, or manually by the user.

- For example, if the warranty is valid for a certain **period of time** from the start date, the system can determine automatically whether the claim is being made within the validity period of the warranty.
- If, for example, the validity of the warranty depends on a **counter reading**, the system technician must take the counter reading and check it against the warranty conditions.

❖ Example

A car dealer sells a car on 01.01.10 with a general warranty valid for up to 1 year or up to 10,000 miles, and a corrosion guarantee valid for up to 5 years from date of purchase.

Six months later, the owner brings his car back to the customer services department. The car dealer performs normal customer service as stipulated by the manufacturer, and checks the service items in the warranty, to establish whether the services that have been performed are covered by the warranty.

The dealer checks the period of time automatically on the basis of the day's date.

He checks the actual mileage of the car's milometer.

If there are particular problems found with the car (for example, first rust patches), these must be checked by an expert. The expert then decides whether the warranty covers the fixing of these problems. He also checks, for example, what external influences the car has been subjected to during the period of time in consideration. Information regarding conditions or usage can be entered in long text form.

Warranty Bequest

The indicators for the warrant bequest have the following meaning:

- **Bequeath Warranty** in the superordinate technical object

If this indicator is set, then the warranty data of the superordinate technical objects are displayed during the warranty check as well as the warranty data for the technical objects checked. However, you can only display a maximum of one superordinate technical object for each warranty type.

The system searches for the next-highest equipment and the next-highest functional location for which the indicator **Bequeath Warranty** is set, and to which a master warranty or a warranty period is assigned.

You can also set the indicator **Bequeath Warranty** when you create a **master warranty**. In this case it specifies whether the master warranty of the technical object should be passed on to the technical objects lower down in the hierarchy. It is copied automatically if you enter the master warranty in a technical object.

- **Inherit Warranty** in the subordinate technical object

If this indicator is set, both the warranties that have been passed on and the warranties for the technical object are displayed in a list for the warranty check. If the indicator is not set, only the warranties for the technical object are displayed.

Warranty Claim Processing (LO-WTY)

Purpose

The component **Warranty Claim Processing** has been developed to fulfill the needs both of **manufacturers, importers or vendors of complex products** and their suppliers.

In this business environment, the prerequisites for a right to warranty are becoming more extensive and more complex. **Warranty restrictions due to the length of service or age of the product, authorization processes** and comprehensive **check mechanisms** in the warranty claim make warranty claim processing in many companies a timely and costly procedure. Furthermore, due to a European legal initiative, the warranty or guarantee period for products of specific industry sectors has been extended to **at least two years**. The number of incoming warranty claims has, understandably, increased in the wake of this decision.

Warranty Claim Processing functions offer you a software solution that can deal with a **large number of warranty claims** comfortably and, as far as possible, **automatically**. Only those claims that produce negative results in the **automatic checks** are included in manual processing. You also have a maximum amount of flexibility as regards the warranty conditions that you can define.

Integration

Warranty Claim Processing is a cross-application component that is completely integrated into the SAP solution, from master data management (MM, SD, CS, PM) and pricing (SD) through checking master warranties and creating measurement documents (CS, PM) to posting FI documents (FI/CO) and evaluation of the warranty data (SAP BW).

- [Materials \(LO-MD-MM\)](#), [Serial Numbers \(LO-MD-SN\)](#)
- [Vendors \(MM\)](#), [Customers \(SD\)](#)
- [Vehicles in the Vehicle Management System \(IS-A-VMS\)](#)
- [Equipment, Functional Locations, Installed Bases \(CS-BD / PM-EQM-EQ\)](#)
- [Master Warranties \(CS-AG-WA / PM-EQM-SF\)](#)
- Posting Measurement Documents (CS-IB-MC / PM-EQM-SF-MPC)
- Service Contracts (SD-SLS-OA-SCO)
- [Catalogs \(IS-EC-CEM\)](#)
- [VSR Checks \(FI-SL\)](#)
- IDoc Interface (BC-SRVI-EDI)
- [Message Determination \(CA-GTF-BS\)](#)
- [Pricing \(SD-BF-PR\)](#)

- [Revenue Account Determination \(SD-BF-ACT\)](#)
- [Posting FI Documents and Updating the Values \(FI/CO\)](#)
- [Archiving Warranty Claims \(CA-ARC\)](#)
- [Online Reporting Using SAP Query \(BC-SRV-QUE\)](#)
- [Reporting in SAP Business Warehouse \(SAP BW\)](#)

Features

Warranty Claim Processing offers the following **functions**:

- [Storage of Master Data for Warranty Claim Processing](#)
- [Data Management and Interface for Communication with Claimant and Reimbursing](#)
- [Checks for Automatic Processing of Warranty Claims](#)
- Automatic [Pricing](#) and [Revenue Account Determination](#) with [Posting of Documents in FI and CO](#)
- Numerous [actions](#) that cover the most common warranty claim processing procedures
- Interfaces
 - for generating worklists
 - for [manual processing](#) of warranty claims
 - for [finding](#) warranty claims according to selection criteria
 - for creating [recalls](#) and [authorizations](#)
 - for posting incoming [parts that have to be returned](#)
 - for creating [credit memo lists](#)
 - for [archiving](#)
 - for [mass processing](#)
 - for [online reporting](#)

Objects in a warranty claim can be:

- [Vehicles](#) in the [Vehicle Management System](#)
- [Equipment](#)
- [Functional Locations](#)
- [Installed Bases](#)
- [Material Numbers with Serial Number](#)

i Note

You can use BADIs WTY_READ_SUPPL_DATA and WTY_F4_RELOB to link in other objects according to customer-specific objects.

The following **processes** are supported:

- [Processing with Postcrediting/Precrediting](#)
- [Processing with Authorized Goodwill](#)
- [Processing with Parts to be Returned](#)
- [Processing with Claim Split](#)
- [Processing with Recalls/Technical Campaigns](#)

Transactions

Customizing

Transaction Code	Description
OWTY	Customizing for Warranty Processing

Master Data

Transaction Code	Description
Material Master Record	
MM01, MM02, MM03	Create, change and display material master record
Business Partner	
XK01, XK02, XK03	Create, change and display supplier (creditor) centrally
XD01, XD02, XD03	Create, change and display customer (debtor) centrally
Warranty Objects	
IE01, IE02, IE03	Create, change and display equipment
IL01, IL02, IL03	Create, change and display functional location
IB51, IB52, IB53	Create, change and display installed base
IQ01, IQ02, IQ03	Create, change and display serial number
VELO (only with SAP Discrete Industries; not with SAP S/4HANA Enterprise)	Vehicle Manager (create, change and display vehicle data)
Warranty Conditions	
CT04	Create, change and display warranty counter/characteristics
BGM1, BGM2, BGM3	Create, change and display master warranty
IK01, IK02, IK03	Create, change and display measuring point
IK11, IK12, IK13	Create, change and display measurement document
Other	

Transaction Code	Description
J3GK01, J3GK02, J3GK03 (only with SAP Discrete Industries; not with SAP S/4HANA Enterprise)	Create, change and display catalog entry
FB05	Post outgoing payments
VA41, VA42, VA43	Create, change and display contracts for service object
WE20	Create, change and display partner profiles
SQ1, SQ2, SQ3	Online reporting: maintain queries, InfoSets and user groups
RSA2	Create, change and display DataSources for BW extraction
RSA3	Extract DataSources to BW

Warranty Claim Processing

Transaction Code	Description
Warranty Claim Processing	
WTY	Create, change and display warranty claim
WTYQQ	Process worklist
WTYSE	Find warranty claims
WTYAUT	Create, change and display authorization
WTYRCL	Create, change and display recall
WTYRP	Change status of parts to be returned
WTYCL	Create credit memo list
WTY_ARCHIV	Display archived warranty claims
Master Data	
WTY_UPROF	Assign user profiles
WYP1, WYP2, WYP3	Create, change and display condition records for pricing
WYN1, WYN2, WYN3	Create, change and display message records
WTY_VSR_ACTIVE	Activate validations and substitutions
WTYRCL	Create, change and display recall
Tools	
WTYMP_A	Define mass processing job
WTYMP	Execute mass processing job
WTY_SARA	Archive warranty claims
WTYOR	Execute report

Processes in Warranty Claim Processing

The following **processes** show you how you can use the scope of functions provided in Warranty Claim Processing. All the processes are merely examples that will certainly not occur in business practice in exactly this form.

- [Processing with Postcrediting/Precrediting](#) (standard processing)
- [Processing with Authorized Goodwill](#) for cases when the warranty conditions are no longer fulfilled
- [Processing with Recalls/Technical Campaigns](#) for cases when serious technical faults in the warranty object are to be removed at the cost of the reimbursor
- [Processing with Claim Split](#) when there is more than one reimbursor for the items in a warranty claim
- [Processing with Parts to be Returned](#)

The following processes are not separate forms of warranty claim processing but **partial processes** that can occur in each of the above-named processes:

- [Warranty Check](#) for checking whether the warranty conditions have been fulfilled
- [Posting in Accounting \(FI/CO\)](#) and updating the values
- The process [Grouping of Credit Memos](#) is a separate and optional process during which the posting of credit memos to the claimant is simplified by grouping several credit memos together in a credit memo list.

Processing with Postcrediting/Precrediting

Purpose

This following describes the standard process for warranty claim processing.

in postcrediting cases, i.e.: cases in which the claimant is not provided with a credit memo until an answer has been received from the reimbursor.

in precrediting cases, i.e.: cases in which the claimant is provided with a credit memo immediately and the claim is then sent to the reimbursor later.

Prerequisites

You are familiar with the structure and concepts of the [warranty claim](#) .

You have created the necessary [master data](#) .

You have checked the [control data](#) for warranty processing in Customizing and adjusted the settings to suit your business processes.

Process Flow

Postcrediting

The claimant creates a [warranty claim](#) with individual items (material, labor value, external services, lists) and measurement data (number of kilometers or operating hours) in his/her own system, for example as an XML document, and sends it as an IDoc via

EDI to the processor of the claim. Alternatively, he/she creates the claim in the Dealer Portal or Warranty Web Interface directly in the claim processor's system.

A warranty claim is created automatically from the IDoc in the processor's system ([Version](#) 1: version from claimant). This takes place either manually or via a batch program with appropriate mapping that is processed periodically, for example once a day.

Flexible checks run automatically in the processor's system to check, for example, whether the claimant is authorized to create warranty claims, all the necessary data is complete etc. This all takes place via [action control](#) in combination with [VSR checks](#) . Furthermore, the system then decides, on the basis of the measurement data, whether the claim is accepted, automatically corrected, transferred to manual processing or rejected ([Warranty Check](#)). If the prices for the claim items are not given by the claimant, they are automatically determined using [pricing](#) functions. The entire automatic processing is executed via program **RWTY0001 of the [mass processing function in connection with action control](#)**

If the claim is rejected, it is automatically returned to the claimant for follow-up processing using [message determination](#) . The claimant can then resubmit the claim in a new version. If the claim is accepted, [message determination](#) functions are used to automatically forward a new version of the claim to the reimburer via IDoc/EDI (version 2: version to reimburer).

The claim, having been processed by the reimburer, returns to the claim processor (version 3: version from reimburer).

The claim processor checks this claim. All this again takes place using [action control](#) functions in combination with the [VSR checks](#) . A decision is then made whether the version is accepted by the reimburer or transferred to manual processing.

After manual processing, the claim processor can send a new version for processing to the reimburer (resubmission). Accepted versions are automatically returned to the claimant using [message determination](#) (version 4: version to claimant).


The accounting documents are posted: credit memo to claimant, debit memo to reimburer etc..

The [values are updated in FI and CO](#) on the basis of [revenue account determination](#) and [CO account determination](#) .

The claim is completed either automatically via an action or manually by choosing the appropriate function  .



You can open the claim again by choosing **Warranty Claim → Process Again** .



Warranty Claim Processing: Standard Process

Precrediting

The sequence of the versions is as follows for precrediting:

Version 1: version from claimant

Version 2: version to claimant

Version 3: version to reimbursor

Version 4: version from reimbursor

The rest of the processing steps correspond to those for postcrediting.

Result

Processing is complete. In the best case scenario, i.e.:

if automatic processing has been programmed and correctly defined in Customizing

and

if no errors occur during processing that would otherwise make manual processing necessary

processing runs completely automatically in the background.

The person responsible can display a work list of warranty claims by using the transaction WTYOQ. You can select according to processing status. You can, for example, choose to display only the warranty claims for which errors occurred during processing, i.e. ones that have not yet been completed. You can call and process the warranty claims separately from the work list.

You can [archive](#) completed warranty claims by using transaction WTY_SARA.

Processing with Authorized Goodwill

Purpose

You use this process if you want to authorize a claimant to submit a warranty claim for an object for which, according to the warranty conditions, there is no longer a warranty. In other words, you want to make use of **goodwill**. The system can then **check this authorization** and process the claim **automatically**.

Prerequisites

- For prerequisites, see: [Processing With Postcrediting/Precrediting](#)
- You have programmed an authorization check in the [VSR checks](#) or in an appropriate action.

i Note

The standard system does not contain any action that automatically carries out such a check.

- You have created a special [claim type](#) for authorizations in Customizing for **Warranty Claim Processing** under **Define Warranty Claim Types**.

Process Flow

1. You clarify with the claimant that he/she can make a warranty claim for the object in question although the warranty conditions are no longer fulfilled.
2. You create an authorization in the system on the basis of a warranty type for authorizations (**transaction WTYAUT**). Object type, object number, partner and the items that are affected by the warranty claim are required entries.
3. You approve the authorization (action A300 [Approve Authorization](#)).

i Note

You can cancel the authorization with action A301 ([Reset Approval of Authorization](#)).

4. You forward the authorization number to the claimant.
5. The claimant creates a warranty claim for this object and enters the authorization number and the name of the person granting the authorization.
6. A VSR check or an actions (see: prerequisites) checks whether the object in the claim is the same as the object in the authorization and compares the items contained in each.
7. If the check result is positive, the system automatically processes the claim further.

Processing with Recalls/Technical Campaigns

Purpose

You use this process if you want to enter and process warranty claims with reference to a recall.

In a **recall**, products that have already been sold are recalled publicly to production so that a serious defects or technical errors in the object can be rectified. The **costs of rectifying the defect are carried by the reimbursor or claim processor**, even if the warranty conditions are no longer fulfilled. We are therefore dealing here with a special form of warranty claim processing.

The same applies to a technical campaign, but without the products being recalls publicly. For all products that have to be maintained or repaired anyway, the technical error is eliminated at the same time without the end customer necessarily knowing.

i Note

There is no difference between processing with recalls and processing with technical campaigns in warranty claim processing. This documentation therefore just refers to **recalls**.

Prerequisites

- For prerequisites, see: [Processing With Postcrediting/Precrediting](#)
- You have created a special [claim type](#) for recalls (indicator: recall) in Customizing for [Warranty Claim Processing](#) under [Define Warranty Claim Types](#).

i Note

Two special screen layouts for recall warranty claims are contained in the standard system: one with and one without a navigation tree.

Process Flow

- The reimbursor gives you an external recall number with the appropriate data, i.e.: the validity period of the campaign, the affected objects and the materials and labor values that are incurred in the course of the recall.
- You enter this recall data in the system in the form of a warranty claim with the special claim type for recall claims (**transaction WTYRCL**).
- You release the recall (action A400 [Release Recall](#)).
- You check which of the affected objects have been sold to which customers/claimants and send them appropriate information.
- Your customers provide you with a warranty claim including a dummy item that references this recall (**material** = dummy, **reference type** field = **RC** , **reference number** = external recall number).
- The claim is automatically checked against the recall data. The system checks whether the object in the claim is contained in the recall and whether the reference date is within the recall validity period (action A095, [Find Recalls for Object](#)).
- The dummy item is automatically replaced by the items in the recall (action A096, [Use Recall](#)). The prices from the recall are copied to the warranty claim. For the purposes of reporting, the system stores data specifying for which technical objects warranty claims have been entered with reference to recalls.
- The warranty claim is automatically processed further.

Processing with Claim Split

Purpose

You use this process if there is **more than one reimbursor** for the items in a warranty claim. This could be the case, for example, if for several defects, parts (materials) are requested from different manufacturers who offer a warranty, or when a claim contains

one defect and, at the same time, contains the warranty request for an accessory (independent of the defect).

The process can be used for both **precrediting** and **postcrediting** cases.

During the claim split process, the system creates **several versions for the different reimbursers from one original version from the claimant**. Each individual version can be accepted or rejected by the appropriate reimbursers. Then the system collects the inbound versions from the different reimbursers and groups them together again to form one outbound version to the claimant.

i Note

In precrediting cases, the claimant version that was originally posted has to be cancelled if there are inconsistencies before the reimbursers version can be grouped together.

Prerequisites

- For prerequisites, see: [Processing With Postcrediting/Precrediting](#)
- In Customizing for Warranty Processing under **Define Warranty Claim Types**, you have defined per claim type according to which criteria a claim is to be split, for example, according to the defect code or the vendor/manufacture. You can also choose customer-specific fields as a split criterion.
- If you only want to wait for the complete return and decision on all versions from the reimbursers for a specific pre-defined length of time, you must have defined an appropriate answer period in Customizing for Warranty Processing under **General Settings**.
- The actions for the claim split must be allowed in your [Action Control](#) settings.

Process Flow

1. You receive a claim that should be split from the claimant.
2. You group the claim items according to the split criterion (action A060 **Split Groups Proposal with Dialog Box**) and create, per group, an outbound version to the appropriate reimbursers from the inbound version from the claimant (action A070 **Split Claimant Version in Versions to Reimbursers**). All versions that are created are active.
3. You release the outbound versions to the reimbursers for sending (action A870 **Release Outbound Reimbursers Version for Sending**).
4. The reimbursers send the processed versions back.
5. You check whether a version has been returned within the answer period for each outbound version to the reimbursers (calculated as of the creation date of the warranty claim) and whether this version has been defined as a final version (tab page **Other Version Data**, field **End Version**), i.e.: has been completely processed (action A071 **Group Reimbursers Versions (Claimant)**).
6. If this is the case, the system groups all the versions that have arrived from the reimbursers into one outbound version to the claimant. If this is not the case, i.e.: if a version is missing or a version has not been defined as a final version, the system transfers the claim to manual processing.

i Note

You can automate this process in action control. When you create the appropriate linking action, do not choose action A060 **Split Groups Proposal with Dialog Box** in order to create the split groups; choose action A061 **Split Groups Proposal** to do this.

Processing with Parts to be Returned

Purpose

You use this process if you do not want to process warranty claims until the claimant has returned specific faulty parts to you or to the reimbursor to be checked. In this way you can, for example, discover why a particular part is always defective and thus ultimately improve your **quality assurance** processes.

Prerequisites

- For prerequisites, see: [Processing With Postcrediting/Precrediting](#)
- You have defined the parts that should be returned in the material master record by selecting the **Product Attribute 9** and/or **Product Attribute 10** fields on the tab page **Sales Organization 2**. **Product Attribute 9** indicates the duty of the claimant to return the parts to the claim processor, **Product Attribute 10** indicates the duty of the processor to the reimbursor.

i Note

You can use BAdI WTY_CREATE_COPY to save your own flexible programming for defining the duty to return parts, for example, for linking this duty to the claim type or partner and not to the material or for setting the indicator on customer-specific fields in the material master.

- You have entered a deadline by which parts have to be returned in Customizing for Warranty Claim Processing under **General Settings**. This deadline is valid globally for the entire warranty claim processing.
- You have defined the possible statuses for parts to be returned in Customizing for **Warranty Claim Processing** under **Warranty Claim** ► **Warranty Claim Items** ► **Define Status for Parts to be Returned** ►.

Process Flow

Part process 1: the claimant returns parts to you, the claim processor

1. The claimant sends a warranty claim with a part that has been defined in your system as a part to be returned (**Status Return Parts Claimant: To be returned**).
2. The claimant receives an automatic message from you (via output/message determination) to the effect that he/she has to return this part within a specific time period. This message allows the claimant to print a barcode with claim number and item number as a reference.

When the claimant accesses the data via the Web user interface, all the claims with the status **Pending** are displayed. An action checks the field **Status Return Parts Claimant** and, if necessary, creates a version to the claimant with the status **Pending** from the version from the claimant. The claimant then sees this status in the Web interface.

3. Automatic processing checks at regular intervals whether the part has already been finally delivered and interrupts the automatic processing (action A090 **Check for Parts that have to be Returned**, processing status: **Pending**). Furthermore, it checks whether the return deadline has been adhered to (action A091 **Return Period Check for Parts**). If the part does not arrive within the period of time specified by the deadline, the claim is transferred to manual processing.
4. The claimant sticks the barcode on the part to be returned and sends it back.
5. The barcode is scanned (**transaction WTYRP**). The **Status Return Parts Claimant** field (field for the status of parts) in the warranty claim is then set to **Parts partly returned** or **Final delivery**.

i Note

No goods receipt is posted in transaction WTYRP. A quantity cannot be entered. You can also link in material postings or similar in BAdI WTY_RETURN_PARTS.

6. You check the defective part (quality notification). If the check confirms that the part really is defective, you set the **Status Return Parts Claimant** to **Closed**.
7. The warranty claim is automatically processed further.

Part process 2: as claim processor or claimant, you return parts to the reimburer

This part process is not implemented. You can carry out the part process manually by defining the parts in the field **Status Return Parts Reimburer** as received or you can program an appropriate action for automatic processing.

Warranty Check

Purpose/Use

This process is a partial one that is integrated into every procedure in [warranty claim processing](#). It checks whether the [warranty object](#) still has a valid warranty or not.

Prerequisites

- You have created one or more [master warranties](#) with [warranty counters](#) (transactions BGM1/BGM2/BGM3).
- You have entered the master warranty and the start of the warranty period in the object.
- You have entered measurement positions with characteristics in the object and created measuring points for these measurement positions. The characteristics that you require for the warranty counters have to coincide with the characteristics for the measurement positions in the warranty object.
 - Every non-calendar warranty counter of the master warranty must have been created exactly once as characteristic for the measurement position in the object.
 - Calendar warranty counters of the master warranty should not be copied to the object.

i Note

You can use [reference objects](#) as a reference or a template to copy from when you create measurement positions and measuring points in the object.

i Note

If you want to include the dialog box for the warranty check in the **service notification and the service order**, you need to insert the following coding in customer exit BG000002 in program ZXBG0U02:

```
DATA: ls_bgmkobj TYPE bgmkobj. IF NOT i_equi IS INITIAL.
```

```
ls_bgmkobj-j_objnr = i_equi-objnr.
```

```
ENDIF.
```

```
IF NOT i_iflo IS INITIAL.
```

```
ls_bgmkobj-j_objnr = i_iflo-objnr.
```

```
ENDIF.
```

```
IF NOT ls_bgmkobj-j_objnr IS INITIAL. CALL FUNCTION 'WTY20_DISPLAY_CHECK_DETAIL'
```

```
EXPORTING
```

```
is_bgmkobj = ls_bgmkobj
```

```
iv_check_date = sy-datum.
```

```
ENDIF.
```

```
REFRESH: i_result, i_text1.
```

Process Flow

1. You create a [warranty claim](#) manually or receive one automatically via the Web interface or via IDoc/EDI.
2. You enter the **measurement readings for the version** (example: number of kilometers or operating hours) and, if required, **exactly one measurement reading for the item** in the warranty claim. When you save, CS measurement documents are automatically created with these measurement readings. These measurement documents are then added to the document flow for the warranty claim. No measurement readings are saved in the warranty claim itself.

Alternatively, you can enter the measurement documents outside the warranty claim using transactions **IK11/IK12/IK13** . If you do this, however, they have no reference to the warranty claim version.

A measurement document has to exist for every warranty counter in the object so that the check functions correctly.

3. You start action **A200 Check Master Warranty** either manually or automatically.
4. The system executes the warranty check and compares the measurement readings in the measurement documents with the warranty counter limit values in the master warranties.

To do this, it reads the characteristics/warranty counters in the object and searches for identical characteristics/warranty counters and their value limits in the master warranties. Finally, the system compares the current measurement readings in the warranty claim with the value limits in the master warranties. If a calendar warranty counter has been defined, the system checks whether the reference date for the warranty claim lies within the calculated warranty period.

Result

The system automatically determines whether a valid warranty exists for the [warranty object](#) or not. Depending on the result, the system rejects or accepts the claim, provided the [action](#) with [VSR check](#) has been programmed appropriately.

In manual processing the result is displayed in a dialog screen. During automatic processing the result is saved to the database and can be read by using [VSR checks](#) .

The following results are possible:

- 00 valid warranty, positive check result
- 03 invalid warranty, negative check result
- 01 no warranty check possible since required measuring point is missing
- 02 no warranty check possible since required measurement document is missing
- 04 warranty check date is before warranty start date
- 05 warranty check date is after warranty end date
- 06 warranty object contains two measuring points with the same warranty counter

- 99 negative check result but positive check result for the check on the superior/higher-level object

Example

You have defined a warranty period of two years for a maximum clock reading of 50 000 km in the master warranty.

If you enter a current measurement reading of 49 000 km in the warranty claim but the warranty period has been exceeded, your claim will be rejected.

If you enter a current measurement reading of 49 000 km in the warranty claim and the warranty period has not been exceeded, your claim will be accepted.

Posting in Accounting (FI/CO)

Purpose

This process is a partial one that is integrated into every procedure in [warranty claim processing](#).

Warranty claims generate data that is relevant to accounting. Financial accounting (FI) is involved in the **receivables/debit memos** and **payables/credit memos** that result from Warranty Claim Processing. In cost accounting (Controlling, CO), **warranty costs** (and possibly also revenue) should be analyzed.

Each time, **separate versions** of a warranty claim are posted in accounting. (FI).The versions can be controlled automatically or manually and be transferred to S/4HANA Accounting. You can use Customizing settings to define in which categories the versions should be posted as FI documents.

The calculation of the values of the items in a version including tax is in standard [pricing](#), posting of the credit memos and debit memos to G/L accounts is in standard [revenue account determination](#) and the parallel posting to CO account objects is in standard [CO account determination](#).

The **control logic** for calling the individual functions, on the other hand, is in **Warranty Claim Processing**. This decides when the FI module is called and whether a reversal must be executed beforehand. If you have already posted a version of a warranty claim for a category to FI and you want to create a new version for the same category (with FI posting), you have to reverse/cancel the old FI posting first. If you do not, the data will be posted twice in FI.

The Accounting module is used exclusively for posting receivables/payables against debtors (claimants) and creditors (reimburser). Financial accounting processes the payments and deals with the clearing of open items.

The warranty claim [category](#) and the [partner information](#) (debtor/creditor exists) is used to decide whether a receivable/debit memo or a payable/credit memo is posted.

The version currency is used for the posting.

Prerequisites

You have executed all the steps that are necessary for [pricing](#), [revenue account determination](#) and [CO account determination](#).

Process Flow

The decision code in the warranty claim is the basis for postings in Accounting. There are the following cases:

- **Complete Approval by the Reimbursing**

The reimbursor approves 100% of the amount to which has a claim has been made. The claimant receives a credit memo of 100%, the reimbursor receives a debit memo of 100%. These amounts can be posted automatically to a CO account assignment.

- **Partial Approval by the Reimbursor**

The reimbursor approves X% (0 - 99.9%) of the amount to which has a claim has been made. The claimant receives a credit memo of Y%, the reimbursor receives a debit memo of X%. These X% and Y% can be posted automatically to a CO account assignment. The difference (Y – X) can be posted to no CO account assignment at all, automatically to a different CO account assignment or it the claim processor can distribute it manually to different CO account assignments.

- **Complete Rejection by the Reimbursor**

The reimbursor approves 0% of the amount to which has a claim has been made.

The cases that are processed with **precrediting** and for which **differences** occur are difficult, i.e. those cases in which the reimbursor only partially approves the amount requested by the claimant. Below are some examples.

Precrediting Case with Recall of Difference

In this example, the claim processor reclaims the difference between the amount requested by the claimant, which is credited to the claimant, and the amount actually paid later by the reimbursor. The difference amount is not listed separately. Only the **default CO account assignment** is posted.

1. The claimant forwards a warranty claim of 500 € for a water pump (version from claimant).
2. The claim processor writes a credit memo for 500 € (version to claimant with posting (1) in Accounting).

Posting (1): the customer account is credited with 500 €, the warranty revenue account is debited with 500 €. These 500 € are posted to the default CO account assignment.

3. The claim processor forwards the warranty claim of 500 € to the reimbursor (version to reimbursor).
4. The reimbursor only approves 450 € and receives a debit memo for this amount from the claim processor (version from reimbursor with posting (2) in Accounting).

Posting (2): the vendor account is debited with 450 €, the warranty revenue account is credited with 450 €. These 450 € are posted to the default CO account assignment.

5. The claim processor sends an invoice for 50 € to the claimant (reversal/cancellation of the first version to claimant in posting (3), creation of a new version to claimant in posting (4)).

Posting (3): posting (1) is cancelled/reversed.

Posting (4): finally, the customer account is credited with 450 €, the warranty revenue account is debited with 450 €. These 450 € are posted to the default CO account assignment. The warranty revenue account has been cleared.

Debtor/CL		Warranty Revenue Account		Creditor/RE	
Debit	Credit	Debit	Credit	Debit	Credit
	500 (1)	500 (1)			
			450 (2)	450 (2)	
500 (3)			500 (3)		
	450 (4)	450 (4)			

i Note

CL = claimant, RE = reimburer

Precrediting Case with Recall of Difference and Posting to Interim Account

In this example, the claim processor reclaims the difference between the amount requested by the claimant, which is credited to the claimant, and the amount actually paid later by the reimburer. The difference amount is not listed separately. Only the **default CO account assignment** is posted. The claim processor would like to see the amounts in an **interim account** and not in the warranty revenue account as long as the processing of the warranty claim has not been completed.

1. The claimant forwards a warranty claim of 500 € for a water pump (version from claimant).
2. The claim processor writes a credit memo for 500 € (version to claimant with posting (1) in Accounting).

Posting (1): the customer account is credited with 500 €, the interim account is debited with 500 €. These 500 € are posted to the default CO account assignment.

3. The claim processor forwards the warranty claim of 500 € to the reimburer (version to reimburer).
4. The reimburer only approves 450 €. The claim processor sends the claimant an invoice for 500 €. The reimburer receives debit memo of 450 € from the claim processor (reversal/cancellation of first version to claimant in posting (2), creation of a new version to claimant in posting (3), version from reimburer with posting (4) in Accounting).

Posting (2): posting (1) is cancelled/reversed.

Posting (3): finally, the customer account is credited with 450 €, the interim account is debited with 450 €. These 450 € are posted to the default CO account assignment.

Posting (4): the interim account is credited with 450 €, the warranty revenue account is debited with 450 € (transfer posting). Finally, the warranty revenue account is credited with 450 € and the vendor account is debited with 450 €. These 450 € are posted to the default CO account assignment. The interim account and the warranty revenue account have been cleared.

i Note

Transfer posting from the interim account to the warranty revenue account is controlled via the pricing procedure and the account key (see also; [Pricing](#)).

Debtor/Claimant		Interim Account		Warranty Revenue Account		Creditor/Reimburer	
Debit	Credit	Debit	Credit	Debit	Credit	Debit	Credit
	500 (1)	500 (1)					
500 (2)			500 (2)				
	450 (3)	450 (3)					
			450 (4)	450 (4)	450 (4)	450 (4)	

Precrediting Case without Recall of Difference and with Posting to Interim Account

In this example, the claim processor adopts the difference between the amount requested by the claimant, which is credited to the claimant, and the amount actually paid later by the reimburer. This amount is not recalled. The claim processor would like to see the amounts in an **interim account** and not in the warranty revenue account as long as the processing of the warranty claim has not been completed. Furthermore, the claim processor would also like to have the option of listing the amount differences separately in the warranty revenue account and posting them to a **different CO account assignment**.

1. The claimant forwards a warranty claim of 500 € for a water pump (version from claimant).
2. The claim processor writes a credit memo for 500 € (outgoing version to claimant with posting (1) in Accounting).

Posting (1): the customer account is credited with 500 €, the interim account is debited with 500 €. These 500 € are posted to the default CO account assignment.

3. The claim processor forwards the warranty claim of 500 € to the reimburer (version to reimburer).
4. The reimburer only approves 450 € and receives a debit memo for this amount from the claim processor (version from reimburer with posting (2) in Accounting).

Posting (2): the vendor account is debited with 450 €, the warranty revenue account is credited with 450 €. These 450 € are posted to the default CO account assignment.

5. The interim account is credited with 500 €, the warranty revenue account is debited with 450 € and 50 €. The 50 €, i.e. the difference amount, can be assigned to a different account either manually or automatically.

i Note

Transfer posting from the interim account to the warranty revenue account is controlled via the pricing procedure and the account key (see also; [Pricing](#)).

i Note

The difference amount is determined by using the condition value formula in the pricing procedure for pricing.

Debtor/Claimant		Interim Account		Warranty Revenue Account		Creditor/Reimburer	
Debit	Credit	Debit	Credit	Debit	Credit	Debit	Credit
	500 (1)	500 (1)					
			500 (2)	450 (2)	450 (2)	450 (2)	
				50 (2)			

Grouping of Credit Memos

Purpose

You can use this process if you want to **simplify the posting of credit memos to your customers/claimants**.

In the course of warranty claim processing, one or more credit memos are created for the claimant per warranty claim and then posted to accounting. It does not make sense to send each individual credit memo to the customer/claimant separately; it would seem more sensible to collect the credit memos together and send them all at once at a later date in the form of a **credit memo list**.

Caution

This function is only offered for postings to customer accounts (credit memos to the customer/claimant) and not for postings to vendor accounts (debit memos to the vendor/reimbursing).

Prerequisites

- You have posted credit memos to the customer/claimant in the course of warranty claim processing.
- You have maintained the field **InvoicingListDates** in the sales view of the customer master record for this customer/claimant.

Process Flow

1. Over a specific period of time, you post the credit memos that are created per warranty claim directly to accounting (FI and CO). This has a direct effect on the costs and revenue. However, the customer/claimant is unaware of this.
2. At the end of this period, you create a credit memo list for each customer/claimant (**transaction WTYCL**). All the credit memo amounts for the appropriate customer and period are contained as individual items in this list. The list is a new document with its own reference document number (WL + smallest warranty claim number + version number). This number is inserted in all credit memos when the list is posted.
3. You transfer the credit memo list to the customer/claimant.
4. The open items are automatically cleared using the reference document number (**transaction FB05**).

i Note

You can cancel a credit memo at any time via the warranty claim version, even if the credit memo has already been transferred to the customer/claimant in a credit memo list. The new cancellation document is then included in the next credit memo list that is to be created.

Warranty Claim: Header, Version/Category, Item/Item Type

Definition

A warranty claim is a claim for reimbursement of material, labor and external service costs that are incurred for the purpose of rectifying faults in an object with a valid warranty.

Use

The warranty claim is the central object in [Warranty Claim Processing](#)

Structure

A warranty claim consists of a header and one or more versions of a claim; these versions can belong to different categories and are created manually, by copying or by data transfer via IDoc/EDI from the claimant or reimbursor. Each version has its own data, for example, the specification of the partner, and contains one or more items; each item has a specific item type.

More specifically, this means:

Header

The warranty claim header contains data that is identical for all versions of the claim ([warranty claim type](#) , warranty claim number, object number, reference date etc.).

Version

A version is part of a warranty claim with entitlements to reimbursement and that is directed at or has been made by a specific partner. A version can contain more than one item.

When you enter a warranty claim, exactly one version is created; generally speaking this version is assigned to the category **Versions from Claimant** (see below). During the further claim processing procedure, more versions are created manually or automatically in different categories and sent to the appropriate business partner. There can be more than one version per category. The most current version in a category is always active. More than one version can only be active if you are using [Warranty Claim Processing with Claim Split](#)

Different versions of a warranty claim can differ in the items, the organizational data, the prices, the decision code and so on.

A category is a subdivision within a warranty claim that defines a specific part process. There are four different categories:

Versions from Claimant : category for versions sent by the claimant

Versions to Reimbursor : category for versions that have already been run through specific VSR checks and have been forwarded to the reimbursor

Versions from Reimbursor: category for versions that have been returned by the reimbursor and either been approved or rejected by the latter

Versions to Claimant : category for versions that have been returned to the claimant after they have been run through specific VSR checks

In the postcrediting process, the categories are run through in exactly this order. In the precrediting process, the order is as follows:

Version from claimant

Version to claimant

Version to reimbursor

Version from reimbursor

If, as importer or supplier, you enter warranty claims yourself and forward them directly to the reimbursor, you only deal with the following categories: **versions to reimbursor, versions from reimbursor** .

You define the start category, in other words the category with which the process begins, in Customizing and for each [warranty claim type](#) . The sequence of the further categories depends on the programming for the [action controls](#) .

Item

An item is a detailed description of entitlements in a warranty claim version. Each item has a specific item type that serves as a classification for the item.

SAP delivers the following controlling item types:

MAT (Material): replacement part with material master record

SUBL (Sublet): external service These are invoices for services performed by a third party, for example, hotel expenses, travel expenses and so on, which have been incurred in the course of the repairs. The value of items with this item type can be entered explicitly and is not usually determined via pricing.

FR (Flat Rate): labor value, service

EXP (Exploding List): list of items that the claimant can call, for reasons of ease, with a single key, for example, the items that usually belong to an inspection (mixture of labor values and materials). The subitems can be created using action A080 **Explode Item**.

You can use an installed base (IBase), a task list or routing, a bill of services or a bill of materials as list. A template installed base of type WY **Warranty** is read in the standard system. You can link in other master data using BAdI WTY_ITEM_GENERATE. An example implementation for the material BOM is already included the BAdI for this purpose.

You can also enter items of type **TEXT (TXT)** in the warranty claim.



You can define customer-specific item types in Customizing under **Warranty Claim → Warranty Claim Items → Define Item Types** on the basis of such a controlling item type.

Customer-specific item types are useful if you want to do the following:

choose your own keys and own descriptions for the item types

or

link different catalogs to different item types for the same controlling item type via the BAdIs WTY_CREATE_COPY/WTY_F4_ITMNO

or

exclude certain item types from specific claim types.



You can group the customer-specific item types together to form item type groups (Customizing for **Warranty Claim Processing** under **Warranty Claim → Warranty Claim Items → Define Item Type Groups**) and assign such an item type group to each warranty claim type. You can thus exclude item types from specific claim types or restrict to specific claim types.

Processing Warranty Claims

The goal of warranty claim processing is to automate processing as far as possible and let it run in the background. Nevertheless, manual processing and the appropriate tools for working in dialog mode are also necessary:

- [Standard layout](#) : overview of the sequence of screen areas, explanation of the icons used, guidelines on using customer-specific fields and customer-specific screens
- [Manuel creation](#) of warranty claims
- [Searching](#) for warranty claims with the largest possible flexibility when using selection criteria
- [Archiving](#) of warranty claims that no longer have to be processed
- [Mass processing](#) of warranty claims for the automation of processing

Warranty Claim: Standard Layout

Definition

The layout with the SAP key contained in the standard system delivery is described below. This layout and other layouts are defined in Customizing for **Warranty Claim Processing** under **Layout → Define Screen Layouts** . Here you define which screens (screen groups) should be displayed on which tab pages and which sequence the tab pages should have. The standard layout only contains some of the [available screen groups](#) .

The screen layouts are not user-specific, but specific to the [warranty type](#) .



For linking customer-specific fields into the screen layouts, see also: [Creating Customer-Specific Fields](#) , [Including Customer-Specific Screens in Header Area](#) and [Including Customer-Specific Screens on Tab Pages](#) .



In addition, you can assign a user profile with further user-specific display parameters to every user (transaction WTY_UPROF). The user profile is valid for transaction WTY (warranty claim processing), WTYRCL (recall processing) and WTYAUT (authorization processing). In this user profile you can define:

which of the available tab pages is active when this transaction is called, i.e.: which is displayed in the foreground

Whether the navigation tree is displayed or not when the transaction is called A layout has been defined for each of these cases in the Customizing settings for the warranty claim type: the system then uses this layout when the warranty claim is created If you choose **Extras → Display Navigation Tree** or **Hide Navigation Tree** when you are processing the warranty claim, you not only display or hide the navigation tree, you also branch to another layout.

which URL is called in the right screen area when the transactions are called

whether all the warranty claims for an object are displayed or just the current one


Standard profile SWTY is contained in the standard system. If a user is not assigned to any other profile, a message appears and this standard profile is automatically used. However, the user is not assigned to the standard profile.

Use

The layout refers to the display of the warranty claim in transaction WTY (Warranty Claim Processing).

Structure

The warranty claim display consists of the following areas in the SAP standard system:



Reference area: here you see the [warranty claim type](#) and the warranty claim number.

Navigation area: depending on settings in the user profile, this area contains all the existing claims for an object or just the chosen warranty claim for the object. The data is displayed in a navigation tree. All existing [categories and versions](#) for the claim are always displayed. You can expand or collapse the separate nodes in a warranty claim.

By double-clicking on a version, you can branch from the work area to the version data.

The versions next to which you set the selection indicator are the versions to which the actions refer that you trigger when you choose the function **Actions**.

Key of icons in the navigation tree:

Claim Header , Categories Active Version Inactive Version Manual Processing Accounting Documents Exist Release for Sending

1

In BAdI WTY_DYNPRO_DYNAMIC you can define that claims in the navigation tree are not selected according to the object but according to other criteria (for example: all claims with the same reference number, all claims from the same claimant).

Header area:the header area contains data that is valid for the entire claim, irrespective of which claim version you are currently processing, for example: [object type](#) and object number, reference date, partner placing the claim etc.Furthermore, it contains the function  **Actions, via which you can call and trigger [actions](#)** for chosen versions from an action box.

1

You can hide individual lines in the header area, add a small area to the header area or replace the entire header area by a customer-specific area (see also: [Creating Customer-Specific Fields](#) , [Including Customer-Specific Screens to Header Area](#)).

Work area:in this area you can see the details, grouped thematically on different tab pages, for the claim version that you have chosen by double-clicking on the left in the navigation area. In Customizing for **Warranty Claim Processing** under **Layout → Define Screen Layouts**), you can control how many and which tab pages are displayed , the text that appears on them and how the group boxes are ordered The Customizing settings for the layout of the work area are valid per [warranty type](#) .

1

You can also create tab pages with customer-specific data in the work area (see also: [Including Customer-Specific Screens to Tab Pages](#)).

The work area contains the following tab pages in the SAP standard layout with navigation tree:

Header Detail(screen group 2010): amount totals of last versions in each category, processing data etc.

Version Detail:this tab page helps you to enter claim data quickly. It may suffice just to enter data on this tab page and hide or ignore the other tab pages.

You enter specific information for the [claim version](#) currently being processed in the upper area (screen group 2110), for example, the partner for the version. Furthermore you can use pushbutton functions to call the [messages](#) for the version, the [accounting documents](#) for the version, the [VSR check log](#) for header and version-related checks and the VSR check log for the checks related to the damage/defect. If you choose the F4 value help for the icon **Display Long Text** , a list in alphabetical order appears in which you can tell, by the presence or absence of **X** , for which languages a long text is available. **X** indicates that the language is available.

In the item overview (screen group 2200), you enter the individual [items](#) for the chosen claim version (material, labor values, external service, list), including the measurement value/counter reading for the item. The counter readings that you enter here are version and item-specific, not object-specific. The counter readings are required for the warranty check, in other words for the check that analyses whether there is still a warranty for the object (see also: [Warranty Check](#) and [Master Warranties](#)).

The individual columns correspond to the fields on the tab page **Item Detail** .

You can change the size of display for the item overview.

Prices – Version(screen group 2150) : result of pricing on the version, in other words, the sum of all the items in the version. You can also add additional condition records here, the amount being distributed proportionally across the individual items when you activate the data. Furthermore, you can change manually the prices that are determined.

Item Detail:(screen group S2210) here you can see the fields that are contained as columns on the tab page **Version Detail** in the item overview. This is merely a different way of displaying the same data. Alternatively, you can maintain the item data on both tab pages. The fields **ObjectTyp** (**Object Type**) and **Ext. Obj. No.** help you to track objects. You can trigger a warranty check for the claim on item level.

Furthermore you can see the result of pricing (screen group S2250) for the item that is selected on the tab page **Version Detail** in the item overview. You can call further items using the scroll keys.

Thirdly you see the [VSR check log](#) (screen group S2220) for the item-related checks.

Measurement Data/Notifications:

You enter the measurement values/counter readings (for example: kilometer reading, number of operating hours) for the measurement positions and measuring points relevant to the warranty in the upper area (screen group S2350). The counter readings that you enter here are version-specific, not object-specific. When you save, the appropriate CS measurement documents are created for the counter readings you have entered. The counter readings are required for the warranty check, in other words for the check that analyses whether there is still a warranty for the object (see also: [Warranty Check](#) and [Master Warranties](#)).

i

If you hide this screen (screen group S2350 or S2355) when you define the screen layouts in Customizing, the field **Measurement Reading for Version** is displayed on the tab page **Version Details** (screen group S2110) so that you can at least enter one measurement reading for the version.

i

In addition, you have the screen for the measurement documents (screen group S2300 or S2305) at your disposal when you define screen layouts in Customizing. This screen is not linked into the SAP standard layout. When you link it into a layout, you see all the counter readings that were last entered at a specific time for all the measuring points for an object, in other words, not only the ones relevant to warranty processing. These can be the counter readings from the **Version Details/Item Details** screens, but also the counter readings from earlier independent measurement documents. System date and time are proposed as default settings in the standard system. If you enter a different date or time, you may see different counter readings or none at all.

You can also enter new counter readings here; your new entries then overwrite the existing entries. When you save, the appropriate CS measurement documents are automatically created. The entries are purely object-specific and thus independent of item and version. Changes on this screen do not change the values on the **Version Details** and **Item Details** and on the screens **Measurement Data/Notifications**

Entering object-specific counter readings on this screen is recommended, for example, if the counter readings that were entered in the version are too low and if you do not want to enter a new version with the correct counter readings, but nevertheless want to save the correct counter readings for the object. This is also advisable if you do not wish to have a relationship between measurement document and warranty claim when you create counter readings.

In the lower area of the **Measurement Data/Notifications** tab page (screen S2030) you can create and edit quality notifications, maintenance notifications and service notifications for the object (example: the quality check is triggered directly for a returned part). You can assign exactly one notification to each claim. Prerequisite is that early number assignment has been defined in Customizing for the message type.

Other Version Data: you enter further version-specific data here (screen S2111). You can define default values for some fields, for example for organizational data, in Customizing (IMG activity **Define Warranty Claim Types**). **These values are then set automatically but you can overwrite them if you so wish.**

i

You can implement further customer-specific default values by using BAdI WTY_CREATE_COPY (methods DATA_CHANGE_CREATE and DATA_CHANGE_COPY).

Application toolbar: in this toolbar you can choose the **info.**  **the warning message**  **and the error message**  functions to call the messages for the standard checks, BAdI checks and pricing checks. These messages are independent of the VSR check logs.

Furthermore, you can fill up to seven pushbuttons with frequently used actions in this toolbar and thus make these actions available for fast access. To do this, create button profiles in Customizing for **Warranty Claim Processing** under **Layout → Define Pushbutton Profiles** and assign them to a combination of action control and category.

Available Screen Groups for Screen Layouts

Screen Group	Explanation	Notes
S1502 - S1510	Customer screens for customer exit WTY0002	Screen groups that are reserved for the customer. These groups have already been created but are still empty. See: Including Customer-Specific Screens on Tab Pages
S2010	Header detail: reference object data, amount totals, processing data (with tree)	See: Warranty Claim: Standard Layout
S2015	Header detail: reference object data, amount totals, processing data (without tree)	See: Warranty Claim: Standard Layout Corresponds to S2010, optimized for display without navigation tree
S2020	Header detail: only processing data (with tree)	Part of screen S2010, only processing data
S2021	Header detail: only amount totals (with tree)	Part of screen S2010, only amount totals
S2040	Header detail	Like S2010, obsolete
S2110	Version detail: version data (with tree)	See: Warranty Claim: Standard Layout
S2115	Version detail: version data (with tree)	See: Warranty Claim: Standard Layout Corresponds to S2110, optimized for display without navigation tree
S2200	Version detail: item overview (with tree)	See: Warranty Claim: Standard Layout
S2201	Version detail: item overview (without tree)	See: Warranty Claim: Standard Layout Corresponds to S2200, optimized for display without navigation tree
S2111	Further version data: (with tree)	See: Warranty Claim: Standard Layout
S2112	Further version data: (without tree)	See: Warranty Claim: Standard Layout Corresponds to S2111, optimized for display without navigation tree
S2109	Version detail (with tree) – obsolete	In addition, contains space for displaying VSR check log and pushbutton Actions
S2116	Version detail (without tree) – obsolete	Corresponds to S2109, optimized for display without navigation tree
S2100	Version overview	Empty, obsolete
S2101	Version overview per category	Empty, obsolete
S2150	Prices – version: pricing version	See: Warranty Claim: Standard Layout For display with and without navigation tree

Screen Group	Explanation	Notes
S2025	Version overview: change header conditions	See: Pricing
S2210	Item detail: item data (with tree)	See: Warranty Claim: Standard Layout With icon for expansion
S2215	Item detail: item data (without tree)	See: Warranty Claim: Standard Layout Corresponds to S2210, optimized for display without navigation tree
S2250	Item detail: pricing item (with tree)	See: Warranty Claim: Standard Layout With icon for expansion
S2255	Item detail: pricing item (without tree)	See: Warranty Claim: Standard Layout Corresponds to S2250, optimized for display without navigation tree
S2220	Item detail: VSR check log item (with tree)	See: Warranty Claim: Standard Layout With icon for expansion
S2225	Item detail: VSR check log item (without tree)	See: Warranty Claim: Standard Layout Corresponds to S2220, optimized for display without navigation tree
S2211	Item detail: item data (with tree)	As S2210 but in direct display, without icon for expansion
S2212	Item detail: item data, pricing item VSR check log item	S2210, S2250, S2220 together on one screen, with icons for expansion
S2251	Item detail: pricing item (with tree)	As S2250 but in direct display, without icon for expansion
S2300	Measurement documents/messages: measurement documents for object (with tree)	See: Warranty Claim: Standard Layout
S2305	Measurement documents/messages: measurement documents for object (without tree)	See: Warranty Claim: Standard Layout Corresponds to S2300, optimized for display without navigation tree
S2350	Measurement documents/messages: measurement documents for version (with tree)	See: Warranty Claim: Standard Layout
S2355	Measurement documents/messages: measurement documents for version (without tree)	See: Warranty Claim: Standard Layout Corresponds to S2350, optimized for display without navigation tree
S2030	Measurement documents/messages: quality messages (with tree)	See: Warranty Claim: Standard Layout
S2035	Measurement documents/messages: quality messages (without tree)	See: Warranty Claim: Standard Layout

Screen Group	Explanation	Notes
		Corresponds to S2030, optimized for display without navigation tree
S2310	Measurement documents 2	Obsolete
S2256	Changeable CO account assignments on item level	See: CO Account Assignment
S2257	Changeable CO account assignments on version level	See: CO Account Assignment
S2260	Claim split: split groups (with tree)	See: Processing with Claim Split
S2261	Claim split: split groups (without tree)	See: Processing with Claim Split Corresponds to S2260, optimized for display without navigation tree
S4001	Recalls: version detail	See: Processing with Recalls/Technical Campaigns
S4002	Recalls: item overview	See: Processing with Recalls/Technical Campaigns
S4003	Recalls: object	See: Processing with Recalls/Technical Campaigns
S6100	Warranty objects: serial number/material number	See: Warranty Objects
S6101	Warranty objects: main object plus serial number/material number	See: Warranty Objects
S7910	VSR check log: header and version-related checks	See: VSR Checks
S7915	VSR check log : checks related to the defect code	See: VSR Checks

Creating Customer-Specific Fields

Use

This procedure has been written particularly for technical consultants at the customer site who want to create customer-specific screens with customer-specific fields and include them in the layout of the warranty claim.

Procedure

Include Customer-Specific Fields in Data Tables

- Specify the table you want to enhance:
 - Warranty claim header: table PNWTYH
 - Warranty claim version: table PNWTYV

- Warranty claim item: table PVWTY

2. If you want to enhance table PNWTYH, create an APPEND structure for structure WTY_PNWTYH_CUST in transaction se11. The APPEND structure has to begin with Z.

If you want to enhance table PNWTYV, create an APPEND structure for structure WTY_PNWTYV_CUST.

If you want to enhance table PVWTY, create an APPEND structure for structure WTY_PVWTY_CUST.

3. Enhance the APPEND structure with your own customer-specific fields. The fields must begin with Z.

You may have to create your own data elements and domains for this purpose.

Filling Customer-Specific Fields when Migrating Legacy Data (PNWTYH, PNWTYV, PVWTY)

1. Prepare the data import with BAPIs BAPI_WARRANTYCLAIM_...(see: BAPI documentation).
2. Transfer/map the customer-specific fields within BAdI WTY_BAPI_CREATE (see: BAdI documentation).

Including Customer-Specific Screens in Header Area

Use

This procedure is devoted to technical consultants at the customer's site, who have both ABAP programming knowledge and are also familiar with warranty processing functionality and the customer's business processes.

Procedure

Enhancing Standard Screen in Header Area with Customer-Specific Screen

The screen may be 2 lines without frame and one line with frame (maximum) and appears at the bottom of the standard screen in the header area.

The linking in of this additional screens takes place via customer exit WTY00001.

Call the display of the components for customer exit WTY00001 – subscreen in **Warranty Claim Processing** (header screen) – via transaction SMOD.

You see a list of the function modules used (EXIT_SAPLPVSUIWTY_001 and EXIT_SAPLPVSUIWTY_002) and the subscreens. Subscreens 0100 to 0109 of subscreen container 1500 in program SAPLXWTY are predefined but do not exist yet and are available for use as customer-specific subscreens.

Create a project for WTY00001 (transaction CMOD). All the SAP components you require are copied to this project.

Create a new screen of screen type **Subscreen** (transaction se51) in program SAPLXWTY. Use the Screen Painter to do this. The screen number must be between 0100 and 0109.

Double-click on function module EXIT_SAPLPVSUIWTY_001 in transaction CMOD and then on include ZXWTYU01 to create the screen. Continue in the same way with function module EXIT_SAPLPVSUIWTY_002 / include ZXWTYU02.

The function modules have the following tasks:

EXIT_SAPLPVSUIWTY_001 transports the data from standard processing to the customer-specific function group XWTY of the customer-specific screen in the header area.

EXIT_SAPLPVSUIWTY_002 transports the data from the customer-specific function group XWTY of the customer-specific screen in the header area back to standard processing.

Enhance your screen by adding fields from structure GS_PNWTYH_DYNPRO (transaction se51).

Assign the import parameters to the global variants or structures in include ZXWTYU01 (run through in PBO), for example `GV_MODE = IV_MODE`.

Fill the global structure of customer function group XWTY with data from import structure IS_PNWTYH of function module EXIT_SAPLPVSUIWTY_001.

The TOP include of function group XWTY has preconfigured global variables, structures and tables that you can use:

`gs_pnwt_yh_dynpro` type `wt_y_pnh_dynpro`

`gs_pnwt_yh_dynpro` type `wt_y_pnV_dynpro`

`gs_pvwt_y_dynpro` type `wt_y_pv_dynpro`

`gt_pvwt_y_dynpro` type table of `wt_y_pv_dynpro`

`gv_mode` type `c`



Do not use structure `gs_pnwt_yh` type `pnwt_yh`.

Return the data to the function group in include ZXWTYU02 (run through in PAI).

If changes have been made in the warranty claim:

`EV_ACTIV = 'X'`.

`ES_PNWTYH_DYN = gs_pnwt_yh_dynpro`.

If only customer-specific fields are saved again:

move-corresponding `gs_pnwt_yh_dynpro` to `ES_PNWTYH_CUST`).

Program the PAI and PBO modules.

Activate your project (transaction CMOD).

Enter the new screen in Customizing (Customizing for [Warranty Claim Processing](#) under [Define Warranty Claim Types](#)).



If you have both a customer-specific screen in the header area and a customer-specific screen with header data on tab pages, you have to ensure that the data does not overwrite each other in the customer-specific function group XWTY.

Replacing Standard Screen in Header Area by Customer-Specific Screen

Perform steps 1 to 9 as described above.

Create a new implementation of BAdI WTY_DYNPRO_DYNAMIC, method SET_SCREEN (transaction se19) and enter the following parameters:

CV_HEADER_SCREEN = '1500'.

CV_HEADER_CUSTOMER = '<Number of own screen>'.

Activate the BAdI implementation.

Hiding Standard Screen in Header Area

Create a new implementation of BAdI WTY_DYNPRO_DYNAMIC, method SET_SCREEN (transaction se19) and enter the following parameter:

CV_HEADER_SCREEN = '0049'.

Activate the BAdI implementation.

Hiding Individual Subscreens in Standard Screen in Header Area

Create a new implementation of BAdI WTY_DYNPRO_DYNAMIC, method SET_SCREEN (transaction se19) and enter the following parameters:

CV_HEADER_SCREEN = '1500'.

<Subscreen parameter> = '0049'.

Activate the BAdI implementation.



BAdI WTY_DYNPRO_DYNAMIC is documented in the system.

Including Customer-Specific Screens on Tab Pages

Use

This procedure is devoted to **technical consultants at the customer's site**, who have both ABAP programming knowledge and are also familiar with warranty processing functionality and the customer's business processes.

Procedure

The linking in of the additional screens takes place via customer exit WTY00002.

1. Call the display of the components for customer exit WTY00002 – subscreen in **Warranty Claim Processing** (tab control) – via transaction SMOD.

You see a list of the function modules used (EXIT_SAPLPVSUIWTY_003, EXIT_SAPLPVSUIWTY_004 und EXIT_SAPLPVSUIWTY_005) and the subscreens. Subscreens 1001 to 1020 of subscreen container 1501 in program SAPLXWTY are predefined but do not exist yet and are available for use as customer-specific subscreens.

2. Create a project for WTY00002 (transaction CMOD). All the SAP components you require are copied to this project.

3. Create a new screen of screen type **Subscreen** (transaction se51) in program SAPLXWTY. Use the Screen Painter to do this. The screen number must be between 1001 and 1020.
4. Double-click on function module EXIT_SAPLPVSUIWTY_003 in transaction CMOD and then on include ZXWTYU03 to create the screen. Continue in the same way for function module EXIT_SAPLPVSUIWTY_004 / include ZXWTYU04 and function module EXIT_SAPLPVSUIWTY_005 / include ZXWTYU05.

The function modules have the following tasks:

- EXIT_SAPLPVSUIWTY_003 transports the data from standard processing to the customer-specific function group XWTY of the customer-specific screen.
- EXIT_SAPLPVSUIWTY_004 transports the data from the customer-specific function group XWTY back to standard processing.
- EXIT_SAPLPVSUIWTY_005 assigns the customer-specific screen to the subscreen container. Subscreen containers 1502-1510 are available for customer-specific subscreens; these subscreen containers correspond 1:1 to the screen groups S1502-S1510.

❖ Example

For example, the customer-specific screen 1001 should be assigned to subscreen container 1502 and thus screen group S1502. The program code would be:

```
IF sy-dynnr= '1502'.
```

```
EV_DYNNR = '1001'. ENDIF.
```

This functionality allows you to assign different customer-specific screens to the same screen group and use, via a suitable statement in the coding, to use it, for example, for different claim types or different warranty object types.

5. Enhance your screen by adding fields from structures GS_PNWTYH_DYNPRO (header data) and GS_PNWTYV_DYNPRO (version data) or from table GT_PVWTY_DYNPRO (item data) – transaction se51.
6. Assign the import parameters to the global variants or structures in include ZXWTYU03 (run through in PBO).
 - GV_MODE = IV_MODE.
 - Move-corresponding :


```
is_pnwtyh TO gs_pnwtyh_dynpro,
```

```
is_pnwtyh TO gs_pnwtyv_dynpro.
```
 - gt_pwty_dynpro[] = it_pwty [].
7. Return the data to the function group in include ZXWTYU04 (run through in PAI).

If changes have been made in the warranty claim:

- EV_ACTIV = 'X'
- Move-corresponding:


```
gs_pnwtyh_dynpro TO es_pnwtyh,
```

```
gs_pnwtyv_dynpro TO es_pnwtyv.
```
- et_pwty[] = gt_pwty_dynpro[].
- If you have changed structures, you have to set the change flag:

Header data:

ES_PNWTYH-CHANGE_FLAG = 'C'.

Version data:

ES_PNWTYV-CHANGE_FLAG = 'C'.

Item data:

ET_PVWTY-CHANGE_FLAG = 'N'. (or 'C' or 'D') N stands for new, C for changed and D for deleted.

8. Program the PAI and PBO modules.

9. Enter the new screen group in Customizing for [Warranty Claim Processing](#) under [Layout](#) > [Define Screen Layouts](#).

10. Activate your project (transaction CMOD).

Caution

If you have both a customer-specific screen in the header area and a customer-specific screen with header data on tab pages, you have to ensure that the data does not overwrite each other in the customer-specific function group XWTY.

Create Warranty Claim Manually

Use

You use this procedure if the [warranty claims](#) in your system are not created automatically using the Web interface or via IDoc/EDI and you have to enter them **manually**.

Prerequisites

For prerequisites, see: [Processing With Postcrediting/Precrediting](#)

Procedure

1. Enter the transaction code **WTY**.

You reach the initial screen for Warranty Claim Processing.

2. Choose a [warranty claim type](#) and then choose  **Create**.

The warranty claim type controls further processing and defines the screen layout and default values for the organizational data.

You reach the detail screen for Warranty Claim Processing. The [Warranty Claim Display](#) depends on the screen layout and the user profile. If the navigation tree is switched on, you can see the warranty claim number and type in the reference area, underneath it the start category (generally **Versions from Claimant**) and underneath that the number of the version that you are about to create. You can see the details for this version in the work area.

3. In the header area, choose the [object type and the object number](#) to which the warranty claim refers.

4. Choose the claimant as **Partner** in the header area and in the version details the partner that is displayed in the category, in this case the claimant.

The entry of the [Partner](#) in the version is necessary so that pricing can function properly.

5. Make the following entries for each item on the tab page **Version Detail** in the item overview:

Defect Code, **Item Type** (material, labor value, external service, list)

Key ([Labor Value / External Service Catalog](#)), [Material](#) (only for item type **Material**)

Quantity (only for item type **Material**), **Unit of Measure**

and confirm your entries with  **Enter** .

The values in the fields **Calculation Type** and **Condition Type** and the descriptions for the fields **Defect Code** , **Key** and **Material** are proposed automatically. [Pricing](#) is performed automatically.

6. Enter the warranty measurement readings for the version on the tab page **Measurement Data/Notifications** .

7. Choose  **Save**.

Result

You have created the first version of a warranty claim. You can now start specific [actions](#) for the warranty claim processing by choosing  **Actions**.

Find Warranty Claim

Use

You use this procedure if you want to find and process a specific warranty claim, the number of which you no longer have in mind.

i Note

You can also use transaction code **WTYSE** to search for warranty claims. The disadvantage of this search function is that you have to enter a number range interval, in other words you have to know in which number range interval the numbers of the claim you are searching for are. Furthermore, the selection criteria are defined and can only be changed by using BAdI WTY_SELECTION_LIST. The advantage is that you can branch directly to warranty claim processing by clicking on the claim number in the hit list. You can also return to the hit list from the processing screen.

Procedure

1. Enter the transaction code **WTY**.

You reach the initial screen for Warranty Claim Processing.

2. Call the F4 help function on the field **Claim** .

You access a dynamic search help for the warranty claim. A selection of fields with interval restrictions is displayed. When the search help is called for the first time, only the header fields of the warranty claim are displayed.

3. Choose **New field selection** .

All the header, item and version fields that can be selected for the warranty claim are displayed in a tree in the left-hand area of the search help. The fields shown in the right-hand area are displayed in color.

4. Select the fields that you want to use to search for warranty claims (multiple selection with Control, block selection with Shift) and choose  **Adopt selected items**.

The selected fields are copied to the right-hand area of the search help and are available for selection.

i Note

The field selection is user-specific and remains even when you exit the transaction.

5. Enter the single values or the intervals according to which you want to select and choose  **Execute**.

i Note

The search is quickest if you select using only header fields.

A hit list is displayed, from which you can choose the warranty claim you require. You cannot, however, return to the hit list.

Archiving

Use

You can **archive** completed and paid warranty claims (that you only require for reporting and displaying history) **in the background** and thus reduce the load on the database. In this way you can improve performance when searching for and processing current claims.

SAP makes no particular recommendations as to when warranty claims should be archived since warranty claim processing can be used very flexibly and therefore the business requirements can be very different in this respect.

Integration

SAP Standard Archiving serves as the basis for archiving warranty claims.

You can find further information in the standard documentation under [Introduction to Data Archiving \(CA-ARC\)](#).

Prerequisites

The warranty claims have been defined as relevant to archiving.

i Note

You can only set the archiving indicator automatically in [mass processing](#) via action TAR1. You can remove it again via action TAR2. Neither of these actions can be seen in the action box, can therefore not be triggered manually. Warranty claims that have been defined for archiving cannot be changed. They can only be displayed.

Features

- **Transaction WTY_SARA** is used to write archiving data. This transaction corresponds to the standard transaction SARA. The archiving object is WTY_CLAIM. There is only a limited technical display for reading the archiving data in this transaction. The application-specific **transaction WTY_ARCHIV** offers a better display of the archived warranty claims.
- The system checks the following **authorization objects**: C_WTY_OBJ and C_WTY_STAT.
- The following data is archived:

Header/version/item data

Long texts

Recall objects

Recall history

Pricing data

Messages

Change documents

Relationships to measurement documents

Customer fields are automatically archived as well. The documents associated with the warranty claim (credit memo/debit memo, measurement documents, sales orders etc.) and warranty object master data (installation, equipment etc.) are not archived.

- Each archiving run is **logged** by the system.
- You can also execute archiving in **test mode** .

Caution

Archived warranty claims cannot be reloaded/restored.

Activities

- Choose transaction code **WTY_SARA** in order to archive warranty claims. Choose **WTY_CLAIM Warranty Claims** as object name in the initial screen. You can select according to claim number, claim type and plant.
- Enter transaction code **WTY_ARCHIV** in order to display warranty claims. You can select according to claim number or object. If you select according to claim number, you can only display this one claim. If you select according to object, you can see all the claims for the object at the same time.

In the upper part of the screen you only see the header data for the archived claims. In the middle of the screen you see the version data for the claims. It is best to sort the data according to claim number and claim version. In the lower part of the screen you see the item data for the claims. It is best to sort the data according to claim number, version and item.

You can display the long texts for the header, version and item with  . By choosing  **Recall Objects** in the header data screen (upper screen) you can see the list of recall objects. By choosing  **Change Documents** in the header data screen (upper screen) you can see the change documents that have been archived as well. By choosing  **Pricing Conditions** in the item data screen (lower screen) you can see the price determination screen on item level.

ILM-Based Information for the Archiving Objects

You can use the archiving object WTY_CLAIM with the WTY_CLAIM ILM object as part of SAP Information Lifecycle Management. In order to do so, you must activate the associated business function Information Lifecycle Management (ILM) (transaction SFW5). The system then also displays the ILM Actions frame. You can use these actions to archive documents with the retention periods defined in the Information Retention Manager. You can also make snapshots (copies) of data or delete data that fulfills the prerequisites.

- For more information about the Relevance business functions for SAP ILM, see Activating SAP ILM.
- For more information about ILM Enhancements in data archiving, see ILM-Specific Enhancements to Archive Administration

The following fields for WTY_CLAIM defined in the ILM policy and are visible when processing ILM policies (transaction IRMPOL):

- **Available Time Bases**
 - Last Changed On (LAST_CHANGE_DATE)
- **Available Condition Fields**
 - Claim type (CLMTYP)

- Plant (WERKS)

- **Available Policy Categories**

- RTP: Retention Rules

For more information, see SAP Information Lifecycle Management.

Mass Processing

Use

You use mass processing for warranty claims for the following:

- to standardize and **automate** general warranty claim **processing** With this function, mass processing replaces or enhances the report used until present (report RWTY0001). Mass processing jobs are then started in the background and run automatically without the user having to do anything (see: [Processing with Postcrediting/Precrediting](#)).
- to execute certain **operations** with **more than one warranty claim at the same time** , for example, change the decision code, change the defect code, forward claims to manual processing, reduce amounts for specific defect materials by a specific percentage, adopt changes to master data or Customizing settings etc.
- to execute **actions** that should not be triggered manually and are therefore **hidden** in the action box, for example, actions for setting and/or removing the [Archiving indicator](#) .

Caution

Before you work with mass processing, you should read the [security measures](#) .

Features

There are **two transactions** at your disposal:

- **WTYMP_A Define Mass Processing Jobs:** this transaction has been designed for **system administrators** or members of the project team with special authorizations. Here you can define, in the **development system** and in accordance with the end user requirements, which warranty claims should be processed, which [operations](#) with which parameters with these warranty claims should be executed and how any error that occur should be handled. You can link in any amount of operations.

Furthermore, you define variants with predefined parameter values for the job execution. Finally, you ensure that mass processing jobs and variants are transported to the test system and/or productive system.

The Job Wizard supports you in the definition of the mass processing job. It guides you through the individual steps.

- **WTYMP Mass Processing Warranty Claim:** this transaction has been designed for the **end user** , i.e. the warranty claim processor or the manager who is responsible for the claims. Here you execute, in the **productive system** , the mass processing jobs that have been defined in transaction WTYMP_A and you use the predefined variants. This transaction supports the case when mass processing jobs do not run in the background but require the user to make entries and are therefore started interactively.

Activities

See : [Defining and Executing Mass Processing Jobs](#)

Mass Processing: Security Measures

Use

Mass processing is a critical function during which a large amount of sensitive data is changed **irrevocably**. You should therefore ensure the following:

- the mass processing jobs have to be tested sufficiently before you make them available to the end user
- un authorized users have to be excluded from the execution of mass processing jobs
- Data entries when executing the mass processing jobs that lead to undesired results have to be made impossible

Prerequisites

You are the system administrator and have authorization for transaction WTYMP_A.

Features

- Transaction WTYMP_A contains a **transport connection** . You can therefore define the mass processing jobs and the variants for them in the development system, test them in the test system and then make them available to the end user in the productive system.
- Mass processing jobs can be executed in **simulation mode** . All the changes to the warranty claims are made but not saved.
- You can schedule the mass processing jobs for **background processing** . They then run automatically without the user having to do anything.
- There are two different transactions for the definition of mass processing jobs and the interactive execution of these jobs (see: [Mass Processing](#)). You can therefore control the access to these transactions by assigning **different authorizations** .
- When defining mass processing jobs (see: [Defining and Executing Mass Processing Jobs](#)) you can define an **authorization group** to which you want to restrict the execution of the jobs. Technically-speaking, the mass processing transaction is a report; you can therefore work just as well with authorizations and authorization groups, as you are accustomed to with reports.
- When defining variants you can **fill specific fields with default values** using the standard functionality and also protect these fields from being overwritten or hide them by using the appropriate functions. You can also define fields as **selection variables** . This means that you can, for example, fill the date fields with the current data minus a specific number of days, or enter the name of the user who is currently logged on in the user fields.
- Furthermore, you can define that the job can **only be executed with a variant** in the first screen of the Job Wizard when you define mass processing jobs (see: [Defining and Executing Mass Processing Jobs](#)). The end users can then only execute the job with this variant and, if the variant has been defined correctly, only fill those fields for which they are themselves responsible.

Mass Processing: Operations

Use

Defining and executing operations is a central part of [mass processing](#) .

Prerequisites

You are defining a mass processing job in transaction WTYMP_A and want to choose an operation (see: [Defining and Executing Mass Processing Jobs](#)).

Features

Possible Operations

- **Change Field Values (Substitution)**
 - Only the fields from the header, version and item of the warranty claim are available, for which substitutions are also allowed in the [VSR checks](#) .
 - The fields that you choose here are displayed later in the selection screen when you execute the job. The end user can enter new field values there.
 - It makes sense to define fields that you choose here as required/obligatory. The user must then make entries in these fields and cannot leave them empty. Empty fields would have no meaning for a substitution. This is certainly not desired in the majority of cases.
- **Execute Action**
 - You can choose all the [actions](#) that have been defined in Customizing for Warranty Claim Processing. You can choose exactly one action per operation.
 - You have to choose an action that requires no reaction on behalf of the user, that is contained in [action control](#) and that is allowed for the processing status that the claim has when the job is executed. If this is not the case, the claim is ignored when the job is executed.
- **Pricing Item, Pricing Header**
 - The [condition types](#) that you choose here are displayed later in the selection screen when you execute the job. The end user can enter new values, that is amounts, there.
 - As soon as you choose one of the two operations for pricing, the field **Condition Currency** automatically appears when you execute the mass processing job. If the user makes no entry in this field, the currency of the version that has just been processed is used. Otherwise the currency that has been entered here as **condition currency** is taken for all the condition values that are added or changed by the job.
 - Here it also makes sense to define fields that you choose as required/obligatory (as when changing the field values).
 - You can choose all the **condition types** that have been defined in Customizing for Warranty Claim Processing. If the condition type is not contained in the pricing procedure for the claim, the claim is ignored when the job is executed.
 - You can also choose **standard condition types** , i.e.: the condition types that have been defined in Customizing for [Warranty Claim Processing](#) under [General Settings](#) . If the given standard condition type has not been defined in Customizing or is not contained in the pricing procedure for the claim, the claim is ignored when the job is executed.
- **Check Message Log, Check VSR Check Log**

All the **existing messages** from the message log or VSR check log are checked. On the basis of these checks you can decide whether the job processing or claim processing should be continued.
- **Call Customer Exit**

Prerequisites and Checks

- You can enter prerequisites and checks for all operations for changing values (change field values, execute action, pricing). As **prerequisite** , define that a claim should only be processed if specific field values or specific messages exist in the message log or in the VSR check log. As **check** , define that a claim should be skipped or the job cancelled if specific messages occur in the message log or on the VSR check log after the operation has been executed.

❖ Example

Prerequisite: claims that contain items of item type **EXP** (exploding list); operation: info. text on version level should read: contains exploding list. Execution: the system searches for all the claims that contain at least one exploding list on item level and copies the new info. text on version level for the affected versions of these claims.

❖ Example

Prerequisite: claims that contain a version from claimant; operation: info. text on item level should read: item in version to claimant. Execution: the system searches for all the claims that contain at least one version to claimant and copies the new info. text on item level for the affected items of these claims.

- You can make several entries one below the other when you define **prerequisites for the message log or for the VSR check log**. The OR logic then applies, i.e. as soon as the system finds one of the given messages, the prerequisite is regarded as fulfilled.

If you do not make any entries in the fields **Work Area** , **Message Type** and **Message** , this means that all entries are possible.

- After having executed the operation, you can make several entries one below the other when you define **checks for the message log or for the VSR check log**.

Only the field **Decision** is a required field. **Possible entries in this field are 1 (skip claim) and 2 (cancel job)**. If there is at least one entry of **2** for more then one entry, the job is cancelled. If there is no entry with decision **2** , but more than one entry with decision **1** , then the last entry in the list is logged with decision **1** .

If you do not make any entries in the fields **Work Area** , **Message Type** and **Message** , this means that all entries are possible.

In the **standard check** that you can activate in the global job parameters, there are only the entries for message type (value **E**) and decision (value **1**). This means that the claim should generally be skipped when error messages occur.

- If you include prerequisites or checks for the VSR check log, only the VSR check logs for this versions that fulfill the prerequisites set by the field values. All the existing VSR messages on version, defect code and item level are then evaluated for these versions.

Defining and Executing Mass Processing Jobs

Define Mass Processing Job (System Administrators, Development System)

1. Choose **transaction WTYMP_A** .

A list of the existing mass processing jobs is displayed.

2. Choose  **Create**.

The first screen of the Job Wizard appears.

3. Define the **global job parameters** (job ID, description etc.)
 - If required, define an **authorization group** (see: [Mass Processing: Security Measures](#)).
 - Specify that the mass processing job may only be executed with a **variant** (see: [Mass Processing: Security Measures](#)).
 - Enter a customer-specific class (**customer exit**) if you want to work with customer-specific job parameters.

- o If required, define that the message log is checked automatically every time the field values are changed when the mass processing job is executed. The **standard check** is defined in such a way that a claim is skipped as soon as an error message occurs (message of type E).

This standard check cannot have an effect in retrospect on operations already created. It only applies to new operations.

The standard check is activated in the default settings.

- o If required, specify that when the job is executed the individual steps or operations in the job are not displayed one under the other but on individual tab pages. This is especially useful if a job contains several operations.
- o Specify which additional parameters you want to load to the memory before the claim is processed. Set the appropriate indicator for copying the criteria (**Copy**) next to the desired parameters.

Choose  **Continue**.

The next screen of the Job Wizard appears.

4. Specify according to which **selection criteria** you want to search for warranty claims. Set the appropriate indicator for copying the criteria (**Copy**) next to the desired fields. All the fields from the claim header, version and item are at your disposal. If the field is to be a required field when the mass processing job is executed, set the appropriate indicator for defining it as such (**Required**).

Choose  **Continue**.

The next screen of the Job Wizard appears.

5. If required, define **customer-specific job parameters** by entering a customer-specific DDIC structure and choosing fields from it. These fields are then made available to the warranty claim processor later for entering data when the mass processing job is executed. The entries are then returned to the customer-specific class (customer exit) that you have entered in the first screen of the Job Wizard and processed there (validates, used for calculations etc.).

Choose  **Continue**.

The next screen of the Job Wizard appears.

6. Choose the desired **operation** (change field values, execute action, pricing, check log, execute customer exit). Choose  **Continue**.

A screen appears with different pushbutton functions for the desired operation.

By choosing the appropriate function, specify under which **prerequisites** the operation should be executed, exactly which **operation** should be executed and what the final **checks** should be like. Choose  **Continue**.

i Note

If you have activated the standard check in the global job parameters, this check has already been entered when you choose the function for checking the message log. Instead of the icon  , the icon  is displayed on the pushbutton screen.

7. Repeat the last step for all **further transactions** that are to be executed with the selected warranty claims. Choose  **Generate** after the last operation. Enter the development class/package and a transport request.

The new mass processing job is copied to the list of existing mass processing jobs.

8. Create a **variant** for the new mass processing job. To do this, select the job and choose  **Variant** . Transport the variant with  **Variant**.

You can also define in the variant that the mass processing job should be executed in simulation mode.

⚠ Caution

If you change a mass processing job in retrospect, it may be that your variants are no longer valid.

General Notes for Defining Mass Processing Jobs

- If you have defined prerequisites or checks for operations, the icon  on the appropriate screen is replaced by icon . You see immediately for which screens entries already exist.
- You can change the **descriptions of all the steps** in the Job Wizard except the first one ([Global Job Parameters](#)).
- You can enter a **step ID** for every operation. You only need this step ID if you want to call a customer exit as operation. The step ID has to be unique within the job.
- You can **change** mass processing jobs that have already been saved **in retrospect** . However, you cannot change the sequence of the operations. If you desire a different sequence, you have to delete the operations and create them again in the correct sequence.

Execute Mass Processing Job (End User, Productive System)

1. Choose **transaction WTYMP** .

A list of the existing mass processing jobs is displayed.

2. Select the desired job and choose  **Execute with Variant** .

3. Choose the desired variant.

4. If necessary, enter the required parameter values and choose  **Execute**.

The mass processing job is executed and the appropriate log is displayed.

This log is saved and can be used later for checking purposes.

5. Check the log.

The fields **Claim** , **Category** , **Version** and **Item** are at your disposal in the log as context for the error analysis.

You can also call the log with the standard transactions SLG1 (display log) and SLG2 (delete log). Then enter: **Object MP** , **Subobject WTYMP** , **External Identification (External ID)** : the job ID of your mass processing job.

6. Start the job again if a message informs you that the processing was terminated. Decide whether you want to process all claims again or just the remaining ones.

Caution

In order to avoid data inconsistencies, enter in both these cases the same parameter values as you did when you executed the job for the first time.

Mass processing: Customer exits

Use

You can specify your own customer class in the mass processing job in order to support customer exits.

Prerequisites

- Your class must implement the interface IF_EX_WTY_MASS_PROCESSING

- This class must already exist when you create the mass processing job

Procedure

1. Create the global class that implements interface IF_EX_WTY_MASS_PROCESSING.
2. Optional: define data elements for the parameters of the mass processing job.
3. Optional: create an ABAP Dictionary structure that contains fields of the type defined in step 2, or use data elements that already exist.
4. Define a mass processing job.
 - a. On the **Global Job Parameters** screen of the Job Wizard, enter the name of the class in the field **Customer-Spec. Class**.
 - b. On the **Job Parameters** screen of the Job Wizard, define your own parameters.
 - c. Define a selection screen and at least one standard operation.
 - d. Optional: add at least one other operation (call customer exit).
5. Add an instance variable of the type defined in step 3 to your class.
6. Implement the method INITIALIZATION. Enter coding that adds the parameter IS_PARAMETERS to the instance variable from step 5. Optional: add coding that modifies the parameter CT_RANGES.
7. Implement other methods of the interface. Add logic that conditionally returns SKIP, SKIP_OPERATION or ABORT. Use the method CLAIM_READ_BUFFER to get claim data.
8. In the implemented methods, write coding that adds [messages to the message log](#).
9. Implement VALIDATE_FIELD_VALUE and VALIDATE_CONDITION_VALUE with checks on field values and condition values. If the checks fail, use the command MESSAGE ... RAISING VALIDATION_FAILED.
10. Implement your own logic in the method CUSTOMER_EXIT_OPERATION.
11. Optional: set breakpoints in the implemented methods.
12. Execute the mass processing job.

i Note

Interface IF_EX_WTY_MASS_PROCESSING is documented in the system.

Mass Processing: Logging Messages

Use

You can add your own messages to the mass processing log.

Prerequisites

You are using your own methods for the interface IF_EX_WTY_MASS_PROCESSING.

Procedure

1. Add interface IF_MP_LOGGED_OBJECT to your class.
2. Declare local variable lv_dummy of type C(1) within the method.
3. Add the command MESSAGE INTO lv_dummy
4. Add the command RAISE EVENT if_mp_logged_object~log_message.

❖ Example

DATA lv_dummy.

MESSAGE E10(WTYMP) INTO lv_dummy.

RAISE EVENT if_mp_logged_object~log_message.

Result

You can use the transaction code **WTYMP** and then the function [Display Logs](#) to display your logged messages.

Evaluation of Warranty Claim Data

You have the following two procedures at your disposal for evaluating warranty claim data:

- **Reporting using SAP Query with InfoSets** ([Online Reporting](#))

You configure and create these reports (ad-hoc reports) in the SAP Discrete Industries System. The scope of the function is limited and you cannot save the reports that you create.

- **Reporting in SAP Business Information Warehouse** ([BW Reporting](#))

You configure and create these reports in SAP Business Warehouse. Here you have unlimited opportunities for combining the data to be evaluated, saving data, aggregating data and for the graphical display of the report results.

Online Reporting

Use

As the person responsible or as the manager for warranty claim processing in the SAP Discrete Industries System you can use online reporting to create **ad hoc reports for warranty claim processing** . Examples for possible reports are:

- all claims for which the sum that the claimant makes lies within specific amount restrictions
- all claims with parts that have to be returned
- all claims for a specific vehicle model
- all claims of a specific claimant
- all claims in which a specific replacement part is contained

Integration

The basic reports via SAP Query with InfoSets form the basis for online reporting (BC-SRV-QUE).

You can find further information in the standard documentation [under InfoSet Query](#).

Features

You can use online reporting both to define basic reports, i.e.: define and save **selection criteria** and **report layouts**, and to **create the reports yourself**. You cannot, however, save the results in the system.

You can evaluate data that is created in warranty processing itself and **external data** that warranty processing uses, for example data on the customer, vendor, material, warranty object and so on. However, not all the fields of these object masters are available, only the most important ones. All this data can be used as selection criteria and as output fields in the report.

The SAP standard system delivery contains user group **WTY_OR** for warranty claim processing. The **InfoSet WTY** and the logical database WTY is assigned to this user group. All the available warranty claim processing data is contained in the InfoSet WTY.

Activities

- Choose **transaction SQ01** for creating, changing, displaying and executing queries for a specific user group.
- Choose **transaction SQ02** for creating, changing and displaying InfoSets and for assigning InfoSets to user groups.
- Choose **transaction SQ03** for creating, changing and displaying user groups and for assigning InfoSets and users to user groups.
- Choose **transaction WTYOR** to execute queries. Set the **Global Area** indicator, enter **WTY_OR** as user group, enter one of the existing queries and, if required, a variant and then choose  to execute. You can see which queries already exist in transaction SQ01.

BW Reporting

Use

You can evaluate data from Warranty Claim Processing in the **SAP Business Information Warehouse (SAP BW)**. Here you have the **entire BW functionality** at your disposal in terms of combining data to be evaluated, saving data, aggregating data and the graphical display of report results.

You can find further information in the documentation for SAP Business Information Warehouse.

Features

The queries delivered by SAP list the following:

- Top N claimant
- Top N labor values
- Total number of recalled objects
- Frequency with which a warranty claim is made for damaged material

The Business Content objects can be found in the new information area for warranty claim processing.

The InfoProvider OAU_WTY contains the following:

- InfoCube Completed Claims OAU_WTYG1

- Master Data
 - Recall Number OAU_RCL
 - Vehicle GUID OAU_WVHGUID
- ODS Objects
 - Warranty Claim Header OAU_WTYH
 - Warranty Claim Version OAU_WTYV
 - Warranty Claim Items OAU_WTYI
 - Warranty Counter with its Limits OAU_WTYM
 - Warranty Version and Item Measurement Documents OAU_WTYMP

Activities

Check the delivered queries and, if required, assemble your own.

Master Data

You require the following master data in [Warranty Claim Processing](#) :

- [Materials](#) for the warranty claim items
- [Warranty objects](#) (equipment, functional location, installed base, serial number, also vehicle)
- [Partners](#) (claimant/customer, reimbursor/vendor)
- [Partner profiles](#) for sending IDocs
- [Master warranties](#) for the warranty check
- [Reference objects](#) for entering version-specific measurement readings in the warranty claim
- Condition records for [Output and Message Determination](#) , [Pricing](#) , and [Account Determination](#)
- [Catalogs](#) for defect codes, labor values and external services

Warranty Objects

Use

Warranty objects are the objects for which the warranty is valid and for which you can enter warranty claims. The following technical objects in the SAP system can be warranty objects in warranty processing: **equipment, functional locations, installed bases and material numbers with serial number** . In addition, there is the warranty object **vehicle** for SAP Discrete Industries.

Integration

- Equipment: CS-BD/PM-EQM-EQ
- Functional locations: CS-BD/PM-EQM-FL
- Installed bases: CS-IB-IN/

- Material number with serial number: LO-MD-MM, LO-MD-SN
- Vehicles: IS-A-VMS (only with SAP Discrete Industries; not with SAP S/4HANA Enterprise)

i Note

You can use BAdIs WTY_READ_SUPPL_DATA and WTY_F4_RELOB to link in other objects according to customer-specific objects.

Features

- [Equipment](#)

An equipment item is an **individual object that is maintained as an autonomous unit**, for example a production resource, means of transport, testing and measuring equipment, production resource or tool, a building or a PC. Equipment can be built into or out of functional locations. Each equipment item is maintained in the system with individual data (for example: construction year, end of warranty or location).

- [Functional Location](#)

A functional location is an **organizational unit in Logistics** that structures the maintenance objects of a company according to functional, process-oriented or spatial criteria, for example a pumping station, a sewage or purification plant or a hall. A functional location represents the place at which a maintenance task is performed.

- [Installed Base](#)

An installed base is a **multi-level component structure** for managing products at the customer site and for managing products that are used internally. The installed base describes the structure of these products and their components. The following master records can be part of a component: material, equipment, functional location, installed base and document.

- Material Number with Serial Number

The material master record contains all the data for describing and managing a material, but does not offer any options for differentiating between individual items. The combination of material number and serial number defines **material individual items** and renders them distinguishable.

If you want to work with material numbers/serial numbers, you have to link the screen groups S6100 (serial number/material number) and S6101 (main object plus serial number/material number) to the screen layout of your warranty claim type under ► [Layout](#) ► [Define Screen Layouts](#). ► You can find further information in the system documentation for BAdI WTY_DYNPRO_DYNAMIC, method SET_SCREEN.

- [Vehicle](#) (only with SAP Discrete Industries; not with SAP S/4HANA Enterprise)

A vehicle is produced when you create a vehicle for a vehicle model in the [Vehicle Management System \(VMS\)](#). It is, therefore, an **instance of a vehicle model**, in other words, an individual object. A configuration is always created for a vehicle, the characteristics in the configuration may have been assigned all possible values, only some values or no values at all. A vehicle is identified uniquely by its vehicle numbers.

You can enter warranty conditions (master warranty, start of the warranty period) and measurement positions/measuring points for all objects in the object master record and thus fulfill the prerequisites for the warranty check, in other words the check that tests whether there is still a valid warranty for the object (see also: [Warranty Check](#) and [Master Warranties](#)).

⚠ Caution

Installed bases that you use as warranty objects should be of type WY. Only then can you enter warranty conditions (master warranty, start of warranty period) and measurement positions/measuring points in the master record.

Activities

1. Create objects master records for these objects in the SAP system:
 - Equipment: **transactions IE01, IE02, IE03**
 - Functional location: **transactions IL01, IL02, IL03**
 - Installed base: **transactions IB51, IB52, IB53**
 - Material number: **transactions MM01, MM02, MM03**; serial number: **transactions IQ01, IQ02, IQ03**
 - Vehicle: **transaction VELO**
2. Reference the objects in the warranty claim via object type and object number (**transaction WTY**).

Materials

Use

If you want **pricing** to take place **automatically** and the items to be posted to FI and CO, **material master records** have to exist for all claim items in Warranty Claim Processing.

You create material master records in Warranty Processing in basically the same way as in the standard applications. The following paragraphs therefore only describe the settings that are specific to Warranty Claim Processing.

Integration

You use the material master record in LO-MD-MM to create material master records.

You can find further information in the standard documentation under [Material Master Record](#) .

Features

- You have to create a material master record for each item in a warranty claim because the entry of a material is required for pricing for all the items in the claim.

For **items of item type Labor value** or **External service** , create a service material per item type, for example a service material **Sublet** for all items of item type **External service** and a service material **Flat rate** for all items of item type **Labor value** . You can then determine this service material via a catalog entry or enter it manually.

- You define the **parts that have to be returned** in the material master record by selecting the fields **Product Attribute 9** and/or **Product Attribute 10** on the tab page **Sales Organization 2** . **Product Attribute 9** indicates the duty of the claimant to return the parts to the claim processor, **Product Attribute 10** indicates the duty of the processor to the reimbursing.
- The entry in the **Manufacturer** field in the material master record (purchasing view) is proposed as default value in the **Vendor/Manufacturer** field in the item details if no purchasing info. record with a defined regular vendor exists for this material.

Activities

Choose **transactions MM01, MM02, MM03** to create, change and display material master records.

Partners

Use

Master records have to exist in the system for all warranty partners in Warranty Claim Processing so that when posting warranty claims, credit and debit memos can be created and [posted](#) to the appropriate customer and vendor accounts.

You create master records in Warranty Processing in basically the same way as in the standard applications. The following paragraphs therefore only describe the settings that are specific to Warranty Claim Processing.

You create a **customer master record** for each **claimant** and a **vendor master record** for each **reimbursing** .

Integration

You use the vendor master record in MM and the customer master record in SD to create the business partners.

You can find further information in the standard documentation under Vendor Master Data and [Processing Customer Master Records](#) .

Features

- Each vendor/creditor also has to be assigned to itself as debtor in the vendor master record, otherwise problems occur in pricing and during FI postings. This debtor must have been created in the appropriate sales organization.
- You must maintain the company code data and the sales area data in the customer master record. You only have to maintain the company code data in the vendor master record; purchasing organization data is not required. You must enter the reconciliation account in the company code data.

Activities

- Choose **transactions XK01, XK02, XK03** to create, change and display vendors/creditors.
- Choose **transactions XD01, XD02, XD03** to create, change and display customers/debtors.

Partner Profiles

Use

If you want to receive and send warranty claims via IDocs/EDI within the framework of message determination, you must maintain **partner profiles** for the partners with whom you wish to communicate via **IDocs** . In these partner profiles you define the **general conditions for electronic data exchange** with business partners via IDoc interfaces, i.e.: you define which messages are exchanged, how and in which direction.

Integration

Message determination (component: CA-GTF-BS) is a cross-application component that can be called by warranty claim processing functions using the IDoc interface (component: BC-SRV-EDI).

You can find further information in the standard documentation under [Message Control \(CA-GTF-BS\)](#) , IDoc Interface / Electronic Data Interchange (BC-SRV-EDI) and Defining Partners .

Prerequisites

- You have set up the logical system and maintained the recipient ports.
- You have created the master data for your warranty processing partners (claimant, reimbursing).

Features

- Partners of **partner type KU** (customer; in Warranty Claim Processing: **claimant**)
 - Inbound parameters: partner function AS (claimant), message type WNTYRQ (Warranty Processing: claim request for IDocs for category [Versions from Claimant](#))

Message type WNTYRQ: inbound options: process code WTYIC (Warranty Claim Processing: claim in category [Versions from Claimant](#))

- Outbound parameters: partner function AS (claimant), message type WNTYCF (Warranty Processing: claim confirmation for IDocs for category [Versions to Claimant](#))

Message type WNTYCF: **outbound options:** IDoc basic type **WRANTY02** (warranty claim), **message control:** application RW (Warranty Claim Processing), message type as defined in Customizing for output/message determination, process code WTYOC (Warranty Claim Processing: claim for category [Versions to Claimant](#))

i Note

IDoc basic type **WRANTY02** is the direct successor of type WRANTY01 and differentiates itself from the latter in that it contains an additional segment for header conditions.

- Partners of **partner type LI** (vendor; in Warranty Claim Processing: **reimbursing**):
 - Outbound parameters: partner function VN (vendor), message type WNTYRQ (Warranty Processing: claim request for IDocs for category [Versions to Reimbursing](#))

Message type WNTYRQ: **outbound options:** IDoc basic type **WRANTY02** (warranty claim), **message control:** application RW (Warranty Claim Processing), message type as defined in Customizing for output/message determination, process code WTYOV (Warranty Claim Processing: claim for category [Versions to Reimbursing](#))

- Inbound parameters: partner function VN (vendor), message type WNTYCF (Warranty Processing: claim confirmation for IDocs for category [Versions from Reimbursing](#))

Message type WNTYCF: inbound options: process code WTYIV (Warranty Claim Processing: claim in category [Versions from Reimbursing](#))

i Note

You can enter additional partner functions with partner numbers on header and version level in the warranty claim.

Activities

Use transaction code **WE20** to create partner profiles.

i Note

You can use transaction WE60 to display the structure and documentation for the IDoc basic type WRANTY02.

Master Warranties

Use

If you want to use the option of an automatic [warranty check](#) you have to enter one or more **master warranties** with **warranty counters** for each warranty object in the object master record and create **measurement positions** and **measuring points**. The characteristics that you require for the warranty counters have to coincide with the characteristics for the measurement positions in the object.

You do not need this master data if you do not want to perform a warranty check or if only enter warranty periods in the warranty object and want to work exclusively with these.

i Note

You can use [reference objects](#) as a reference or a template to copy from when you create measurement positions and measuring points in the object.

Integration

Warranty counters are represented by characteristics in the Classification System (CA-CLCHR). Master warranties and measuring points are master data in the S/4HANA component Customer Service (CS).

- Master warranties: CS-AG-WA/PM-EQM-SF
- Measuring points: CS-IB-MC / PM-EQM-SF-MPC

You can find further information in the standard documentation under [Master Warranty](#).

Features

- [Master warranty](#) with warranty counters.

Master warranties define the **general scope of the services** that a company performs when there are **defects or problems** in a technical object. For vehicles, a master warranty can contain as warranty conditions a warranty deadline of two years with a maximum number of 50,000 km, for example.

You require master warranties so that you can assign individual warranty conditions to each warranty object and check in warranty claim processing whether the object has a valid warranty.

- Warranty Counter (Characteristics)

Warranty counters are a means by which the **wear and tear and depreciation of an object, consumption or the depletion of a supply** can be represented within the framework of the validity of a warranty. The **characteristics from the classification system** serve to represent the warranty counters.

You require the warranty counters in the **master warranty** and the **warranty object**. You can represent the number of kilometers traveled, hours operated and warranty periods with warranty counters.

You have to enter these characteristics as warranty counters in Customizing and, where necessary, define them as time-dependent (Customizing for [►Plant Maintenance and Customer Service►Master Data in Plant Maintenance and Customer Service►Basic Settings►Warranties►Define Warranty Counters►](#)). Only after having done this can you link the characteristics into a master warranty as warranty counters.

There are two types of **time-dependent warranty counters**: those which require a measuring point and a measurement document as they do not run continuously with time (example: equipment operating hours for equipment that can be turned off) and calendar warranty counters, which require no measuring point and no measurement documents since they run continuously (example: warranty periods). Time is calculated as of the reference date in warranty claims with these warranty counters.

The characteristics that you require for the warranty counters have to coincide with the characteristics for the measurement positions in the warranty object.

- Every non-calendar warranty counter of the master warranty must have been created exactly once as characteristic for the measurement position in the object.
- Calendar warranty counters of the master warranty should not be copied to the object.
- Basically you can assign **several master warranties** (alternatively several simple warranty periods) to one technical object in Warranty Claim Processing. However, the standard system supports only two (at the most) master warranties for technical objects of object type EQUI, FUNC and SERN, i.e. exactly one vendor warranty and exactly one customer warranty.

If you want to use this enhanced functionality, you must define how the overall check result for the master warranty is to be calculated from the check result for the individual items (Customizing for Warranty Claim Processing under ► **Control Data** ► **Warranty Check** ► **Define Settings for Master Warranty Check**). ►

Furthermore, for objects of object types EQUI, FUNC and SERN you have to link in the warranty claim processing screen as customer screen and hide both subscreens for both standard warranties (Customizing for Warranty Claim Processing under ► **Control Data** ► **Warranty Check** ► **Prepare Warranty Check** ►). This is not necessary for objects of object type IBAS and VELO.

You can assign exactly one master warranty and/or exactly one warranty period to each warranty type.

If all these conditions have been met, you can compare the measurement readings for the measuring points with the warranty counter specification limit readings in the master warranty in the [warranty check](#) .

Activities

- Enter transaction code **CT04** to define warranty counters.
- Use transaction codes **BGM1**, **BGM2** and **BGM3** to create master warranties.

Reference Objects

Use

You can use reference objects as a **reference** or a **template to copy from** when you **create measurement positions and measuring points** in the object.

When you copy or create the measurement positions, measuring points are automatically created in the object for these measurement positions. You can enter measurement readings for these measuring points in the warranty claim at a later date.

Features

You can define reference/template objects for every combination of [object type](#) (vehicle, equipment, installation, functional location) and **subtype for the chosen object type** in Customizing for Warranty Claim Processing under ► **Warranty Claim** ► **Define Template Objects**. ► If the object type is the installed base, for example, you can enter reference/template objects for each installed base category.

You can define one reference object each for the **version level** in the warranty claim and the **item level** within this version. Background: a replacement motor (items), for example, can have a different warranty than the vehicle itself (version).

The reference object on version level can have any number of measurement positions relevant to warranty. The reference object on item level should only have one measurement position relevant to warranty, otherwise the measurement position last created in

the reference object is used.

The reference/template object serves as a **reference** for creating object master records manually with reference to the measurement positions that have been created. It can be used as a complete copy template for equipment; for installed bases and functional locations it serves as a reference for creating measurement positions.

The measurement positions in the reference object and in the object itself have to be called the same if you want to enter values for the measurement position via the warranty claim that should be linked to the version. The characteristics that are linked to these measurement positions, however, can be different. Furthermore, the object can contain further measurement positions. These are then irrelevant to warranty claim processing ; you cannot enter measurement readings for these measurement positions in the warranty claim.

Catalogs

Use

A catalog is a grouping of codes that belong together content-wise with which qualitative subjects written in text form can be encrypted in a form that can be processed automatically.

You use catalogs in Warranty Processing when you **enter items** for a version. Catalogs can be called in the following functions: as a list of **defect codes** , of **labor values** (services) or of **external services** (invoices for materials and labor values or expenses).

i Note

You can link in your own defect catalogs using BAdI WTY_F4_DEFECT and your own external service catalogs and labor value catalogs using BAdI WTY_F4_ITMNO. These catalogs can be in the form of an external data carrier, external system or also as SAP catalog, for example, the standard catalog from the component Quality Management (QM).

⚠ Caution

There are important differences between the warranty claim processing functions in SAP Discrete Industries and in Enterprise. These differences are described below.

Implementation in SAP Discrete Industries

Catalogs that use the **SAP Classification System and class type 600 (catalogs)** are used in the standard system for SAP Discrete Industries. A class in this class type is assigned to each catalog. This ensures that this class is also assigned to all the catalog numbers in this catalog. The characteristics that are required for the value assignment are provided by the class.

When you call a catalog and choose an entry, you can assign values to the catalog characteristics. These values are then copied to the appropriate fields of the warranty claim and used in pricing.

♣ Example

For example, the characteristics **Material** and **Quantity** can be contained in the labor value catalog (WTY2). You should always assign the same service material and appropriate number of service units to all the entries in the catalog. You can the store condition records with prices for this service material. These prices can be determined automatically in pricing.

This procedure can be recommended since materials do not usually exist for labor values but pricing, however, is linked to the material.

Integration

The catalog used in **Warranty Processing** is the same as the one originally implemented in the component **Equipment and Tools Management** (IS-EC-CEM) .

You can find further information under [ETM Catalog](#) .

Features

No catalogs, classes or characteristics are delivered for Warranty Processing.

- BADIs WTY_F4_ITMNO, WTY_F4_DEFECT and WTY_CREATE_COPY via which the catalogs are called are, however, **hard-coded** on the following **catalog codes** :
 - WTY1 (defect catalog, field **Defect Code**)
 - WTY2 (labor value catalog, field **Key** for item type **Labor Value**)
 - WTY3 (external service catalog, field **Key** for item type **External Service**)

The appropriate catalogs are therefore called directly when you choose the F4 help function. However, the catalogs themselves do not exist yet. You have to create them yourself with these catalog codes.

- The above-named BADIs are also **hard-coded** on the following **characteristics** :
 - Defect catalog: no characteristics
 - Labor value catalog: characteristics WTY_DIENMAT (material), WTY_FLATRATE (quantity)
 - External service catalog: characteristic WTY_DIENMAT (material)

These characteristics do not exist yet either. You have to create them first.

Activities

1. Create the catalog codes WTY1, WTY2, and WTY3 according to your own business requirements in Customizing for Warranty Claim Processing.
2. Choose **transactions J3GK01, J3GK02, J3GK03** to create, change and display catalog entries for these catalog codes.

Implementation in SAP S/4HANA Enterprise

A catalog of type **C** from **Customer Service** (**CS**) is used as the defect code catalog. Instead of a labor value and external service catalog, the material master is displayed.

Activities

Maintain a catalog of the appropriate type **C** either in Customizing for **Customer Service (CS)** or Customizing for **Quality Management (QM)** under ►**Customer Service** ► **Solution Database** ► **General Data** ► **Catalog Maintenance and Settings for Reporting** ► **Maintain Catalogs** ► or ►**Quality Management** ► **Quality Notifications** ► **Notification Creation** ► **Notification Content** ► **Maintain Catalogs** ► .

Control

Warranty Claim Processing uses the following control elements:

- [Warranty claim types](#) for defining processing
- [Pricing](#) for the items of a warranty claim version

- [Message Determination](#) for printing credit memos and sending warranty claim IDocs to the business partners involved
- [Revenue Account Determination](#) for determining G/L accounts that are posted in FI when credit memos are created for the claimant and debit memos for the reimburer.
- [CO account determination](#) for determining the CO account assignment objects that are posted in CO at the same time as the FI G/L accounts.
- [Copying control](#) for copying warranty claim versions
- [VSR checks](#) for the substitution and validation of fields in the warranty claim
- [Action controls](#) for linking [actions](#) and processing statuses in an action matrix

Warranty Claim Types

Use

The warranty claim type determines the processing procedure that a [warranty claim](#) goes through (examples: [precrediting](#), [postcrediting](#), [authorization](#), [recall](#)). It contains **default values for the organizational data** and **control parameters**.

You cannot create any warranty claims without a warranty claim type. You always define the warranty claim type first and then create a warranty claim for this warranty claim type (see also: [Creating Warranty Claim Manually](#)).

The control parameters control the processing of the warranty claim and determine the [screen layout](#).

The default values serve as an aid when you enter data. They can be copied to all warranty claims of a warranty claim type and can be overwritten there, if necessary. You can alter default value determination and change the default values themselves by using BAdI WTY_CREATE_COPY.

You define warranty claim types in Customizing for [Warranty Claim Processing](#) under [Define Warranty Claim Types](#).

i Note

You can define settings that you want to be valid for all warranty claim types in Customizing for [Warranty Claim Processing](#) under [General Settings](#). These settings affect certain check periods and preferred condition types for the fast entry of items.

Prerequisites

You have made all the Customizing settings that are necessary for the creation of warranty claim types.

Features

- The following are some of the **control parameters** for a warranty claim type:
 - [Screen layouts](#) (a screen layout each for layout with navigation tree and layout without navigation tree) and a screen area in the claim header in which customer-specific fields can be used.

i Note

For linking customer-specific fields into the screen layouts, see also: [Creating Customer-Specific Fields](#), [Including Customer-Specific Screens in Header Area](#) and [Including Customer-Specific Screens on Tab Pages](#).

- Procedures for [Pricing](#), [Message Determination](#), and [Revenue Account Determination](#)

- [Default Values for Header Items](#) , i.e.: condition types within the assigned pricing procedure that should be used during fast entry of warranty claims as header conditions (Customizing for [Warranty Claim Processing](#) under [Pricing](#) > [Define Default Values for Header Conditions](#)).
- Entry defining for which condition types within the assigned pricing procedure you want the [CO Account Assignment](#) to be changeable (Customizing for [Warranty Claim Processing](#) under [Accounting](#) > [Allow Changeability of CO Account Assignments for Condition Types](#)).
- [Copy Procedures](#) for copying warranty claim versions (Customizing for [Warranty Claim Processing](#) under [Control Data](#) > [Copying Control](#) > [Assign Copy Procedures to Claim Types](#)).
- [Action Controls](#) , Start processing status, Start category, split criteria for [Processing with Claim Split](#) , item type group, indicator for creation of change documents

i Note

You can find further information on categories and item types in this documentation under [Warranty Claim](#) .

- Document types for credit and debit memos and PA transfer structures for Profitability Analysis (CO-PA) .
- Indicator whether changes made to warranty claims already saved should be saved in **change documents** .
- The following are some of the **default values** :
 - Partner roles/functions and partner numbers
 - Sales organization, distribution channel, division
 - Purchasing organization
 - Plant
 - Version currency

Activities

Check the warranty claim types delivered in the standard system Customizing. If necessary, define you own warranty claim types by copying ones that already exist to the customer namespace.

Pricing

Use

In Warranty Claim Processing, pricing serves to **determine specific prices and post them to Financial Accounting** for each warranty claim item and each warranty claim version. The system determines the appropriate condition records and therefore also the prices using the **condition technique** (see also: [Introduction to the Condition Technique](#)).

Integration

Pricing in Warranty Claim Processing is the same as the pricing functions that are used in Sales and Distribution (SD-BF-PR). The only difference is the application **RW** for [Warranty Claim Processing](#) .

You can find further information in the standard documentation under [Pricing and Conditions](#) .

Prerequisites

- You have entered a [partner](#) with a customer or vendor master record in the version for which pricing is to be performed.
- You have entered a [material number](#) for each item in the warranty claim for which pricing is to be performed. The material number can be determined automatically in the background via a catalog or an external number can be entered.
- You have defined the following in Customizing for **Warranty Claim Processing** under **Pricing** :

Pricing procedure

Condition type

Access sequences

Tables

Field catalog

(Usage **A** for **Pricing** , application **RW** for **Warranty Claim Processing**).

- If required, you have defined default condition types for header conditions in Customizing for Warranty Claim processing under **►Pricing► Define Default Values for Header Conditions. ►**
- If you want to work with header conditions, you have linked screen group S2025 into the screen layout of your warranty type in Customizing for Warranty Claim Processing under **►Layout► Define Screen Layouts. ►**
- You have assigned a pricing procedure to each [warranty claim type](#) in Customizing for Warranty Claim Processing under **Define Warranty Claim Types** .
- You have defined condition records for pricing (**transactions WYP1, WYP2, WYP3**).
- If you use pricing procedure WT0001 that is delivered with the standard system (see below) and want to work with **condition 597** , you have defined which condition type is to be restricted to which category and for which item type (material, labor value, external service) this restriction should be valid. You do this in Customizing for Warranty Claim processing under **►Pricing► Restrict Validity of Condition Types ►**).
- You have defined [copy procedures](#) in Customizing for Warranty Claim Processing under **►Control Data► Copying Control► Define Copy Procedures ►** and assigned a copy procedure to each possible copying transaction within a [warranty claim type](#) under **►Control Data► Copying Control► Assign Copy Procedures to Claim Types. ►** By doing this you have defined whether, per item type, the prices should be copied or not when you copy versions.

Features

• Pricing on Version and Item Level

The version in the warranty claim corresponds to the header in the SD sales order. Each version can contain pricing information, i.e.: pricing functions are available at any time and in any version. Price changes are basically only possible for active versions that have not yet been posted to FI.

When you create a new version, pricing is always carried out again. The basis for this is the copying of the price information from the referenced version (see Customizing for the copy procedure), a manual entry or an access to master data.

The item in the warranty claim corresponds to the item in the SD sales order. This means that you can call the pricing screen for each item and execute a pricing separately.

• Manual/Automatic Pricing

When a new version is created, pricing can be principally always be carried out automatically based on the master data or manually by transferring external price conditions.

• Posting to Financial Accounting

In Customizing for [Action Control](#) ([Define Action Controls](#)) you can define which categories can be posted in FI. In principal, all four categories can be posted in FI. However, it is recommended to choose just one category from each of the category pairs: [Versions from Claimant/Versions to Claimant](#) (credit memo, payable) and [Versions from Reimbursing/Versions to Reimbursing](#) (debit memo, receivable).

- **Customizing in the SAP Standard System Delivery**

The following pricing procedures are delivered with the SAP standard system:

- Pricing procedure **WT0002** (simple procedure) supports four pricing condition types (one per category), several addition/deduction condition types and two condition types for VAT and input tax. The four pricing condition types allow you, for example, to post the amounts for the four possible categories to different accounts and enter different account keys.
- Pricing procedure **WT0001** supports 12 pricing condition types; within the pricing condition type it differentiates not only by category but also according to material/labor value/external service. **The other settings are such that the person responsible for the standard postcrediting case has a type of history and can track how much was originally requested by the claimant, the amount that was forwarded to the reimbursing, the amount that the reimbursing approved and how much was finally agreed on as payment to the claimant.**
- Pricing procedure **WT0012** supports the posting of an amount to an interim account (G/L account) before this amount is posted from the interim account to the warranty revenue account in a second step (see: [Posting in Accounting \(FI/CO\)](#)). These reserves make sense if, for example, amounts should not yet be paid to the warranty revenue account in a precrediting case as long as the warranty claim is still in process. Account key WY3 is used for posting from the interim account to the warranty revenue account; the appropriate indicator is set for this account key in the pricing procedure.
- Pricing procedure **WT0022** allows you to change the CO account assignments that are determined automatically for individual condition types.

i Note

You can find further information on these pricing procedures in the system documentation for IMG activity [Define Pricing Procedures](#) .

Activities

1. Check the cumulated prices for all items of a version on the tab page [Prices - Version](#) . You can also enter **header conditions for this version** manually on this tab page, for example percent discounts and absolute discounts. If you then choose  [Activate](#) or save the claim, the amounts you have entered are distributed amongst the individual items (absolute discount) or the percentages for the individual items are calculated (percent discount).

Choose  [Update](#) to execute pricing again.

2. Check the prices per item on the tab page [Item Detail](#) . Only those condition types for which condition records have been found are displayed and/or those condition records without an access sequence, in other words without condition records, for which prices can only be entered manually. Condition types that have been defined in Customizing as manual are not displayed. Where required, change the prices manually and/or add further item condition types. You can only choose condition types for which you can make manual entries.

Choose  [Analysis to go to the condition analysis](#). The system displays a list of all the valid condition types for the item with a brief overview of the transactions involved in the automatic pricing. You can use this information to help you check how the individual pricing elements for the item were calculated in the system.

Choose  [Update](#) to execute pricing again.

3. If you work with screen group S2025 (see: prerequisites), you can, if required, enter **header conditions for all versions of a warranty claim** manually in this overview screen, for example percentage discounts and absolute discounts. If you then

choose  **Activate** or save the claim, the amounts you have entered are distributed amongst the individual items (absolute discount) or the percentages for the individual items are calculated (percent discount).

Message Determination

Use

You can automate the **output or subsequent processing of partner-dependent messages** by using message determination. The application calls message determination via defined interfaces.

You can use these **interfaces** to describe different data constellations and the desired processing methods. If one of these data constellations occurs in the application, appropriate processing is started either synchronously or asynchronously. You can define the processing in numerous ways, for example, as workflow, printout or as IDoc for EDI.

You can use message determination in Warranty Claim Processing to trigger the **printing of credit memos** , for example, and/or to **forward warranty claim versions** that have been received and processed **via IDoc/EDI to the reimbursor or claimant** .

Integration

Message determination is a cross-application component (CA-GTF-BS) that can be called by Warranty Claim Processing using defined interfaces. It is active for the application RW in Warranty Claim Processing.

You can find further information in the standard documentation under [Message Control \(CA-GTF-BS\)](#) and IDoc Interface / Electronic Data Interchange (BC-SRV-EDI) .

Prerequisites

- In Customizing for Warranty Claim Processing under [Message Determination](#) you have defined a **message determination procedure, message type, access sequences, tables and a field catalog** for message determination (usage **B** for [Message Determination](#) , application **RW** for [Warranty Claim Processing](#)).
- You have defined condition records for message determination (transactions **WYN1, WYN2 and WYN3**).
- You have assigned a message determination procedure to each [warranty claim type](#) in Customizing for Warranty Claim Processing under [Define Warranty Claim Types](#) .
- You have assigned a **partner function** for the claimant and a partner function for the reimbursor to each warranty claim type in Customizing for Warranty Claim Processing under [Define Warranty Claim Types](#) .
- You have maintained [partner profiles](#) for the business partners for sending IDocs via EDI (**transaction WE20**) and executed actions A860 [Release Outbound Claimant Version for Sending](#) and action A870 [Release Outbound Reimbursor Version for Sending](#) .

Features

Message determination procedure WTY001 with the following message types is delivered with the standard system:

- W001 Printout/fax of credit memos
- WTOC Shipping of warranty claim versions using IDoc/EDI. This message type has access sequence 0005. In this access sequence, the first access refers to condition records for the key **Partner Type** , the second access to condition records for the keys [Release for Sending](#) and [Partner Type](#) .

i Note

This message type is restricted to partner types LI (vendor) and KU (customer).

Activities

1. Choose  **Messages** on the tab page **Version Details** .

A screen appears with a proposal for output, which you can change if you wish. As long as the traffic lights are showing amber, the message has not been sent yet. If the traffic lights are on green, the message has been sent.

2. Choose  **Processing log to display the results of the output/message processing (number of the IDoc etc.)**.

Choose  **Goto**  **Determin. analysis**  . The system displays a list of all the valid condition types for the item with a brief overview of the automatic output/message determination transactions.

Revenue Account Determination

Use

Revenue account determination in Warranty Claim Processing serves to automatically determine the **G/L accounts** to which the revenue, sales deductions (additions and deductions) and tax should be posted **when posting the credit memos to the claimant or debit memos to the reimbursers**. Amounts from debit memos to the reimbursers are posted as positive revenue, amounts from credit memos to the claimant are posted as negative.

Integration

Revenue account determination in Warranty Claim Processing is identical to the revenue account determination that is used in SD (Sales and Distribution). The only difference is the **RW** application for Warranty Claim Processing.

You can find further information in the standard documentation under [Working with Account Assignment](#).

Prerequisites

- You have defined the following in Customizing for Warranty Claim Processing under **Revenue Account Determination**:

Account determination procedure

Account determination type

Access sequences

Tables

Field catalog

Condition records

(Usage **C** for Account Determination, application **RW** for Warranty Claim Processing). You can find the condition records in the IMG activity **Assign G/L Accounts**.

- You have assigned an account determination procedure to each **warranty claim** in Customizing for Warranty Claim Processing under **Define Warranty Claim Types**.

- In Customizing for Warranty Claim Processing under ► **Revenue Account Determination** ► **Define Account Key** ► you have defined **account keys**, and assigned the account keys to the individual pricing types in the pricing procedure under ► **Pricing** ► **Define Pricing Procedures** ►.
- You have defined **document types** in Customizing for Warranty Claim Processing under ► **Accounting** ► **Define Document Types** ► and assigned them to the warranty claim types under **Define Warranty Claim Types**.
- You have created the necessary [G/L Accounts](#) in Financial Accounting and entered them in the [Chart of Accounts](#) for your company code.
- You have performed **pricing** for the warranty claim version that you want to post to Financial Accounting.

Features

- Revenue account determination copies the quantities and values to be posted in the version currency from [Pricing](#), also the information for the posting of the tax (tax key, tax rate, tax amount, base amount). Quantities are only updated for pricing conditions (not for surcharges, discounts etc.).
- The SAP standard system provides the account determination procedure KOF100 with account determination type KOFI; this account determination type has access sequence KOFI. The above supports the following:
 - First access: condition records for the keys **account assignment group debtors**, **account assignment group material**, and **account key**
 - Second access: condition records for the keys **account assignment group debtors**, and **account key**
 - Third access: condition records for the keys **account assignment group material** and **account key**
 - Fourth access: condition records for the key **account key**
 - Fifth access: general condition records without any special key
- Furthermore, the SAP standard system provides the document types **WP** (warranty credit memo) and **WR** (warranty debit memo).
- Posting example: see [Posting in Accounting \(FI/CO\)](#).

Activities

1. Post the desired version to Financial Accounting. Depending on the version, choose one of the actions **A040 Post Versions from Claimant to FI**, **A041 Post Versions to Claimant in FI**, **A042 Post Versions to Reimbursing in FI**, **A043 Post Versions from Reimbursing in FI**.

i Note

You can undo postings to Financial Accounting with actions A051, A052, A053, A054. Action A049 cancels the current version.

2. Choose  **FI/CO Documents** on the tab page **Version Details** to display the documents created for the appropriate version. If you click on the document number, you branch to the document itself.

Choose  **Document Flow** on the standard toolbar to display the document flow across all versions. Besides the FI/CO documents, the measurement documents that are created during the warranty check can also form part of and can be seen in the document flow.

In the menu, choose ► **Extras** ► **Account Determination Analysis** ► to display the account determination types of the account determination procedure with their accesses.

CO Account Determination

Use

Controlling (CO) and Financial Accounting (FI) are implemented in SPA as two complete and separate application components. Data transfer takes place regularly between these two components.

All the data relevant to costs flows automatically from Financial Accounting to Controlling. The **costs and revenue** of different **CO account assignment objects** are assigned (for example, cost centers, projects or claims). The relevant FI accounts are managed as cost elements or revenue elements in Controlling. The values in Controlling and Financial Accounting can thus be compared and reconciled.

Thus, when accounting documents are posted in Warranty Claim Processing, CO account assignment objects are also posted.

Integration

CO account determination is identical to the CO account determination delivered with the standard system (transaction OKB9). Of course, as in the standard system, account determination can also be found by means of a customer-specific substitution (transaction OKC9).

You can find further information in the standard documentation under [Account Assignment of Controlling Objects](#).

Prerequisites

- You have created **account assignment objects** in CO.
- In Customizing for Warranty Claim Processing under ► **Accounting** ► **Define Automatic CO Account Assignment Determination** ► you have defined a **default account assignment** for each cost element that is to be posted in Warranty Claim Processing
- In Customizing for Warranty Claim Processing under ► **Accounting** ► **Define Automatic CO Account Assignment Determination**, ► you have set the **PrfSeg** (profitability segment) indicator for each cost element that is to be posted to a **profitability segment**.
- In Customizing for Warranty Claim Processing under ► **Accounting** ► **Allow Changeability of CO Account Assignments for Condition Types** ►, you have defined for which condition types the persons responsible are allowed to change the automatically determined CO account assignment during the processing of warranty claims, in other words for which they are allowed to post to a different CO account assignment object.
- If you want to work with changeable CO account assignments, you have linked in either screen group S2256 (changing the CO account assignment on item level) or screen group S2257 ► **(changing the CO account assignment on version level) to the screen layout of you warranty claim type in Customizing for Warranty Claim Processing under Layout ► Define Screen Layouts.** ►

Features

- **Automatic/Manual CO Account Determination**

Determination of CO account assignment is always executed automatically. The persons responsible can **change the CO account assignment manually** per item when they process the warranty claims for the condition types that have been defined in Customizing. This can be useful if, in a precrediting case, the reimbursor does not approve the entire amount and the difference is to be posted to a separate CO account assignment (see: [Posting in Accounting \(FI/CO\)](#)).

- **Possible Account Assignment Objects**

You can choose from the following account assignment objects: **cost center, claim, profitability segment or profit center**. Company code and cost element are available as criteria for CO account assignment determination.

- **Specifying the Categories**

In Customizing for [Action Control](#) ([Define Action Controls](#)) you can define which categories can be posted in FI. In principal, all four categories can be posted in FI. However, it is recommended to choose just one category from each of the category pairs: **Versions from Claimant/Versions to Claimant** (credit memo, payable) and **Versions from Reimbursing/Versions to Reimbursing** (debit memo, receivable).

Activities

1. If you work with screen groups S2256 or S2257 (see: prerequisites), you can overwrite the automatically determined CO account assignments on these screens on version level or item level.
2. Post the desired version to Financial Accounting. Depending on the version, choose one of the actions A040 **Post Versions from Claimant to FI** , A041 **Post Versions to Claimant in FI** , A042 **Post Versions to Reimbursing in FI** , A043 **Post Versions from Reimbursing in FI** .

i Note

You can undo postings to Financial Accounting with actions A051, A052, A053, A054. Action A049 cancels the current version.

3. Choose the function  **FI/CO Documents** on the tab page **Version Details** to display the documents created for the appropriate version. If you want to branch to the document itself, click on the document number.

Choose  **Document Flow on the standard toolbar to display the document flow across all versions**. Besides the FI/CO documents, the measurement documents that are created during the [warranty check](#) can also form part of and can be seen in the document flow.

Tax Determination

Use

In Warranty Claim Processing, tax determination is used to determine the sales tax of a warranty claim as well as the corresponding general ledger (G/L) accounts when posting a warranty claim in Financial Accounting or in an external system. [Pricing](#) calculates the taxes before the warranty claim is posted in Financial Accounting. The way taxes are determined in pricing depends on the tax type.

Features

During pricing, the system copies the tax code, which is required for determining the tax amount, from the condition record (depending on the tax classification for the customer and material). For vendors, the system uses the tax classification of the customer assigned to them.

You can also determine the tax code when you create an item by using the default implementation or customer implementation of the Business Add-In **BAdI: Data Change after Copying/Creating/Changing** (WTY_CREATE_COPY), and then save it in the TAX_CODE field of the item. This is necessary if the system does not determine the tax values from the (warranty) condition record. If you want the tax code to be dependent on the material and vendor, you can make this setting in the purchasing info record.

You can also set the tax code in the **BAdI: Transfer of Data to Pricing** (WTY_KOMK_KOMP) Business Add-in directly before calling pricing (method CHANGE_KOMP, field KOMP-MWSKZ). The system uses the value KOMV-MWSK1 that was determined in pricing

when posting the warranty claim in Financial Accounting.

In the example implementation for BAdI WTY_KOMK_KOMP (method CHANGE_KOMP), the system also transfers the tax code from the purchasing info record to the pricing communication structure.

If you do not want the tax condition to be valid for all item types, you can remove the pricing condition for this item. For an example, you can use the WTY15_KOBED_060 (Condition Type Only Valid for Material Items) function.

Output Tax

For output taxes or input taxes (for example, for Germany), you have defined condition records for pricing (transactions WYP1, WYP2, WYP3). The values must match the values configured in Financial Accounting.

For account determination, the system uses the Customizing settings for Financial Accounting.

External Tax Systems

For the connection to external systems (for example, for USA and Canada), you can use price formulas that call interface programs. The formulas return the values determined in the external system to the tax conditions in Warranty Claim Processing. For more information about connecting an external tax system for Warranty Claim Processing, see SAP Note 1281376.

For account determination, the system uses the Customizing settings for Financial Accounting.

Withholding Tax

To determine the withholding tax, the system uses the withholding tax settings in Customizing for Financial Accounting and special condition types.

You have created the pricing condition type in Customizing for Sales and Distribution and Warranty Claim Processing and assigned it to the withholding tax type in Customizing for Financial Accounting. You make this Customizing setting under **Financial Accounting (New) > Financial Accounting Basic Settings (New) > Withholding Tax > Extended Withholding Tax > Calculation > Withholding Tax Type > Assign Condition Type to Withholding Tax Type**. In addition, you have entered the (warranty) pricing condition types with condition class **W** and condition type **D**. You make these Customizing settings under:

- **Plant Maintenance and Customer Service > Warranty Claim Processing > Pricing > Define Condition Types**
- **Sales and Distribution > Basic Functions > Pricing > Pricing Control > Define Condition Types**

The system determines the condition values during pricing from the withholding tax tables for the country, from the withholding tax type, and the withholding tax code.

You have entered a partner with a customer or vendor master record for the warranty claim version for which pricing is to be performed. You have created the withholding tax data for this partner. You can adjust the withholding tax data transmitted to the Financial Accounting BAPI by using the **BAdI: Data Change before Calling FI-BAPI** Business Add-In (method WITH_HOLDING_TAX_DATA_CHANGE).

For account determination, the system uses the Customizing settings for Financial Accounting.

Non-Deductible Input Tax

For non-deductible input tax, you have created condition types with condition class **D** (Taxes) and condition type **N** (Input Tax not Deductible) in Customizing for Warranty Claim Processing. You make this setting under **Warranty Claim Processing > Pricing > Define Condition Types**.

You copy these condition types to the pricing procedure using a formula for calculating the tax value from the Customizing settings in Financial Accounting. The standard condition formula 599 with the WTY15_KONDI_WERT_599 function is available for this. You

make this setting under [Warranty Claim Processing > Pricing > Define Pricing Procedures](#).

The formula calculates percentage condition values for a maximum of two condition types in the customer namespace. The prerequisite for this is that the first condition in the procedure represents the non-deductible amount and the second condition represents the deductible amount. If you want to use more than two condition types (max. 6), or you want to use another sequence within the procedure, you must create your own formula.

If you have created condition types in Warranty Claim processing with the same names as the condition types in Financial Accounting, the system also determines the tax values with the formula from Financial Accounting (such as condition types MWVN and MWVZ).

You can make the condition value visible (with or without the net value) via the totals lines in the price determination schema in the pricing view of the warranty claim (tab page [Prices - Version and Item Details](#)).

It is also possible to store the tax values in Warranty Claim Processing condition records and work without using formulas (transaction WYP1). However, you must use the same values that were determined during posting in FI.

When posting the warranty claim version in FI, the system adds the value of the non-deductible amount of tax to the revenue posting amount.

Copying Control

Use

For actions that copy versions, principally **all header, version and item data** is copied from the source version to the target version. Exception: technical fields, such as the "Globally Unique Identifiers" (GUID). You can use the copy procedure to exclude individual fields from the copying process.

You define copy procedures in Customizing for Warranty Claim Processing under [Copying Control > Define Copy Procedures](#). Under [Copying Control > Assign Copy Procedures to Claim Types](#) you can assign a copy procedure to each copying direction within a claim type.

Features

- You can exclude the **long texts** and **all the fields of tables PNWTYH (header data), PNWTYV (version data) and PVWTY (item data)** from the copying process.
- The copy procedure is not specifically for an action but **specifically for a type of copying direction within a claim type**. For example, if you want to copy the version from the claimant (source version) to the version to the reimbursor (target version) within a warranty claim type, you can enter a different copy procedure than the one you use for copying the version from the reimbursor to the version to the claimant.
- You can define per copying direction within a warranty claim type whether the **prices** should also be copied when you copy items or whether new pricing should take place. You can control the copying of prices for the item types MAT, FR and SUBL separately.
- Furthermore you can define (per copying direction within a warranty claim type) that items, for which a specific field is filled, are not copied. In this way you can, for example, control that an item that has received the decision code **rejected** in the version form the claimant is not copied to the version to the reimbursor during postcrediting.

VSR Checks

Use

In **Warranty Claim Processing**, VSR checks (VSR = validation/substitution rule) serve to check the validity of the data entered with a high degree of automation before it is saved to the database (**validation**) and to replace specific data (**substitution**). The checks can then be linked in to actions and be called automatically or manually in Warranty Processing depending on the settings in Customizing.

A **validation** comprises at least one step. Each step is composed of three components: prerequisite (optional), check and message. The check is only carried out when the prerequisite has been fulfilled. If the check runs up against an error, a predefined message is displayed.

A **substitution** comprises at least one step. Each step is composed of two components: prerequisite and substitution. The substitution is only carried out when the prerequisite has been fulfilled.

i Note

If the system is to display messages for substitutions as well as validations you first have to create a validation with the same prerequisite for the appropriate substitution and also an inverse check (for this prerequisite). In the case of the substitution (i.e. prerequisite is fulfilled), the validation encounters an error and an appropriate message is displayed.

The standard actions for calling VSR checks therefore expect a validation for every substitution. If you want to work with substitutions without validation (and therefore without message), you have to program your own actions.

You can combine several terms to complex **rules** by using operators (for example, AND, OR). If you do not want to have to create the same rule every time with the editor, you can define and save rules per call-up point (see below), which are then available for every validation or substitution of this call-up point.

Integration

The VSR checks are identical to the VSR checks that are used in FI-SL **Special Ledger**.

You can find further information in the standard documentation under [Validation, Substitution and Rules](#).

Features

- You create validations and substitutions for each call-up point in the application area warranty. Call-up points are specific places in an application at which the processing of a validation or substitution is called up. Data available for the validation and substitution depends on the call-up points.

The possible call-up points in warranty claim processing result from the possible combinations of the following parameters (see also: [Warranty Claim](#)):

- **Category:** versions from claimant, versions to reimbursing, versions from reimbursing, versions to claimant
- **Claim level:** header + version, defect code (on item level), entire item

You can differentiate between 3 different call-up points for each combination.

- The system can display a **message** as the result of a validation. If you assign a decision code to such a message, this code is set in the warranty claim as the result of the validation.

If a validation checks whether an object still has a warranty and the result is negative, the system can display the message "There is no longer a warranty for the object", for example, and then set the decision code **Rejected** in the warranty claim.

- The default settings only allow warranty claim data to be evaluated. If you wish to link in other data, you have to enter your own exits in Customizing for **Warranty Claim Processing** under **Control Data** > **VSR Checks** > **Define Client-Dependent**

User Exits.

- The validations and substitutions that you create are automatically called by the standard actions A006, A007, A016, A017, A026, A027 and A036. Action A006 **Rule Engine Versions from Claimant (Time 1/2/3)**, for example, processes all the validations and substitutions one after the other that belong to the category **Versions from Claimant**, that perform checks on the data on header and version level and that have been defined for call-up points 1, 2 and 3.
- There is one VSR check log each for the header and version-related checks, for the item-related checks and for the checks related to the defect code. In the [standard layout](#) you can find the first two logs on the tab page **Version Detail**, the third log on the tab page **Item Detail**. However, you can also place the check logs together on a separate tab page. You have screen groups S2220/2225, S7910 and S7915 at your disposal for this purpose.

Activities

1. Create validations and substitutions and rules, if required, in Customizing for **Warranty Claim Processing** under ►► **ControlData** ► **VSR Checks** ►.
2. Activate the VSR checks that are currently require (**transaction WTY_VSR_ACTIVE**).
3. Include the VSR checks in the [programming of your own action modules](#).

Example

You can, for example, send all the claims from a specific dealer that contain an item with a value of over € 1000 to be processed manually. To do this, create a validation that finds the claims of this dealer as prerequisite and determines the items with a value of over € 1000 as check. Then create a substitution to define that the field **Manual Processing** in the claim is selected for these claims.

Action Controls

Use

You define [processes](#) for automatic and manual warranty claim processing by defining **action controls** and assigning an action control to each [warranty claim type](#). The processing procedures can be different from claim type to claim type.

An action control contains an **action matrix**, in which you define which [actions](#) are allowed for a specific **processing status** of the claim and which new status then results.

You define action controls in Customizing for Warranty Claim Processing under ►► **Control Data** ► **Process Control** ► **Define Action Controls** ►.

Features

An action control defines the following:

- in **manual processing**, the actions that can be performed at each processing status. These actions are then displayed in the action box in the warranty claim as available for being performed.
- in **automatic warranty claim processing**, the action that is processed automatically at each processing status (indicator: **Automatic**)

Only one action per action control and processing status can be defined as an action for automatic processing.

If there is more than one elementary action that should be performed automatically at a specific processing status, you first have to group these elementary actions together into an interlinking action, then enter this interlinking action in the matrix and define it as automatic.

Activities

1. Check the processing statuses, actions and action controls in Customizing of the standard system.
2. If required, define new action controls.
3. Assign an action control to each [warranty claim type](#) .

Actions

Use

An action is a business part process in Warranty Claim Processing.

You define actions and processing statuses in Customizing for Warranty Claim Processing under **Control Data** > **Process Control** and link them to [action controls](#) in action matrices.

Features

Actions can be **elementary actions** or **interlinking actions** . Interlinking actions can consist of two or more actions that are linked to one another; the latter can be either elementary actions or interlinking actions themselves.

i Note

If an action runs up against an error within an interlinking action, the processing status that was last successfully reached is set. In other words, the entire interlinking action is not reset.

Furthermore, actions can be differentiated according to whether they should be displayed in the **action box** in the warranty claim or not. Actions that are only relevant to automatic warranty claim processing and should not be able to be triggered manually, ought not to be displayed.

The **standard system** contains numerous actions that cover the most common processing statuses. The following lists and groups all the delivered actions that are displayed in the action box.

Action Code	Use
A006, A007, A016, A017, A026, A027, A036	Start YSR checks and set decision code.
A008, A010, A011, A012, A013, A014, A015, A018, A019, A020, A021	Copy a version to a version of the same category or of another category.
A860, A870	Release version for sending.
A039, A040, A041, A042, A043	Post version to financial accounting.
A049, A051, A052, A053, A054	Delete FI documents for a version.
A110	Determine service contracts for object number
A101	Debit memo request

Action Code	Use
A102	Credit memo request
A200	Check master warranty .
A090, A091	Check whether a version contains parts to be returned .
A060, A061, A062, A070, A071	Split claimant version into several reimbursing versions and/or group several reimbursing versions to one claimant version.
A097, A098, A099	Perform mass changes on items.
A080	Explode an item of item type List , i.e.: display the subitems for a main item.
A096, A400, A095	Release recalls , find recalls per object, use recalls.
A300, A301	Allow authorizations and/or undo the authorization.
A100	Create free delivery.
S001	Interlinking action: automatic processing of warranty claims in postcrediting case after the version has been received from the claimant.
S002	Interlinking action: automatic processing of warranty claims in postcrediting case after the version has been received from the reimbursing.
S003	Interlinking action: check master warranty (A200) and call VSR checks (A006).

Activities

Check the delivered actions and, if required, programme your [own actions](#) .

Program Flow when Calling Actions

Below is a list of the individual technical processing steps that the system performs if a warranty claim is changed in transaction WTY.

This information is mainly aimed at technical consultants who want to create and include customer-specific actions.

Presentation Layer PAI

1. Transfer data from presentation layer buffer to the dialog structures
2. Process OK codes that are not represented as actions and that are not processed after the processing layer (load, ACTIONNtc.)
3. Call processing layer
4. Process OK codes that are not represented as actions and that are processed after the processing layer because they access an up-to-date buffer (save, CANCEL, BACK etc.)

Processing Layer (Method Claim_Maintain of Class CL_PPELIWTY_CNTL)

1. Data transfer from presentation layer or BAPI
2. Determine current warranty claim header and current warranty claim version
3. Check the user authorization and, if required, terminate processing
4. Read Customizing for claim
5. Data transfer form the dialog structures to the buffer structures of the processing layer
6. Read buffer before changes are made to warranty claim and save in a temporary table
7. Call BAdI WTY_DATA_CHANGE_1 with method DATA_CHANGE_1. This BAdI is used to change the warranty claim before calling standard processing.
8. Compare old buffer content with new content
9. If changes exist: determine additional data (for example texts, master data, Customizing, measuring points etc.) Then call BAdI WTY_CREATE_COPY with method data_change_changeThis BAdI allows changes to be made in the change mode for warranty claims
10. Update buffer with the current data (inclusive pricing)
11. Call action control: the buffer is read for each of the actions to be called, the action is executed, the target processing status determined, the totals on header and version level calculated and, if required, the buffer is updated. If an action returns an error, the old buffer with the warranty claim data is restored.

Presentation Layer PBO

1. Read the current buffer content of the processing layer and transfer to the puffer structures of the presentation layer
2. Call the different subscreens

Creating and Including Customer-Specific Actions

Use

This procedure is devoted to technical consultants at the customer's site, who have both ABAP programming knowledge and are also familiar with warranty processing functionality and the customer's business processes.

Prerequisites

You have read [Program Flow when Calling Actions](#) .

Procedure

Preparations

Before you create a customer-specific action, you should check whether a standard action is contained in the delivered Customizing settings that fulfills your requirements.

Identify the business process in which the action should be used.

The business process is represented in Customizing by the [warranty claim type](#) .An [action control](#) is assigned to each warranty claim type there.The action control contains an action matrix in which is defined which [actions](#) are allowed at which processing status of the claim and how the processing status is changed by the action.

Define the framework for the action.

Which processing status does the warranty claim have before the desired action?Which processing status does it have afterwards?

For copying actions: which [categories](#) of the versions are involved?(versions form claimant, versions to reimbursers etc.)

Define in which mode the action is to be executed (display, change, create, automatic processing).

Define the functionality of the action (copy, check, pricing etc.).

If you require more than one functionality within the action, you can create an interlinking action (see below).

Check whether you can use one of the existing standard actions.

To do this, choose the action in Customizing by using the description or search for the action in the action matrix of the action control by using the start and target processing status and then compare the description.

Does the action module deliver the desired functionality?

Are the general Customizing settings for the action correct?

Is the action matrix of the action control in which the action is contained correct?

Execution

If you do not want to use a standard action either because Customizing has not been defined as you require it or because the action module does not have the desired functionality, proceed as follows:

Create a new [warranty claim type](#) (Customizing for Warranty Claim Processing under [Define Warranty Claim Types](#)).Copy an existing warranty claim type to the customer namespace.

Make further settings in Customizing if you require them for programming your own action modules.

Only for copy actions: Customizing for [Copying Control](#) (Customizing for Warranty Claim Processing under [Control Data – Copying Control](#))

Is a copy procedure required?

Has the copy procedure been defined?

Has the copy procedure been assigned to the claim type, source category and target category?

If you do not enter a copy procedure, all the field contents are copied. with the exception of technical fields such as the GUID.

Only for check actions: Customizing for [VSR Checks](#) (Customizing for Warranty Claim Processing under [Control Data – VSR Checks](#))

Only for pricing actions: Customizing for [Pricing](#) (Customizing for Warranty Claim Processing under [Pricing](#))

If required, create your own action function module.To do this, copy action module WTY04_EXAMPLE_FOR_ACTION to the customer namespace.

You can find out more about the export parameters in the long text for the appropriate parameters.

Program the desired functionality in this action module.

In Customizing, create a new [action](#) with action code in the customer namespace with descriptive text (Customizing for Warranty Claim Processing under **Control Data** → **Process Control** → **Define Actions**).

Choose action type F or T (elementary action) or A or V (interlinking action).

Can you display the action?

Should the action be logged in the action log?

Only for interlinking actions: define which actions should be contained in the interlinking action and in which sequence they are to be processed.

Both elementary and interlinking actions can be used in an interlinking action.



Leave space between the items when you enter the sequence so that you can add further actions later, e.g.: enter 5, 10, 15 and not 3, 4, 5.

Only for elementary actions: assign an action module to the action.

Use the action module of a suitable standard action or your own action module (see above).

Assign a unique function code to the action code (Customizing for Warranty Claim Processing under **Control Data** → **Process Control** → **Assign Function Codes to Action Codes**).

Each action that you start via the action box, triggers a function code. The action code and the function code are the same for these actions. Nevertheless, you have to enter the appropriate assignment.

For function codes that are triggered via pushbuttons and menu path commands, the function code is defined in the Screen Painter or the Menu Painter for existing screens. For new screens, you have to enter a function code there. You must assign this function code to the action code.

Define the start and target processing status for the action (Customizing for Warranty Claim Processing under **Control Data** → **Process Control** → **Define Processing Statuses**).

Which processing status do the warranty claims to be processed have?

Which processing status should the processed warranty claims have?

Use the existing processing statuses or create new ones in the customer namespace.



For interlinking actions, ensure that the processing statuses of the actions contained build on each other. Example: interlinking action V1 contains actions A1, A2 and A3 in this sequence. For A1, the processing status changes from B1 (start processing status) to B2, for A2 from B2 to B3, for A3 from B3 to B4. B1 must therefore be entered as start processing status for V1 and B4 as target processing status.

When executing an interlinking action, the target processing status of the last successfully performed action is always set as target processing status. If, in our example, action A3 is not successful when V1 is executed, the target processing status is set to B3 and

Create a new [action control](#) an (Customizing for Warranty Claim Processing under **Control Data → Process Control → Define Action Controls**).Copy an existing action control to the customer namespace.

Copy this action with start and target processing status to the action matrix of this action control.

Should automatic processing be possible for the chosen start processing status?



If you want to allow a grouped area of connected actions for a specific start processing status, you can work with placeholders.

Assign user authorizations for the action (authorization object **Action**).

All users should have at least the authorization for the delivered actions with action code T*, since these are mostly technical actions that are required for the display and processing of warranty claims.

Assign your action control to the warranty claim type (Customizing for Warranty Claim Processing under **Define Warranty Claim Types**).

Business Add-Ins (BAdIs)

BAdI	Description
Processing Warranty Claims	
WTY_READ_SUPPL_DATAReading of Additional Data for Claim	You can use this BAdI to read a claim from the database or to change the warranty object master data for the object or to read short texts for the catalog entries and measuring points for the object. When changes that do not directly affect the warranty object itself are made in the claim, you also have to implement BAdI WTY_CREATE_COPY.
WTY_CREATE_COPYData Change after Copying/Creating/Changing	You can use this BAdI to read additional data when creating and changing warranty claim and copying claim versions, determine default values, fill customer-specific fields, change standard fieldsand validate fields etc. The methods of this BAdI are run through both when processing a warranty claim using WIN UI and when creating /changing data using a BAPI (BAPI_WARRANTYCLAIM_CHANGE), IDoc and WEB UI after the standard coding has been read and before pricing and update of the data buffer.
WTY_DATA_CHANGE_1Data Change After Data Entry but Before Standard Processing	You can use this BAdI to change data after entry but before standard processing starts and before the methods of BAdI WTY_CREATE_COPY are called. At this point in time, no GUID has been assigned when a new item is created. As regards its scope of functions, the BAdI corresponds in many ways to BAdI WTY_CREATE_COPY. The only difference is the time at which the methods are called.

BAdI	Description
WTY_DISPLAY_OBJECTDisplay Object Data	You can use this BAdI to call data for the object by double-clicking on the object number in the warranty claim. Display transactions for the appropriate object type is called in the BAdI. These transactions access the object master record. This BAdI replaces BAdI WTY_CALL_OBJECT_DATA.
WTY_F4_DEFECTF4 help for field Defect Code	You can use this BAdI to call and display a damage/defect catalog by calling the F4 help function on the field Defect Code . The system returns your chosen defect code (CV_DEFECT) to the calling program. The catalog of damages/defects can be in the form of an external data carrier (CD-ROM), an external system or an SAP catalog.
WTY_F4_ITMNOF4 help for field Key	You can use this BAdI to call and display a catalog by calling the F4 help function on the field Key . The system returns your chosen code, together with further parameters, to the calling program. The catalog can be in the form of an external data carrier (CD-ROM), an external system or an SAP catalog.
WTY_F4_MATNRF4 help for field Material	You can use this BAdI to change the standard search help or replace it with a customer-specific one by calling the F4 help function on the field Material. Furthermore, you can influence which material data should be displayed when you double-click on the material number in the warranty claim.
WTY_F4_MGANRF4 help for field Master Warranty	You can use this BAdI to change the standard search help or replace it with a customer-specific one when you create installed bases of type WY in transaction IB51 by calling the F4 help function on the field Master Warranty .
WTY_F4_RELOBF4 help for field Ext. Object Number	You can use this BAdI to change the standard search help or replace it with a customer-specific one and influence certain related checks when you call F4 help functions in relation with the warranty object.
WTY_DOCU_FLOWEnhancement of Document Flow	You can use this BAdI to add documents for new actions that are not displayed by default to the document flow and display them.
WTY_ITEM_GENERATEPreparation of Master Data for Item Generation	You can use this BAdI to read and prepare master data for the generation of subitems for a main item for an item of item type EXP (list). The master data could be an installed base, a material BOM, a bill of services or a routing/task list. This BAdI is used together with action A080 Explode List.
WTY_KOMK_KOMPTTransfer of Data to Pricing	You can use this BAdI to copy claim data or data read at a later date to the pricing structures KOMK and KOMP during pricing and make this data available for pricing.
WTY_SELECTION_LISTSearch for Warranty Claims	You can use this BAdI to add another selection when searching for warranty claims (transaction WTYSE). If you implement this BAdI the standard selection is not used.
WTY_RECALLSObject Selection for Recalls	You can use this BAdI to change the object selection in dependence of the object type and object ID for action A095 Find Recalls for Object. The object selection in the recall itself and the object selection in action A095 have to correspond.

BAdI	Description
WTY_RETURN_PARTSGoods receipt posting of parts to be returned	You can use this BAdI to add in material postings, or similar, when you post the receipt of parts to be returned (transaction WTYRP). The default settings/settings in the standard system dictate that only the status of the parts to be returned is changed in the warranty claim.
WTY_DYNPRO_DYNAMICDynamic Setting of Screen Areas	You can use this BAdI to set the screen areas dynamically in the warranty claim and to influence the structure of the navigation tree.
WTY_COPA_CRITERIAFeeding of Characteristics in CO-PA	You can use this BAdI to feed the characteristics of the profitability analysis (CO-PA) with values from the warranty claim or the information resulting from the claim.
WTY_COPA_VALUEFIELDSDFeeding of Value Fields in CO-PA	You can use this BAdI to feed the value fields of the profitability analysis (CO-PA) with values from the warranty claim. It is called when a warranty claim version is posted in Accounting.
Creating Warranty Claims Externally	
WTY_BAPI_CREATEAddition of Customer Fields in BAPI_WARRANTYCLAIM_CREATE	If you process warranty claims by using BAPI: • BAPI_WARRANTYCLAIM_CREATE (to create) • BAPI_WARRANTYCLAIM_CHANGE2 (to change) • BAPI_WARRANTY_CLAIM_ADD_VERSION (to create new versions of a warranty claim) you can add customer fields with this BAdI.
WTY_CLAIM_IDOC_INData Check and Data Change with Inbound IDocs	You can use this BAdI to check the data in inbound IDocs from the claimant or the reimburer and, if necessary, change it, transfer data from the customer segments to the SAP data structure, define the warranty claim type for IDocs from the claimant, determine the equipment for the vehicle and to check the partner function etc.
WTY_CLAIM_IDOC_OUTData Check and Data Change with Outbound IDocs	You can use this BAdI to change the segments, and, if necessary, add new segments for outbound IDocs to claimant or reimburer. The data for all segments is available to you every time you call this BAdI.
SAP Business Warehouse	
WTY_BWCopy Warranty Claim Data to SAP Business Warehouse	You can use this BAdI to influence which warranty claim data the system extracts to the Business Information Warehouse (BW) and is therefore available for evaluations there. It is called after standard processing has finished but before the data is extracted to BW.
Accounting (FI)	
WTY_POSTING_DATA	You can use this BAdI in the FI posting actions to make changes before the FI BAPI is called.

Warranty Claim Processing (Fiori)

The warranty claim processing has been developed to fulfil the needs of both customers and suppliers.

The **Manage Supplier Claims** application allow users to create a reimbursement request to a supplier for a complaint or repair of a product. It contains detailed information of the complaint/repair, such as specific prices for the replaced material and labor tasks, dates, and other related data.

Customer Facing

With the **Manage Customer Claims** application, a claim analyst can create and process a warranty claim from a customer (based on a performed repair). With this application, it is possible to create a claim, validate it for completeness and eligibility for reimbursement, document the claim decision, and perform the payment.

Prerequisites

This section summarizes all prerequisites to conducting the test in terms of systems, users, master data, organizational data, other test data and business conditions.

System Access

System	Details
System	Accessible via SAP Fiori launchpad. Your system administrator provides you with the URL to access the various apps assigned to your role.

Roles

Assign the following business roles to your individual users:

i Note

The following roles are provided as example roles from SAP. You can use these as templates to create your own roles.

For more information on business roles, refer [How to Create a Business Role for an Administrator](#) and Assigning Roles to a User in the [Administration Guide](#).

Roles		
Business Role	Object	Application Name
SAP_BR_MAINTENANCE_PLANNER	- Equipment - Functional Location	Create/Change and Display Technical Objects
SAP_BR_BUPA_MASTER_SPECIALIST	- Supplier - Customer	- Manage Supplier Master Data - Manage Customer Master Data
SAP_BR_CLAIMS_ANALYST_COMPL	Claim	Manage Claims

Business Role	Object	Application Name
SAP_BR_PRODMASTER_SPECIALIST	Material	Manage Product Master Data
SAP_BR_MD_SPECIALIST_WRNTY	Warranty Master Data	- Create Pricing Condition Records - Change Pricing Condition Records - Display Pricing Condition Records

i Note

You need to maintain master data (equipment/functional location/supplier or material) used within the warranty claims while navigating to the individual applications with the relevant test user in the cloud system.

Master Data, Organizational Data, and Other Data

The organizational structure and master data of your company has been created in your system during activation. The organizational structure reflects the structure of your company. The master data represents materials, customers, and suppliers, for example, depending on the operational focus of your company. Use your own master data or the following sample data to go through the test procedure.

For more information on creating master data objects, see the following [Master Data Scripts](#) .

- For supplier claim, refer [Warranty Claim Management - Supplier Recovery Processing](#).
- For customer claim, refer [Warranty Claim Management - Customer Claim Processing](#).

Business Conditions

Scope Item	Business Conditions
1LQ	his scope item provides best practice information for SAP S/4HANA output management that can be used to implement business scenarios that include output-related tasks. For details, refer SAP Best Practices Explorer  .

Master Data

You require the following master data in warranty claim processing:

- [Warranty Objects](#) (equipment, functional location)
- [Materials](#) for the warranty claim items
- [Partner](#) (supplier)
- Maintain [Pricing Condition Records](#)

Warranty Objects

Warranty objects are the reference objects, where warranty information can be maintained in the system and which can be used in a claim as reference. The following technical objects in the SAP system can be warranty objects in warranty processing: equipment and functional locations.

Objects

- Equipment

An equipment item is an individual object that is maintained as an autonomous unit, for example a production resource, means of transport, testing and measuring equipment, production resource or tool, a building or a PC. Equipment can be part of functional locations or independent. Each equipment item is maintained in the system with individual data (for example: construction year, warranty information or location).

- Functional Location

A functional location is an organizational unit in *Logistics* that structures the maintenance objects of a company according to functional, process-oriented or spatial criteria, for example a pumping station, a sewage or purification plant or a hall. A functional location represents the place at which a maintenance task is performed and start date and master warranty must be assigned to it.

The claim analyst can assign a master warrant to maintain the respective warranty conditions (start / end date and counters).

Warranty objects can be accessed through the Fiori application [Change Technical Object](#).

The role, *SAP_BR_MAINTENANCE_PLANNER*, is required to launch this application.

Change Technical Object : 210100001

Read Only | Check Entries | Set User Status | Change Structure | Additional Functions | You can also

Technical Object: 210100001 | Technical Object Type: Equipment | Description: Manual Isolation Valve | Category: M - Machines | Valid From: 26.07.2022 | System Status: INST | 0 Document(s)

General Data | Location Data | Organization Data | Structure | Documents | Classes | Characteristic Values

Manufacturer Data

Manufacturer: | Country/Region of Manufacture: US |
 Model Number: | Month/Year of Construction: 11 | 2014 |
 Manufacturer Part Number: | Manufacturer Serial Number: |

Reference Data

Acquisition Value/Currency: 10.000,00 EUR | Acquisition Date: 10.04.2011 |

Customer Warranty

Warranty Start/End: 26.08.2022 | Master Warranty: 1 | General Equipment Terms and Conditions |
 Inherit Warranty: ☒ | Pass On Warranty: ☒ |

Vendor Warranty

Warranty Start/End: 26.08.2022 | Master Warranty: 2000000000 | General Equipment Terms and Conditions |
 Inherit Warranty: ☒ | Pass On Warranty: ☒ |

The following master data information can be maintained here:

- For vendor warranty: Warranty Start date, Acquisition Date, and Master Warranty
- For customer warranty: Customer Warranty start date, Acquisition Date, and Master Warranty

Materials

Within the **Manage Claims** applications, all items within a warranty claim require a material number. Depending on the item type (material, labor or sublet), the material is either a:

- replacement/spare parts (for material positions)
- or a
- service material (for labor and sublet positions)

For further information, refer the standard documentation under [Material Master Record](#).

Procedure

Material records can be accessed through the Fiori application, **Manage Product Master Data**. The role `SAP_BR_PRODMASTER_SPECIALIST` is required to launch the application.

The screenshot shows the SAP Fiori application interface for 'Manage Product Master Data'. The product being viewed is 'Trading Good 0011,PD,Regular Proc.' (TG0011). The navigation bar includes 'Sales', 'Storage', 'Warehouse Management', 'Distribution Chains' (selected), 'Plants', 'Valuation Areas', 'Texts', and 'Attachments'. The 'Plants' section displays a table with 4 plants, all of which are 'Standard' type. The table columns are Plant, MRP Type, MRP Contr..., and Marked for

Plant	MRP Type	MRP Contr...	Marked for ...
Plant 1 DE 1010	Forecast Consumption, No Planning Time Fence (PD)	001	No
New Plant 1020 1020	No planning (ND)		No
New Plant 1030 1030	Forecast Consumption, No Planning Time Fence (PD)	001	No
Plant 1 US 1710	Forecast Consumption, No Planning Time Fence (PD)	001	No

Within the application, spare part and service materials need to be set up with the appropriate organization data (plant/purchasing organization and so on for supplier claim process) or (sales organization for customer claim process). Atleast one service material should be created for labor positions and at least one service material for sublet positions. The service material for the sublet position should be created with a unit of measure that has time relevance (for example, hours).

Returnable Materials

In addition to the above mentioned differentiation, it is also relevant in the claim process to manage of a replacement or spare part should be returned (from customer or to supplier). To initiate the respective mechanism in the claim (change of field *Return part flag* on the item detail page of a claim), the material should be maintained by setting the flag at produt attribute *ten*.

The claim analyst needs to enter product attribute as ten. **Material Master → Sales: Sales Organization 2 → Product attribute 10 is flagged.**

Partner

In the warranty claim process, a partner is used to derive the correct prices, post the amount to account, and identify where the claim statement should be sent.

Partner records can be accessed through the Fiori application [Manage Business Partner](#). The role, `SAP_BR_BUPA_MASTER_SPECIALIST` is required to launch this application.

Business Partner Role	Valid From	Valid To
Customer (Fin. Accounting) FLCU00	26.07.2022	31.12.9999
Customer FLCU01	26.07.2022	31.12.9999
Collections Management UDM000	26.07.2022	31.12.9999

Prerequisites

Within the application, the relevant business partner roles for the supplier and customer claim process should be maintained.

For the customer process,

- Customer role (sales view)
- Customer role F1 (Company code view)
- Customer

- Customer (Fin Accounting)

For the supplier process,

- Customer role (Sales view)
- Customer role F1 (Company code view)
- Vendor role
- Vendor role F1 (Company code view)
- Customer
- Customer (Fin Accounting)
- Supplier (Fin Accounting)

As relevant prerequisite for communication with partners (claim statements, part request), it is mandatory to maintain an email address in the partner information.

i Note

For each supplier (vendor) record, a customer record should be linked to ensure a correct price determination.

Procedure

Maintain Customer Data

1. Log onto the SAP Fiori launchpad with the role, *SAP_BR_BUPA_MASTER_SPECIALIST*.
2. Navigate to the **Manage Business Partner** application.
3. Enter value for business partner and press enter.
4. Select *Customer (Fin Accounting) (defined)* from the **Change in BP Role** dropdown. Then click *Customer: General Data*.
5. Verify the customer number in the respective fields.

Maintain Supplier (Vendor) Data

This procedure is applicable only for supplier claim process.

1. Select *Supplier (Fin Accounting) (defined)* from the **Change in BP Role** dropdown. Then click *Vendor: General Data*.
2. Verify the supplier (vendor) number and customer details in the respective fields.

i Note

For each supplier (vendor) record, a customer record should be linked to ensure a correct price determination. In a scenario wherein customer is not linked, this step needs to be performed.

3. Within the **Output Parameter Determination** page, select the following:
 - Show Rules For: Warranty Claim
 - Determination Step: Email Receipt

Screenshots for reference

Output Parameter Determination

Search in: Apps

▼ Select Business Rules

▼ Maintain Business Rules

Show Rules for:

▼

Determination Step:

▼

Supplier Evaluation Score

Supplier Invoice

Treasury and Risk Management Correspondence

WM Handling Unit

WM Outbound Delivery Order

WM Physical Inventory

WM Warehouse Order

Warranty Claim (Customer)

Warranty Claim (Supplier)

Waste Transportation Document

Output Parameter Determination

Search in: Apps

▼ Select Business Rules

▼ Maintain Business Rules

Show Rules for:

Warranty Claim (Customer)

Determination Step:

Output Type

Edit

Check

Activate

More

▼ Decision Table: DT_OUTPUT_TYPE, Output Type

Export To Excel

Context Overview

Table Contents

Find:

Next

Previous

#	Processing Status	Output Type	Dispatch Time
1	=C020	WARRANTY_CLAIM_CUST_RET_PARTS (Customer Ret...	1 (immediately)
2	=C240	WARRANTY_CLAIM_CUST_REJ_STMNT (Customer CL...	1 (immediately)
3	=C120	WARRANTY_CLAIM_CUST_STMNT (Customer Claim St...	1 (immediately)

Output Parameter Determination

Search in: Apps

▼ Select Business Rules

▼ Maintain Business Rules

Show Rules for:

Warranty Claim (Customer)

Determination Step:

Form Template

Edit

Check

Activate

More

▼ Decision Table: DT_FORM_TEMPLATE, Form Template

Export To Excel

Context Overview

Table Contents

Find:

Next

Previous

#	Output Type	Role
1	=WARRANTY_CLAIM_CUST_RET_PARTS (Customer Return Parts Statement)	=AG
2	=WARRANTY_CLAIM_CUST_REJ_STMNT (Customer Claim Rejection Statement)	=AG
3	=WARRANTY_CLAIM_CUST_STMNT (Customer Claim Statement)	=AG

Select Business Rules
 Show Rules for: Warranty Claim (Supplier) Determination Step: Output Type

Maintain Business Rules
 Edit Check Activate More

Decision Table: DT_OUTPUT_TYPE, Output Type
 Export To Excel Context Overview

Table Contents
 Find: Next Previous

#	Output Type	Dispatch Time
1	WARRANTY_CLAIM (Supplier Claim Statement)	1 (Immediately)

Select Business Rules
 Show Rules for: Warranty Claim (Supplier) Determination Step: Form Template

Maintain Business Rules
 Edit Check Activate More

Decision Table: DT_FORM_TEMPLATE, Form Template
 Export To Excel Context Overview

Table Contents
 Find: Next Previous

#	Output Type	Role	Channel
1	WARRANTY_CLAIM (Supplier Claim Statement)		

4. Click **Maintain Business Rules**.

Note

The email address of receipt must be set up as in step 3. If not, the email address is retrieved from the business partner address data.

Pricing Condition Records

Determining correct prices is a central element within the warranty claim processing. To ensure that the appropriate amount can be claimed from the supplier/payment to the customer, the correct prices need to be set up in the system. Each of the different item types (material, labor, sublet) has its own condition to ensure proper maintenance and relationship to the already existing pricing records.

Material Items

For Supplier Claim Process


Material items derive their value based on the purchasing price (condition PPRO from application M) from procurement into condition PBRO in the claim. To do this, the system uses tables 017 (with attributes, partner/material number/purchasing organization/plant) and 018 (with attributes, partner/material number/purchasing organization) to derive the price from the maintained entries of procurement.

Note

Tables to maintain pricing condition records for material conditions PPRO:

A305 Customer/material with release status

The records can be displayed or maintained with application [Create Condition Records](#) (MEK1). The role, *SAP_BR_PURCHASER* is required to launch this application.



Procedure

1. Log onto the SAP Fiori launchpad with the role, *SAP_BR_PURCHASER*.
2. Navigate to the *Create Condition Records* (MEK1) application from purchasing. The *Display Conditions Record* page displays.
3. Enter *PPRO* as condition type.
4. Select either *Material Info Record* (with attributes partner/material number/purchase organization/plant) or *Material Info Record* (with attributes partner/material number/purchase organization).

Check if entries exist for the relevant partner, material, purchase organization, and plant.

For Customer Claim Process

In the customer process, the material items value is derived from spare part sales prices (condition PPRO from application V) from SD and saved into condition PROO in the claim. This is done with tables A305 (with attributes, customer/material number) and table A304 (only with attribute material number) to derive the price from the maintained entries of sales and distribution. The records can be displayed or maintained with application [Set Material Prices - Sales](#). The role, *SAP_BR_PRICING_SPECIALIST* is required to launch this application.

Procedure

1. Log onto the SAP Fiori launchpad with the role, *SAP_BR_PRICING_SPECIALIST*.
2. Navigate to *Set Material Prices - Sales* application.
The *Display Conditions Record* page displays
3. Enter *PPR0* as condition type.
4. Maintain customer/material and material prices.

Labor

Generally, the labor items are not pre-set up by other departments (for example, sales department) in the system and need to be created by the warranty team. These records need to be set up with the respective service material (as described in section *Materials*). In the claim, these values will be pulled into condition type *PBFO*.

i Note

Tables to maintain Pricing condition records for Labor condition PF00.

A305 Customer/material with release status

A150 Dest. Ctry/Material

A304 Material with release status

The records can be displayed or maintained with the application [Create Pricing Records \(WYP1\)](#). The role, *SAP_BR_MD_SPECIALIST_WRNTY* is required to launch the application.

For Supplier Claim Process

In the claim, the labor values will be pulled into the condition type *PBFO*.

The screenshot shows the SAP Fiori 'Create Condition Records' application. The 'Key Combination' dialog is open, with 'Dependent on material' selected. Below the dialog, a table titled 'Dependent on material' is visible. The table has the following columns: Material, Description, Amount, Unit, per, UoM, C..., S..., Valid From, and Valid To. The first row is highlighted with a red background.

Material	Description	Amount	Unit	per	UoM	C...	S...	Valid From	Valid To

The following information is required:

- Material
- Amount
- Unit
- Per
- UoM

Procedure

1. Log onto the SAP Fiori launchpad with the role, *SAP_BR_CLAIMS_ANALYST_COMPL*, with the name claim analyst.
2. Navigate to Create Pricing Condition Records (WYP1) application. The *Change Conditions Record* page displays.
3. Enter *PBFO* as condition type.
4. Press enter and click **Choose**. The **Create Labor Rate Condition (PBFO): Fast Entry** page displays.
5. Enter the pricing details, as in the following example, and choose **Save**:
 - Material: SRV_01 (This should be your service material for labor).
 - Amount: 50
 - Unit: EUR
 - per: 1
 - UoM: HR

For Customer Claim Process

In the claim, the labor values will be pulled into the condition type, *PFOO*.

Condition Type: PF00

Key Combination

- ☒ Customer/material with release status
- ☐ Dest. Ctry/Material
- ☐ Material with release status

* Sales Organization:

* Distribution Channel:

* Customer:

Select Rule

Customer/material with release status

* Material	S... Description	P... Amount	Unit	per	UoM	C...	S...	Valid From	Valid To
☐									
☐									

The following information is required:

- Material
- Amount
- Unit
- Per
- UoM
- Per:1
- UoM: HR

Procedure

1. Log onto the SAP Fiori launchpad with the role, *SAP_BR_MD_SPECIALIST_WRNTY*, with the name master warranty specialist.
2. Navigate to *Create Pricing Records (WYP1)* application. The *Change Conditions Record* page displays.
3. Enter *PF00* as condition type.
4. Press enter and click **Choose**. The **Create Labor Rate Condition (PF00): Fast Entry** page displays.
5. Select either the customer, material, or destination country.
6. Enter the pricing details, as in the following example, and choose **Save**:
 - Material: SRV_01 (This should be your service material for labor).
 - Amount: 50
 - Unit: EUR
 - per: 1
 - UoM: HR

Pricing condition record *PF00* is created. Maintain condition records for other materials. as mentioned above.

Sublet

Sublet items have no condition where specific records can be maintained to be determined in the claim. For these items, the system always expects a manual input.

i Note

The sublet items are always manually entered in the claim. Therefore, no pricing records need to be set as preliminary step.

Procedure

The procedure is applicable for both the supplier claim process and customer claim process.

The sublet items are entered manually in the warranty claim. Therefore, no pricing records need to be setup as a preliminary step.

Create Master Warranty

- Relevant master data: Organizational details, Supplier, and Material
 - A valid claim should exist
 - The role *SAP_BR_MD_SPECIALIST_WRNTY* should be assigned
1. Log into the application with a registered user
 2. Open the **Manage Master Warranty** application
 3. Create a master warranty without entering any values in the mandatory field
 4. Enter values in the following fields:
 - Description
 - Master Warranty
 - Warranty Type
 - Customer Warranty
 - Vendor/Customer Warranty
 5. Validate item creation, warranty creation without adding the item, match *ALL/ANY* option, and warranty counter without entering warranty counter, description, counter value, and counter unit of measure

Configuration

You require the following configurations in warranty claim processing:


- [General Ledger \(GL\) Accounts](#)
- [Number Ranges](#)
- [Assign Pricing Procedure to Claim Type/Company Code](#)
- [Maintain Claim Rules](#)
- [Actions in Warranty Processing](#)

- [Maintain Claim Rules](#)


General Ledger (GL) Accounts

The claim analyst can configure on which general ledger (GL) accounts the cost to a customer or the revenues from a supplier should be posted. The configuration can be done through the Fiori application.

The user should navigate to **Manage Your Solution** → **Configure Your Solution**.



Choose **Finance** as application area and **General Ledger** as sub application area. The value **Charts of Accounts** should be selected from the list.



Standard

Application Area: 100297

Sub Application Area:

Mandatory: All

Country/Region-Dependent: All

Redo in P System: All

Adapt Filters (6)

All Items (1)

Item Name Status

Chart of Accounts Confirmed

Finance: General Ledger 19 Step(s)

Chart of Accounts

Description	Configuration Steps	Comments				
7. Define Financial Statement Versions	Confirmed Set Status	Recommended	No	102669	Configure	
8. Manage G/L Account Master Data	Confirmed Set Status		No	000000	Configure	
9. Assign Financial Statement Versions to Accounting Principles	Confirmed Set Status	Recommended	No	103215	Configure	
10. Define Semantic Tag Group	Confirmed Set Status	Optional	No	101877	Configure	
11. Define Semantic Tags for Financial Statement Versions	Confirmed Set Status	Recommended	No	101878	Configure	
12. Assign Semantic Tags to Financial Statement Versions	Confirmed Set Status	Optional	No	102659	Configure	
13. Automatic Account Determination	Confirmed Set Status	Mandatory	No	100297	Configure	
14. Create Groups of Bank Areas for In-House Banking Account Determination	Confirmed Set Status	Optional	No	105993	Configure	

SAP Automatic Account Determination

Apps Search in: Apps

1 Area


1. Area

Area:

- Controlling
- Financial Accounting
- Joint Venture Accounting
- Sourcing and Procurement
- Personnel Management
- Sales
- Warranty

When performing the activity **Configure** (with Automatic account determination), the following values should be selected:

- Area: Warranty
- Charts of Accounts: YCOA



The appropriate GL account can now be maintained in relation to the appropriate condition tables. Tables 001, 002, 003, 004, and 005 are to derive accounts in the customer facing process and tables 021 and 022 are to derive accounts in the supplier facing process. The role, [SAP_BR_BPC_EXPERT](#), is required to launch the application and perform the above mentioned steps.

i Note

In a scenario wherein no setup is done, the standard account 65008600 is used as default to post customer costs.

By default, the access sequence KOFI00 (for customer process) and KOFI01 (for supplier process) are set in the system with the following sequence:

KOFI00:

Step	Table
10	001
20	002
30	003
40	005
50	004

KOFI01

Step	Table
10	021
20	022

You can also define through SPRO [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Warranty Claim](#) → [Revenue Accounting](#) → [Define Access Sequence](#). and assign through SPRO [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Define Warranty Claim Type](#) different or own access sequence.

Prerequisites

- Automatic account assignment must have the required cost center maintained.

Navigate through SPRO → [Controlling](#) → [Internal Orders](#) → [Actual Postings](#) → [Maintain Automatic Account Assignment](#)

Procedure

This procedure is applicable only for the supplier claim process.

- Log onto the SAP system.
- Navigate to the [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Revenue Account Determination](#) → [Assign GL Accounts](#).
- Click [Assign G/L Accounts](#).
- Choose the following:
 - Area: Warranty from the dropdown
 - Chart of Accounts: YCOA
 - Condition Tables: 001, 002, 003, 004, 005, 021, and 022

Number Ranges

Each claim has a unique identification (claim) number. To ensure the uniqueness and to provide the possibility to differentiate claims (for example, by type), there can be number ranges set up or assigned to the different claims.

The configuration of number ranges consist of the following activities:

- [Define Number Ranges for Warranty Claims](#)
- [Assign Number Ranges to Claim Types](#)

Define Number Ranges for Warranty Claims

The configuration can be done through the Fiori application.

The user can view all existing number ranges and which of them are already in use (including the latest assigned number).

i Note

The assignment of numbers within the interval is always done by the SAP system (no external number assignment is allowed).

	Number Range No.	From Number	To Number	Number Range Status	External
☐	01	000000000001	200000000000	10	☐
☐	02	200000000001	500000000000	200000000030	☐
☐					

Navigate to [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Define Number Ranges for Warranty Claims](#).

Without number ranges, it is not possible to create any warranty claims.

- Internal number assignment

Here, a number within the number range interval allowed is assigned by the SAP system.

i Note

External number ranges are not supported.


How to Define Number Ranges

1. In your configuration environment, use the search function to open the activity: [Define Number Ranges for Warranty Claims](#)
2. In the [warranty claim](#) view, create, edit and delete number range intervals.

Assign Number Ranges to Claim Types

The configuration can be done through the Fiori application.

The user should navigate to [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Assign Number Ranges to Claim Type](#).



	WtyClnType	Description Claim Type	NR
☐	1C01	Pre-Credit Process Claim	02
☐	1S01	Supplier-Facing Claim	01
☐			

The user can view all claim types for the Fiori application [Manage Claims](#) and to which number ranges they are already assigned. The user can select an existing claim type and change the existing assignment or assign a number range (for the first time), if the field is empty.


i Note

For claim types that have no number range assigned, it is not possible to create any claim in the [Manage Claims](#) application.

Assign Pricing Procedure to Claim Type/Company Code

Prices (and in particular taxes) can be different in each country. In addition, the price determination is different for claims from a customer and claims addressed towards a supplier. To ensure that the right price is available with regards to respective process and country, the warranty claim key can define different pricing procedures that can be used.

The configuration can be done through a Fiori application. The user can view all the existing assignments or pricing procedures per country and warranty claim process (from customer/towards supplier). The user can add, edit, or remove entries to maintain the appropriate configuration.



	WtyCltmType	WtyProc	CoCd	Proced	Validity
☐	1C01	C Claimant	1010	A10A01	Valid
☐	1C01	C Claimant	1710	A17A01	Valid
☐	1S01	V Reimburer	1010	A10B01	Valid
☐	1S01	V Reimburer	1710	A17B01	Valid

Navigate to [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Assign Pricing Procedure to Claim Type/Company Code](#).

The pricing procedure is assigned to the claim type, warranty process (claimant or reimburer), and the company code. For this, the company code should be defined and there should be valid claim type.

How to Assign Pricing Procedure

1. In your configuration environment, use the search function to open the activity: [Assign Pricing Procedure to Claim Type/Company Code](#).
2. In the [Maintenance View for Country Based Pricing](#) view, check the validity of claim type and company code.

Actions in Warranty Processing

Actions are the building blocks within the warranty processes. With the implementation of scope items, standard contents are delivered. As of now, there are no self service configuration user interface (SSCUIs).

There are two types of actions:

- Elementary actions are the smallest entity to execute one logical transaction completely, for example post claim to finance. In the standard settings, these actions are set to *not visible*.
- Interlinking actions contain one or many elementary actions or interlinking actions. In the standard settings, these actions are set to *visible* as they support the automatic claim processing.

The action matrix defines list of all actions to be performed along with their corresponding source and target statuses (and also target error status).

Standard Naming Conventions

- 1st Digit: "V" (For Supplier process) or "C" (For Customer process)
- 2nd Digit: "1" (For Elementary action) or "2" (For Interlinking actions)
- 3rd and 4th digit: Free usage to provide hort meaningful insights what the action code does

For example:

1. V1CL : Elementary action to close supplier claims
2. C2FP: Interlinking action to do finance posting of customer claims

i Note

Actions or action codes created by customers should be set up in the customer namespace to prevent potential issues with delivered content in later releases.

Related Information

[Set up of Standard Actions for Customer Processes](#)

[Set up of Standard Actions for Supplier Processes](#)

Set up of Standard Actions for Customer Processes

To make the customer process run in the [Manage Claims](#) application, the relevant statuses, actions, and action matrix (to link status and actions) should be set up. With the implementation of scope item 63Y, all the relevant contents will be loaded into the below mentioned tables.

If required, the warranty claim key user can find the configuration:

- Define Actions: [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Warranty Claim](#) → [Control Data](#) → [Define Actions](#)
- Define Status: [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Warranty Claim](#) → [Control Data](#) → [Define Status](#)

Processing Statuses						
PrsStatus	Description of Process. Status	Category	Migration Status	Focus Status	Processing Status Classification	
C010	Created	IC Incoming Customer (IC)	☐	☐	IN Initial	
C015	Discarded	IC Incoming Customer (IC)	☐	☐	CL Closed	
C020	Submitted	IC Incoming Customer (IC)	☐	☒		
C025	Additional Information Requested	IC Incoming Customer (IC)	☐	☒		
C030	Error in Formal Validation	IC Incoming Customer (IC)	☐	☒		
C040	Formal Validation Successful	IC Incoming Customer (IC)	☐	☐		
C060	Ready for Content Validation	OC Outgoing Customer (OC)	☐	☐		
C070	Error in Content Validation	OC Outgoing Customer (OC)	☐	☒		
C080	Content Validation Successful	OC Outgoing Customer (OC)	☐	☐		
C120	Claim Posted	OC Outgoing Customer (OC)	☐	☐		
C200	Claim Posted and Closed	OC Outgoing Customer (OC)	☐	☐	CL Closed	
C240	Claim Rejected	OC Outgoing Customer (OC)	☐	☐		
C300	Claim Rejected and Closed	OC Outgoing Customer (OC)	☐	☐	CL Closed	
C900	Claim Closed (Migrated)	OC Outgoing Customer (OC)	☒	☐	CL Closed	
S010	Created	OV Outgoing Vendor (OV)	☐	☒	IN Initial	
S030	Error in Validation	OV Outgoing Vendor (OV)	☐	☒		
S040	Successfully Validated	OV Outgoing Vendor (OV)	☐	☐		
S080	Waiting for Supplier Response	OV Outgoing Vendor (OV)	☐	☒		
S100	Supplier Response Received	IV Incoming Vendor (IV)	☐	☐		
S120	Posted to Finance	IV Incoming Vendor (IV)	☐	☐		
S200	Claim Posted and Closed	IV Incoming Vendor (IV)	☐	☐	CL Closed	
S220	Claim Cancelled	IV Incoming Vendor (IV)	☐	☐	CL Closed	
S240	Claim Rejected	IV Incoming Vendor (IV)	☐	☐		
S300	Claim Rejected and Closed	IV Incoming Vendor (IV)	☐	☐	CL Closed	
S900	Claim Closed (Migrated)	IV Incoming Vendor (IV)	☒	☐	CL Closed	

- Define Action Matrix: [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Warranty Claim](#) → [Control Data](#) → [Define Action Control](#)

"Define Action Controls": Display

Action Code	Action Type	Description of Action Code
C1CL	T Elementary Action Hidden i.	Close Claim
C1DC	T Elementary Action Hidden i.	Discard Claim
C1FP	T Elementary Action Hidden i.	Post to Finance
C2AD	A Interlinking Action Displa.	Adjust Claim
C2CI	A Interlinking Action Displa.	Complete Inbound Process
C2CL	A Interlinking Action Displa.	Close Claim
C2DC	A Interlinking Action Displa.	Discard Claim
C2FP	A Interlinking Action Displa.	Post to Finance
C2IP	A Interlinking Action Displa.	Information Provided
V1FP	T Elementary Action Hidden i.	Post To Finance
V1RE	T Elementary Action Hidden i.	Reprocess Claim
V1RJ	T Elementary Action Hidden i.	Reject Claim
V1RO	T Elementary Action Hidden i.	Reopen Claim
V1RR	T Elementary Action Hidden i.	Maintain Supplier Response
V1RV	T Elementary Action Hidden i.	Reverse Posted Claim
V1SS	T Elementary Action Hidden i.	Validate Claim
V1VC	T Elementary Action Hidden i.	Validate Claim
V2AD	A Interlinking Action Displa.	Adjust Claim
V2CA	A Interlinking Action Displa.	Cancel Claim
V2CL	A Interlinking Action Displa.	Close Claim
V2FP	A Interlinking Action Displa.	Post to Finance
V2RE	A Interlinking Action Displa.	Reprocess Claim

i Note

There are no Self-Service Configuration User Interface (SSCUI) available as of this release, to manage the action control. Standard packaged content is available to execute the claim process.

Navigate to

Define Actions

As part of the standard content of scope item 63Y, the below interlinking and elementary actions along with their grouping is packaged:

Action	Interlinking Action Description	Sequence Entry	Elementary Action	Elementary
C2DC	Discard Claim	10	C1DC	Discard Claim
C2RI	Request Additional Information	10	C1RI	Request Additional Information
C2IP	Information Provided	10	C1IP	Information Provided
C2AD	Adjust Claim	10	C1AD	Adjust Claim
C2RJ	Reject Claim	10	C1RJ	Reject Claim

Action	Interlinking Action Description	Sequence Entry	Elementary Action	Elementary
C2RV	Reverse Posting	10	C1RV	Reverse Posting
C2CL	Close Claim	10	C1CL	Close Claim
C2FP	Post to Finance	10	C1FP	Post to Finance
C2AC	Accept Claim	10	C1AC	Accept Claim
		20	C2FP	Post to Finance
C2VC	Content Validation	10	C1VC	Content Validation
		20	C2FP	Post to Finance
C2CI	Complete Inbound Process	10	C1CI	Complete Inbound Process
		20	C2VC	Content Validation
C2VF	Formal Validation	10	C1VF	Formal Validation
		20	C2CI	Complete Inbound Process
C2RE	Reprocess Claim	10	C1RC	Claim Reprocessing Content
		20	C1RF	Claim Reprocessing Formal
C2RO	Reopen Claim	10	C1RO	Reopen Claim

Define Action Controls

As part of standard content of scope item 63Y, the action matrix *CUSI* is packaged.

Start Status	Action	Target Status (Success)	Target Status (Error)
C010 [Created]	C1DC [Discard Claim]	C015 [Discarded]	
C010 [Created]	C1VS [Validate on Submit]	C020 [Submitted]	
C020 [Submitted]	C1RI [Request Additional Information]	C025 [Additional Information Requested]	
C020 [Submitted]	C1VF [Formal Validation]	C040 [Formal Validation Successful]	C030 [Error in Formal Validation]
C020 [Submitted]	C1RP [Request Return Part]	C020 [Submitted]	
C025 [Additional Information Requested]	C1IP [Information Provided]	C020 [Submitted]	
C030 [Error in Formal Validation]	C1RI [Request Additional Information]	C025 [Additional Information Requested]	
C030 [Error in Formal Validation]	C1VF [Formal Validation]	C040 [Formal Validation Successful]	

Start Status	Action	Target Status (Success)	Target Status (Error)
C030 [Error in Formal Validation]	C1AD [Adjust Claim]	C020 [Submitted]	
C030 [Error in Formal Validation]	C1RP [Request Return Part]	C030 [Error in Formal Validation]	
C030 [Error in Formal Validation]	C1RJ [Reject Claim]	C240 [Claim Rejected]	
C040 [Formal Validation Successful]	C1CI [Complete Inbound Process]	C060 [Ready for Content Validation]	
C040 [Formal Validation Successful]	C1RP [Request Return Part]	C040 [Formal Validation Successful]	
C060 [Ready for Content Validation]	C1VC [Content Validation]	C080 [Content Validation Successful]	C070 [Error in Content Validation]
C060 [Ready for Content Validation]	C1RP [Request Return Part]	C060 [Ready for Content Validation]	
C070 [Error in Content Validation]	C1VC [Content Validation]	C080 [Content Validation Successful]	
C070 [Error in Content Validation]	C1AC [Accept Claim]	C080 [Content Validation Successful]	
C070 [Error in Content Validation]	C1RJ [Reject Claim]	C240 [Claim Rejected]	
C070 [Error in Content Validation]	C1RP [Request Return Part]	C070 [Error in Content Validation]	
C080 [Content Validation Successful]	C1RP [Request Return Part]	C080 [Content Validation Successful]	
C120 [Claim Posted]	C1RV [Reverse Posting]	C080 [Content Validation Successful]	
C120 [Claim Posted]	C1CL [Close Claim]	C200 [Claim Posted and Closed]	
C240 [Claim Rejected]	C1CL [Close Claim]	C300 [Claim Rejected and Closed]	
C070 [Error in Content Validation]	C1RF [Claim Reprocessing Formal]	C030 [Error in Formal Validation]	
C240 [Claim Rejected]	C1RC [Claim Reprocessing Content]	C070 [Error in Content Validation]	
C200 [Claim Posted and Closed]	C1RO [Reopen Claim]	C120 [Claim Posted]	
C300 [Claim Rejected and Closed]	C1RO [Reopen Claim]	C240 [Claim Rejected]	
C060 [Ready for Content Validation]	C1SP [Initiate Supplier Process]		

Start Status	Action	Target Status (Success)	Target Status (Error)
C010 [Created]	C2DC [Discard Claim]	C015 [Discarded]	
C010 [Created]	C2VS [Validate on Submit]	C120 [Claim Posted]	
C020 [Submitted]	C2RI [Request Additional Information]	C025 [Additional Information Requested]	
C020 [Submitted]	C2VF [Formal Validation]	C120 [Claim Posted]	
C020 [Submitted]	C2RP [Request Return Part]	C020 [Submitted]	
C025 [Additional Information Requested]	C2IP [Information Provided]		
C030 [Error in Formal Validation]	C2RI [Request Additional Information]	C025 [Additional Information Requested]	
C030 [Error in Formal Validation]	C2VF [Formal Validation]	C120 [Claim Posted]	
C030 [Error in Formal Validation]	C2AD [Adjust Claim]	C020 [Submitted]	
C030 [Error in Formal Validation]	C2RP [Request Return Part]	C030 [Error in Formal Validation]	
C030 [Error in Formal Validation]	C2RJ [Reject Claim]	C240 [Claim Rejected]	
C040 [Formal Validation Successful]	C2CI [Complete Inbound Process]	C120 [Claim Posted]	
C040 [Formal Validation Successful]	C2RP [Request Return Part]	C040 [Formal Validation Successful]	
C060 [Ready for Content Validation]	C2VC [Content Validation]	C120 [Claim Posted]	
C060 [Ready for Content Validation]	C2RP [Request Return Part]	C060 [Ready for Content Validation]	
C070 [Error in Content Validation]	C2VC [Content Validation]	C120 [Claim Posted]	
C070 [Error in Content Validation]	C2AC [Accept Claim]	C120 [Claim Posted]	
C070 [Error in Content Validation]	C2RJ [Reject Claim]	C240 [Claim Rejected]	
C070 [Error in Content Validation]	C2RP [Request Return Part]	C070 [Error in Content Validation]	
C080 [Content Validation Successful]	C2FP [Post to Finance]	C120 [Claim Posted]	
C080 [Content Validation Successful]	C2RP [Request Return Part]	C080 [Content Validation Successful]	

Start Status	Action	Target Status (Success)	Target Status (Error)
C120 [Claim Posted]	C2RV [Reverse Posting]	C080 [Content Validation Successful]	
C120 [Claim Posted]	C2CL [Close Claim]	C200 [Claim Posted and Closed]	
C200 [Claim Posted and Closed]	C2CL [Close Claim]	C300 [Claim Rejected and Closed]	
C240 [Claim Rejected]	C2RE [Reprocess Claim]	C030 [Error in Formal Validation]	
C200 [Claim Posted and Closed]	C2RO [Reopen Claim]	C120 [Claim Posted]	
C300 [Claim Rejected and Closed]	C2RO [Reopen Claim]	C240 [Claim Rejected]	

Related Information

[Actions in Warranty Processing](#)

Set up of Standard Actions for Supplier Processes

To make the supplier process run in the Manage Claims application, the relevant statuses, actions and action matrix (to link status and actions) should be set up. With the implementation of scope item 5HR, all the relevant contents are loaded into the below mentioned tables.

If required, the warranty claim key user can find the configuration:

- Define Actions: SPRO → [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Warranty Claim](#) → [Control Data](#) → [Define Action](#).
- Define Status: SPRO → [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Warranty Claim](#) → [Control Data](#) → [Define Status](#).
- Define Action Matrix: SPRO → [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Warranty Claim](#) → [Control Data](#) → [Define Action Control](#).

i Note

There are no Self-Service Configuration User Interface (SSCUI) available as of this release, to manage the action control. Standard packaged content is available to execute the claim processes.

Define Actions

As part of standard content of scope item 5HR, the below interlinking and elementary actions along with their grouping is packaged:

Action	Sequence Number	Elementary Action	Elementary Action Description
V2CL	10	V1CL	Close Claim

Action	Sequence Number	Elementary Action	Elementary Action Description
V2RV	10	V1RV	Reverse Posted Claim
V2FP	10	V1FP	Post to Finance
V2RJ	10	V1RJ	Reject Claim
V2CA	10	V1CA	Cancel Claim
V2AD	10	V1AD	Adjust Claim
V2VC	10	V1VC	Validate Claim
	20	V2SS	Send to Supplier
V2SS	10	V1SS	Send to Supplier
V2RR	10	V1RR	Maintain Supplier Response
V2RO	10	V1RO	Reopen Claim
V2RE	10	V1RE	Reprocess Claim

Define Action Controls

As part of standard content of scope item 5HR, the action matrix *SUP1* is packaged.

Start Status	Action	Target Status (Success)	Target Status (Error)
S010 [Created]	V1VC [Validate Claim]	S040 [Successfully Validated]	S030 [Error in Validation]
S030 [Error in Validation]	V1VC [Validate Claim]	S040 [Successfully Validated]	
S030 [Error in Validation]	V1AD [Adjust Claim]	S010 [Created]	
S010 [Created]	V1CA [Cancel Claim]	S220 [Claim Cancelled]	
S030 [Error in Validation]	V1CA [Cancel Claim]	S220 [Claim Cancelled]	
S040 [Successfully Validated]	V1CA [Cancel Claim]	S220 [Claim Cancelled]	
S040 [Successfully Validated]	S040 [Successfully Validated]	S080 [Waiting for Supplier Response]	
S080 [Waiting for Supplier Response]	V1RR [Maintain Supplier Response]	S100 [Supplier Response Received]	
S100 [Supplier Response Received]	V1RJ [Reject Claim]	S240 [Claim Rejected]	
S100 [Supplier Response Received]	V1FP [Post To Finance]	S120 [Posted to Finance]	
S120 [Posted to Finance]	V1RV [Reverse Posted Claim]	S100 [Supplier Response Received]	
S120 [Posted to Finance]	V1CL [Close Claim]	S200 [Claim Posted and Closed]	

Start Status	Action	Target Status (Success)	Target Status (Error)
S240 [Claim Rejected]	V1CL [Close Claim]	S300 [Claim Rejected and Closed]	
S200 [Claim Posted and Closed]	V1RO [Reopen Claim]	S120 [Posted to Finance]	
S300 [Claim Rejected and Closed]	V1RO [Reopen Claim]	S240 [Claim Rejected]	
S240 [Claim Rejected]	V1RE [Reprocess Claim]	S100 [Supplier Response Received]	
S010 [Created]	V2VC [Validate Claim]	S080 [Waiting for Supplier Response]	
S030 [Error in Validation]	V2VC [Validate Claim]	S080 [Waiting for Supplier Response]	
S010 [Created]	V2CA [Cancel Claim]	S220 [Claim Cancelled]	
S030 [Error in Validation]	V2CA [Cancel Claim]	S220 [Claim Cancelled]	
S040 [Successfully Validated]	V2CA [Cancel Claim]	S220 [Claim Cancelled]	
S040 [Successfully Validated]	V2SS [Send to Supplier]	S080 [Waiting for Supplier Response]	
S080 [Waiting for Supplier Response]	V2RR [Maintain Supplier Response]	S100 [Supplier Response Received]	
S100 [Supplier Response Received]	V2RJ [Reject Claim]	S240 [Claim Rejected]	
S100 [Supplier Response Received]	V2FP [Post to Finance]	S120 [Posted to Finance]	
S120 [Posted to Finance]	V2RV [Reverse Posting]	S100 [Supplier Response Received]	
S120 [Posted to Finance]	V2CL [Close Claim]	S200 [Claim Posted and Closed]	
S240 [Claim Rejected]	V2CL [Close Claim]	S300 [Claim Rejected and Closed]	
S200 [Claim Posted and Closed]	V2RO [Reopen Claim]	S120 [Posted to Finance]	
S300 [Claim Rejected and Closed]	V2RO [Reopen Claim]	S240 [Claim Rejected]	
S240 [Claim Rejected]	V2RE [Reprocess Claim]	S100 [Supplier Response Received]	

Maintain Claim Rules


A central element of the claim process is the validation. The solution design foresees multiple (validation) points in the claim process where rules can be called to validate a claim. For each of these validated points, it can be defined which rules should be executed. This indicates that the same rules (or set of rules) can be executed even multiple times within the process flow or a claim.

The warranty claim key users can access the configuration through SPRO → [Plant Maintenance and Customer Service](#) → [Warranty Claim Management](#) → [Warranty Claim Processing\(Fiori\)](#) → [Warranty Claim](#) → [Control Data](#) → [Rule Control](#) → [Maintain Claim Rules](#).


In this configuration, the user can view all the existing entries.

These entries consist of:

- 1. Validation point: As mentioned above, these are points where validations are triggered. As part of scope item 63Y (for customer facing process), the validation points *Validation on claim submission*, *Formal validation*, and *Content validation* are delivered. As part of scope item 5HR, for supplier facing process, the validation point *Validation for supplier outbound process* is delivered.



- 2. Rule Groups: Multiple rules can be grouped under a *Rule Group*. These groups are then assigned to a validation point.



- 3. Rules: The rule represent the real check. Rules can be assigned to one or many rule groups. For each rule individually, an activation status (draft, inactive, or active) can be set.

i Note

If a rule is applied in multiple rule groups which are all assigned to the same validation point, the rule is only executed once.

Rule Name	Rule Description	Resultchk	Validity
☐ SAP_CLAIM_ITEM_EXISTENCE_CHECK	Validate item existence in claim	SP Stop Claim Processing on Error	Valid
☐ SAP_CLAIM_PERSON_RESPONSIBLE_CHECK	Validate person responsible	CP Continue Claim Processing on E...	Valid
☐ SAP_CLAIM_REQUESTED_AMOUNT_CHECK	Validate requested claim amount	SP Stop Claim Processing on Error	Valid
☐ SAP_CUSTOMER_ORG_DATA_CHECK	Validate customer organization data	SP Stop Claim Processing on Error	Valid
☐ SAP_DAMAGE_DATE_ORDER_CHECK	Validate damage date	SP Stop Claim Processing on Error	Valid
☐ SAP_MATERIAL_VOM_CHECK	Validate unit of measure	SP Stop Claim Processing on Error	Valid
☐ SAP_PARTS_CAUSING_DAMAGE_CHECK	Validate existence of part causing damage	SP Stop Claim Processing on Error	Valid
☐ SAP_REFERENCE_OBJECT_DATA_CHECK	Validate object data assigned to claim	SP Stop Claim Processing on Error	Valid
☐ SAP_REPAIR_DATE_ORDER_CHECK	Validate repair date	SP Stop Claim Processing on Error	Valid
☐ SAP_SUPPL_CLAIM_PERSON_RESPONSIBLE_CHECK	Validate person responsible (Supplier)	CP Continue Claim Processing on E...	Valid
☐ SAP_SUPPLIER_ORG_DATA_CHECK	Validate supplier organization data	SP Stop Claim Processing on Error	Valid
☐ SAP_WARRANTY_ASSIGNMENT_CHECK	Validate master warranty assignment	SP Stop Claim Processing on Error	Valid
☐ SAP_WARRANTY_COVERAGE_CHECK	Validate warranty terms and conditions of assigned object	SP Stop Claim Processing on Error	Valid

Processes

The following processes are supported in warranty claim management:


- [Supplier-Facing Warranty Claims](#)
- [Customer-Facing Warranty Claims](#)

Supplier-Facing Warranty Claims

The **Manage Supplier Claims** application enable users to create warranty claims that are forwarded to suppliers for reimbursement. This includes the creation of supplier claims (based on repairs), the validation for completeness and eligibility for reimbursement and determining the correct prices (for example materials, labor tasks) to claim the appropriate amount.

Once the supplier responds, the application supports the transparent maintenance of values and posting of the negotiated amount.

The following image explains the entire warranty claim processing




Customer-Facing Warranty Claims

The Manage Customer Claims application enables you to create a warranty claim on behalf of a customer, which are validated and appropriately paid. The scenario covers the relevant steps starting with the creation of a claim (based on performed repair), continuing with the validation for completeness, eligibility for reimbursement, and identifying the correct prices for material, labor tasks, and so on.

The scenario supports the transparent maintenance of values and reimbursement of amount to the customer and is based on the supported and performed validations.

The following image explains the entire warranty claim processing.



Application(s)

- [Manage a Supplier Claim](#)
- [Manage a Customer Claim](#)
- [Manage a Master Warranty](#)
- [Overview of Supplier Claims](#)
- [Overview of Customer Claims](#)

Manage a Supplier Claim

With the *Manage Supplier Claims* application, you can create warranty claims that are forwarded to the suppliers for reimbursement. This includes creating supplier claims (based on repairs), validating claims for completeness and eligibility for reimbursement, and determining correct prices (for example materials, labor tasks) to claim the appropriate amount. Once the supplier responds, the application supports the transparent maintenance of values and posting of the negotiated

A warranty claim is a claim for reimbursement of material and labor costs that are incurred for the purpose of rectifying faults in an object with a valid warranty.

Key Features

A claim analyst can use this application to do the following:

- [Create a Supplier Claim](#)
- [Edit a Supplier Claim](#)
- [Validate a Supplier Claim](#)
- [Send a Claim to Supplier](#)
- [Adjust a Supplier Claim](#)
- [Record Supplier Response](#)
- [Post Supplier Claim to Finance](#)
- [Reverse Posted Supplier Claim](#)
- [Cancel a Supplier Claim](#)
- [Reject a Supplier Claim](#)
- [Reprocess a Supplier Claim](#)
- [Close a Supplier Claim](#)
- [Reopen a Supplier Claim](#)

Supported Device Types

- Desktop
- Tablet
- Smartphone

Create a Supplier Claim

As a claim analyst, you can use the below procedure to create a claim to send to supplier for reimbursement. The newly created claim is considered as the outgoing vendor (OV) version.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorization to perform the task.

Procedure

1. Launch the **Manage Supplier Claims** application from the launchpad.
2. Choose **Create**.
3. In the **Partner and Repair Details** section, maintain information for the following:
 - a. Supplier
 - b. Object Type
 - c. Object Number
 - d. Damage Date
 - e. Repair date

i Note

These are mandatory fields.

4. In the **Additional Details** section, maintain information for the following:
 - a. Plant
 - b. Purchasing Organization
 - c. Distribution Channel
 - d. Division
 - e. Currency

i Note

These are mandatory fields

5. In the **Item Information** section, create atleast an item to the warranty claim. Choose:
 - Material
 - Quantity
 - Part Causing Damage: Atleast one item should be set as the part that is causing damage. For more informtion, refer [Validate a Supplier Claim](#).

i Note

In case a part needs to be returned, the respective parts return status is automatically set. The status can also be set manually using the [Return Parts Status](#) field or marked to shipped in case the shipment is already done. This is possible only for the *Mat (material)* item type.

6. Choose **Create**.

Edit a Supplier Claim

A claim analyst can use this procedure to edit a supplier claim.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorization to perform the task.

Procedure

1. Launch the [Manage Supplier Claims](#) application from the Launchpad.

i Note

You can edit newly or already created claim from the list.

2. Choose **Edit**.

The details of the selected claim displays.

3. Depending on the processing status of the warranty claim, respective fields can be edited.

- For the status, *Created*, all the fields can be edited
- For the status, *Posted to Finance*, only comments can be saved

4. Choose **Save**.

Validate a Supplier Claim

A warranty claim is validated for completeness and checked if eligible for reimbursement before sending to the supplier.

Prerequisites

- The claim analyst have the necessary role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorization to perform the task.
- A valid claim with all the mandatory fields is available. A person responsible and atleast details of one item should be available within the claim. For more information, refer [Create a Supplier Claim](#)

Procedure

1. Select a warranty claim from the list with the processing status **Created**.
2. Choose **Validate**.
3. Claim is validated for the following parameters:
 - Damage Date

i Note

This date should be:

- after the warranty start date
- on or before the repair date

- Repair Date

i Note

This date should be:

- after the warranty start date
- on or before the repair end date
- after the damage date

- Person Responsible: An email should be maintained for the person responsible in the partner master. An email is required to ensure proper communication in the further steps of processing warranty claims.
- Item: At least one item should be added to the claim
- Part Causing Damage: At least one item should be set as the part that is causing damage. This is applicable only for items of item type, *MAT (Material)*.

i Note

- If there is one or multiple items within a claim, at least one of them must be flagged as *Part Causing Damage*.
- In a scenario wherein no item is flagged or if multiple items are flagged, an error message displays

4. Choose **Validate**. You must perform validation through the rule engine.

The details of rules within the individual groups are as provided in [Rules for Supplier](#).

- If all the above defined parameters are met, then the claim status changes to *Successfully Validated*. The claim can be send to the supplier. For more information, refer [Send a Claim to Supplier](#)
- If any of the defined parameters are not met, then the status of claim displays as *Error in Validation*. The error messages are visible within the **View Alerts** pop up.

i Note

Please note that the descriptions specifically explain what is done / happens in the individual process steps. The scope item (as a whole) is set up to support process automation. This means that when a process step is successfully executed, the succeeding process step is directly initiated / performed. Therefore, it is possible that the claim status is set to *Waiting for supplier response* as succeeding steps could be successfully executed as part of this automation.

Rules for Supplier

You can find below details of rule within the individual groups:

Validation Point	Group	Rules
S10 Validation point for supplier outbound check	SAP_SUPPLIER_DATA_FORMAT_CHECK	- CLAIM_ITEM_EXISTANCE_CHECK - SUPPLIER_CLAIM_PERSON_RESPONSIBLE_CHECK - CLAIM_REQUESTED_AMOUNT_CHECK - MATERIAL_UOM_CHECK - PARTS_CAUSING_DAMAGE_CHECK
S10 Validation point for supplier outbound check	SAP_SUPPLIER_DATE_CHECK	- DAMAGE_DATE_ORDER_CHECK - REPAIR_DATE_ORDER_CHECK
S10 Validation point for supplier outbound check	SAP_SUPPLIER_MASTER_DATA_CHECK	- WARRANTY_ASSIGNMENT_CHECK - REFERENCE_OBJECT_DATA_CHECK - SUPPLIER_ORG_DATA_CHECK
S10 Validation point for supplier outbound check	SAP_SUPPLIER_WARRANTY_CHECK	WARRANTY_COVERAGE_CHECK

Send a Claim to Supplier

A claim analyst can use this procedure to send a validated claim to supplier for their response.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorization to perform the task.
- A successfully validated claim is available. For more information, refer [Validate a Supplier Claim](#)

i Note

The email address of receipt needs to be maintained within the *Output Parameter Determination* page. If not, the email address is retrieved from the business partner address data.

- In case parts need to be returned, the shipment of parts should be done before the claim is sent to the supplier.

Procedure

1. Launch the [Manage Supplier Claims](#) application on the launchpad.
2. Search for a claim with the status *Validated*.
3. Click the supplier claim from the list to view the details.

i Note

In a scenario wherein you want to return a damaged part, use the *Return Parts Status* option. The status must be maintained as *parts shipped* or *no parts to be returned*. If you maintain the status as *parts to be returned*, then an error message displays. This step is only applicable for items of item type *MAT*.

4. Choose **Send to Supplier**. The claim status changes to *Waiting for Supplier Response*.

5. Navigate to the **Output Management** tab.

The claim output as email and in pdf format should be visible in this tab. You should be able to open the pdf.

The email address is configured in the master data. For more information, refer [Partner](#)

6. Verify the email contents, for example, repair data, damage date, or item information.

Adjust a Supplier Claim

As a claim analyst, you can adjust details or requested amount within the warranty claim, before sending to the supplier.

Once a claim passed the successful validation, it is not possible to change or update the data. If a claim analyst wants to adjust any data, the **Edit** option can be used or choose to adjust the claim. On adjusting a claim, the processing status of the respective claim changes to **Created**.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorization to perform the task.
- A successfully validated claim is available. For more information, refer [Validate a Supplier Claim](#)

Procedure

1. Launch the **Manage Supplier Claims** application on the launchpad.
2. Search for a claim with the status *Validated*.
3. Select the supplier claim from the list to view the details.
4. Choose *Edit*. You should be able to edit or changes values in the fields, *Decision*, *Header Note*, *Version Note*, and *Attachments*.
5. Then, choose **Adjust Claim**.

In the displayed pop up, confirm. The processing status of the claim changes to *Created*. You should be able to edit the claim contents as mentioned in [Edit a Supplier Claim](#)

Record Supplier Response

Once a supplier responds to the warranty claim, the claim analyst should maintain the information such as the approved amount within the claim.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorization to perform the task.

- A validated claim, awaiting supplier response is available. For more information, refer [Validate a Supplier Claim](#) and [Send a Claim to Supplier](#)

Procedure

1. Launch the **Manage Supplier Claims** application from the Launchpad.
2. Search for a claim with the processing status *Waiting for Supplier Response*.
3. Choose **Maintain Supplier Response**.

The processing status changes to *Supplier Response Received*.

4. Depending on the supplier response, do the following:
 - In a scenario wherein the supplier approves the claim, then set the decision code of version to *Approved*.
 - In a scenario wherein the supplier approves the claim partially, you can maintain the supplier's response at the overall claim level or individually for each of the items.
 - Item level: Respective items must be adjusted. In the detailed page of the item, enter amount and currency. Below condition types are automatically inserted based on the item type:
 - PBRS: material
 - PBFS: labor
 - PBSS: sublet

In addition, check the updated or changed amount within the *Pricing Information* section and document header. Also, set the decision of version to *Approved Partially*. For more information, refer [Post Supplier Claim to Finance](#)

 - Overall claim level: Set the condition **PTSU** in the version grid.
 - In a scenario wherein the supplier rejects the claim, then set the decision code of version to *Rejected*.
5. Within the **Additional Details** tab, the version category displays as Incoming Vendor (IV) and version number to 2.
6. Within the **Versions** tab, the two versions, the outgoing vendor and incoming vendor versions display. Click each version to view further details such as the pricing, notes, and items.
7. The process flow displays both the versions, outgoing vendor, and incoming vendor.
8. Choose **Save**

The respective approved value displays in the header. If the claim is approved, then the approved amount should display the same value as the requested amount. If the claim amount is rejected, the approved amount within the header should be 0.

Post Supplier Claim to Finance

Once the supplier response to the claim is maintained and the reimbursement of amount is considered, the claim can be posted.

A claim analyst can use the below procedure:

Prerequisites

- The claim analyst have the role, **SAP_BR_CLAIMS_ANALYST_COMPL** assigned and necessary authorization to perform the task.

- A claim to which supplier has responded is available. The response from the supplier needs to be approved or partially approved. For more information, refer [Record Supplier Response](#)

Procedure

1. Launch the **Manage Supplier Claims** application from the Launchpad.
2. Search for claim with processing status *Supplier Response Received*.
3. Select the claim the view further details. The *Edit*, *Reject Claim*, and *Post to Finance* options displays on the page.
4. Choose **Post to Finance**.

In case the claim has a decision *Rejected*, the message *version (x) not approved* displays in the *View Alerts* popup.

i Note

- Accounting document linked to the incoming version (IV) displays in the **Versions** tab.

i Note

The accounting document provides a link from the warranty claim to the financing document. You need to maintain the general ledger (GL) accounts. For more information, refer [General Ledger \(GL\) Accounts](#)

5. Choose **Save**.

Reverse Posted Supplier Claim

A reversal of a posted supplier claim is performed when the initial posting is not correct and require rectification.

A claim analyst can use the below procedure to post reversal.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorization to perform the task.
- A claim that is posted to finance is available. For more information, refer [Post Supplier Claim to Finance](#)

Procedure

1. Launch the **Manage Supplier Claims** application from the Launchpad.
2. Search for a claim that is posted to finance.
3. Select a claim to view further details. The option **Reverse Posting** should be enabled.
4. Choose **Reverse Posting**.
 - The message *Supplier response received; new incoming claim version is created* displays. The processing status of the claim changes to *Supplier Response Received*
 - The version of the incoming vendor will increase by one
5. Use the **Versions** tab to view various versions of the claim.
 - Version 1: Outgoing Vendor (OV) : version created by the claim analyst and send to the supplier

- Version 2: Incoming Vendor (IV): version received as response from the supplier. On posting to finance, a corresponding accounting document is created. The billing document date is updated with the date on which the posting is done
- Version 3: version updated when reverse posting of the claim is done. The billing document date is updated with the date on which reverse posting is done. The accounting document with details as in warranty claim displays.
- Version 4: working version that can be posted again.

6. Use the **Process Flow** tab to view different versions of the claim.

Cancel a Supplier Claim

A claim analyst can decide to cancel a claim before sending to the supplier as a result of different validations (for example, as a result of errors during the validation of claim).

Use the below procedure to cancel a supplier claim.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorization to perform the task.
- The claim is not sent to the supplier (claim status must be either *Created*, *Error in Validation*, or *Successfully Validated*).

Procedure

1. Launch the **Manage Supplier Claims** application from the Launchpad.
2. Create or search a claim. For more information, refer [Create a Supplier Claim](#).
3. Select an already created or newly created supplier claim from the list to view further details.
4. Choose **Validate**. To know the parameters required for successful validation of a claim, refer [Validate a Supplier Claim](#).

The *View Alerts* pop up displays the errors messages, if any.

i Note

This is an optional step.

5. Choose **Cancel Claim**.

The processing status of the claim changes to *Claim Cancelled*.

i Note

A supplier claim can be cancelled until it is sent to the supplier. For example, once a claim is created or if there are any errors while validating.

The value of the **Decision** field in all items and within the **General Information** tab changes to *Cancelled*.

Reject a Supplier Claim

A claim analyst can use the below procedure to reject a supplier claim

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and authorization to perform the task.
- A claim to which supplier has responded is available. The response from the supplier needs to be in rejected status. For more information, refer [Record Supplier Response](#).

Procedure

1. Launch the [Manage Supplier Claims](#) application from the Launchpad.
2. Search for a claim with the processing status *Supplier Response Received*.
3. Select the supplier claim to view the details. The *Edit*, *Reject Claim*, and *Posted to Finance* within the [Process Actions](#) option displays on the page.
4. Choose [Reject Claim](#).

The processing status changes to *Claim Rejected*. The decision code needs to be set to *Rejected*.

Reprocess a Supplier Claim

A claim analyst can use the below procedure to reprocess a supplier claim.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and authorization to perform the task.
- A claim to which supplier has responded is available. The response from the supplier needs to be in rejected status. For more information, refer [Record Supplier Response](#).

Procedure

1. Launch the **Manage Supplier Claims** from the Launchpad.
2. Search for a claim with the processing status *Claim Rejected*.
3. Choose *Reprocess Claim* from the [Process Actions](#) option.

The processing status changes to *Supplier Response Received*.

Close a Supplier Claim

A claim analyst can use the below procedure to close a supplier claim.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and authorization to perform the task.
- A validated claim on which the supplier has responded is available. For more information, refer [Record Supplier Response](#).

Procedure

1. Launch the [Manage Supplier Claims](#) application from the Launchpad.
2. Search for a claim with the processing status *Claim Posted*.

3. Choose **Close Claim**. The processing status is set to *Claim Closed*.

4. Choose **Save**.

i Note

You can also close a rejected claim.

Reopen a Supplier Claim

A claim analyst can use the below procedure to reopen a claim.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL*, assigned and authorization to perform this task
- A claim that is closed is available. For more information, refer [Close a Supplier Claim](#).

Procedure

1. Launch the **Manage Supplier Claims** application from the Launchpad.
2. Search for a claim with the processing status, *Claim Closed*.
3. Select the supplier claim to view the details.
4. Choose **Reopen Claim**. You can reopen a rejected claim. In this scenario, the claim status is set to *Supplier Response Received*.

i Note

Reopening of claim sets the claim status to the previous status. Reopening a claim in the *Claim Rejected and Closed* status leads into *Claim Rejected* and reopening claims in *Claim Posted and Closed* status lead into *Claim posted*.

Manage a Customer Claim

With the Manage Customer Claims application, you can create a warranty claim on behalf of a customer, which are validated and appropriately paid.

The scenario covers the relevant steps starting with the creation of a claim (based on performed repair), continuing with the validation for completeness, eligibility for reimbursement, and identifying the correct prices for material, labor tasks, and so on. It also supports the transparent maintenance of values and reimbursement of amount to the customer and is based on the supported and performed validations.

A warranty claim is a claim for reimbursement of material and labor costs that are incurred for the purpose of rectifying faults in an object with a valid warranty.

Key Features

With this application, you can do the following:

- [Create a Customer Claim](#)
- [Discard a Customer Claim](#)

- [Validate a Customer Claim](#)
- [Adjust a Customer Claim](#)
- [Request Customer Returns Part](#)
- [Request Additional Information from Customer](#)
- [Accept a Customer Claim](#)
- [Start Supplier Process from Customer](#)
- [Post a Customer Claim](#)
- [Reverse Posted Claim](#)
- [Reject a Customer Claim](#)
- [Reprocess a Customer Claim](#)
- [Close a Customer Claim](#)
- [Reopen a Customer Claim](#)

Supported Device Types

- Desktop
- Tablet
- Smartphone

Create a Customer Claim

As a claim analyst, you can use the below procedure to create a customer claim on behalf of a customer.

Prerequisites

The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorizations to perform the task.

Procedure

1. Launch the **Manage Customer Claims** application from the launchpad.
2. Choose **Create**.
3. In the **Partner and Repair Details** section, maintain information for the following:
 - Customer
 - Object Type
 - Object Number
 - Damage Date
 - Repair Date

i Note

These are mandatory fields.

4. In the **Additional Details** section, maintain information for the following:

- Plant
- Sales Organization
- Distribution Channel
- Division
- Currency

i Note

These are mandatory fields.

5. In the **Item Information** section, create atleast an item to the customer claim. Maintain information for the following:

- Material
- Quantity
- Part Causing Damage: Atleast one item should be set as the part causing damage. For more information, refer [Validate a Customer Claim](#).

6. Choose **Create**.

Discard a Customer Claim

As a claim analyst, you can use the below procedure to discard a customer claim on behalf of a customer.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorizations to perform the task.

Procedure

1. Launch the **Manage Customer Claims** application from the Launchpad.
2. Search for a claim with the processing status *Created*. For more information, refer [Create a Customer Claim](#)
3. Select a customer claim to view further details.

The options, *Validate on Submit* and *Discard Claim* displays.

4. Choose **Discard Claim**.

Validate a Customer Claim

A customer warranty claim is validated multiple times during the processing. First it is checked for completeness while submitting to ensure all the relevant information is by the customer. Secondly, it is checked formally to ensure all the related and relevant master data is set up properly. Finally it is checked with regards to the business rules to take a decision if and how much the customer should be reimbursed.

Prerequisites

- The claim analyst have the necessary role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorization to perform the task.

Procedure

Select a customer warranty claim from the list. The following are the three stages in validation:

- [Validate on Submit](#)
- [Formal Validation](#)
- [Content Validation](#)

i Note

Please note that the descriptions specifically explain what is done / happens in the individual process steps. The scope item (as a whole) is set up to support process automation. This means that when a process step is successfully executed, the succeeding process step is directly initiated / performed. Therefore, it is possible that the claim status is set to *Claim Posted* as succeeding steps could be successfully executed as part of this automation.

Related Information

[Rules for Customer](#)

Validate on Submit

This is the first step on validating a customer claim.

Prerequisites

- A valid claim with all the mandatory fields is available. A person responsible and atleast details of one item should be available within the claim. For more information, refer [Create a Customer Claim](#)

Procedure

1. Choose **Validate on Submit**.

The errors identified during validation displays in the *View Alerts* and *View Messages* tab. These errors must be fixed before proceeding to formal validation, The status of the claim is set to **Created**.

Formal Validation

Once validate on submit of a claim is successful, a claim analyst can perform a formal validation.

Procedure

1. Choose **Formal Validation**.

In this step, customer organization data and reference object details are validated.

If there are any errors in validation in this step, the processing status is set to **Errors in Formal Validation**. Once the errors are fixed, you need to validate the claim again. Errors are visible on clicking the *View Alerts* and *View Messages* buttons

Content Validation

The final step in validating a customer claim is content validation.

Prerequisites

- Inbound process should be completed. For more information, refer [Complete Inbound Process of Claim](#).

Procedure

1. Choose **Content Validation**.

The errors identified during this validation step displays in the *View Alerts* and *View Messages* tab. These errors must be fixed before proceeding to formal validation. The status of the claim is set to **Errors in Content Validation**. In this step, the master warranty (assigned to the reference object) is checked and the eligibility is derived.

The decision code is automatically set to *Approved* and can be edited.

Rules for Customer

You can find below details of rule within the individual groups for customer:

Validation Point	Group	Rules
C10 Validation point for claim submission	SAP_DATA_FORMAT_CHECK	• CLAIM_ITEM_EXISTANCE_CHECK • CLAIM_PERSON_RESPONSIBLE_CHECK • CLAIM_REQUESTED_AMOUNT_CHECK • MATERIAL_UOM_CHECK • PARTS_CAUSING_DAMAGE_CHECK
C10 Validation point for Claim Submission	DATE_CHECK	• DAMAGE_DATE_ORDER_CHECK • REPAIR_DATE_ORDER_CHECK
C20 Validation point for Formal checks	SAP_MASTER_DATA_CHECK	• WARRANTY_ASSIGNMENT_CHECK • REFERENCE_OBJECT_DATA_CHECK • CUSTOMER_ORG_DATA_CHECK
C30 Validation point for customer business checks	SAP_WARRANTY_CHECK	• WARRANTY_COVERAGE_CHECK

Adjust a Customer Claim

As a claim analyst, you can adjust details or requested amount within the customer warranty claim, before sending to the manufacturer.

Prerequisites

This is custom documentation. For more information, please visit [SAP Help Portal](#).

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and the necessary authorizations to perform the task.

Procedure

1. Launch the **Manage Customer Claims** application from the launchpad.
2. Search for a claim with the status *Created*. For more information, refer [Create a Customer Claim](#)
3. Select the claim and click **Validate on Submit**.

If there are no errors during validation, the status of claim is set to **Submitted**.

4. Click **Formal Validation**.

Once the formal validation is successful, you can adjust the claim details using the **Adjust Claim** option.

The claim status is set to *Submitted*, once it is adjusted.

Request Customer Returns Part

As a claim analyst, you can use the below procedure to validate the status of return parts

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorizations to perform the task.

Procedure

1. Launch the **Manage Customer Claim** application from the Launchpad.
2. Search for a claim with the status Content Validation Successful. For more information, refer [Content Validation](#).
3. Select the respective claim from the list.

The claim is displayed with the status *Content Validation Successful* with the options, *Edit*, *Reject Claim*, *Post to Finance*, *Request Return Parts*, and *Process Actions*.

4. Navigate to the Item Information and open the item. The customer returns part status should be *Parts have to be returned*.
5. Click **Request Return Parts**. The statement is generated and visible within the *Output Management* tab.
6. Navigate to the **Output Management** tab and the statement is available for print and for emailing.
7. Open the statement to view further details. The statement details should match the contents within the customer claim.

Request Additional Information from Customer

As a claim analyst, you can ask for more information from the customer on the claims. You can also validate the status change from *Submitted* or *Formal Validation successful* or *Ready for Content validation* to *Additional info requested*.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and the necessary authorizations to perform the task.

Procedure

1. Launch the [Manage Customer Claims](#) application from the Launchpad.
2. Search the claim with processing status *Submitted* or *Formal Validation successful* or *Ready for Content Validation*.
3. Select a claim from the list. The claim is displayed with the status *Submitted* or *Formal Validation* or *Ready for Content Validation* with the options, *Edit*, *Adjust Claim*, *Process Actions*, and *Request Additional Information*.
4. Click [Request Additional Info](#). The claim is saved with the processing status *Additional Info Requested*.
5. Verify the following:
 - Edit: Claim displays with the status *Additional Info requested*. Only the fields, *Mileage*, *Operating Hours*, *Attachments*, and *Notes* are enabled.
 - Mileage: Enter a value
 - Attachments: Upload a document
 - Notes: Enter any required additional information

Complete Inbound Process of Claim

During this stage of validation, a new outgoing claimant (OC) is created. A claim analyst can follow the below step to complete this process.

Prerequisites

- A claim with successful formal validation is available. For more information, refer [Formal Validation](#)

Procedure

1. Choose [Complete Inbound Process](#).

A new outgoing claimant version is created.

Accept a Customer Claim

As a claim analyst, you can use the below procedure to accept a claim, irrespective of whether validation errors exist or not.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL*, assigned and authorization to perform this task.

Procedure

1. Launch the [Manage Customer Claims](#) application from the Launchpad.
2. Create a claim. For more information, refer [Create a Customer Claim](#).

i Note

You can also search for a claim with the processing status *Error in Content Validation* and proceed. For more information, refer [Content Validation](#).

3. Choose **Validate on Submit**. Two scenario's exist:

- If there are no errors during this stage, the claim can be processed for formal validation.
- If there are errors identified during the claim validation, the details display within the *View Alerts* and *View Messages* tab. You need to fix these errors before proceeding to formal validation.

4. Choose **Formal Validation**. The identified errors must be fixed and validated again, if errors existed during formal validation. For details on validating a claim, refer [Validate a Customer Claim](#).

5. Choose **Complete Inbound Process**. A new outgoing claimant version (OC) is created. For more information, refer [Complete Inbound Process of Claim](#)

6. To complete the validation process, click **Content Validation**. If errors exists during this step, the option to accept claim displays.

i Note

Please note that the descriptions specifically explain what is done / happens in the individual process steps. The scope item (as a whole) is set up to support process automation. This means that when a process step is successfully executed, the succeeding process step is directly initiated / performed. Therefore, it is possible that the claim status is set to Claim Posted as succeeding steps could be successfully executed as part of this automation.

Start Supplier Process from Customer

As a claim analyst, you can initiate creating supplier claim through a customer claim.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and the necessary authorizations to perform the task.

Procedure

1. Launch the **Manage Customer Claims** application from the Launchpad.
2. Search for a claim with the processing status **Ready for Content Validation**. For more information, refer [Validate a Customer Claim](#)
3. Select a claim from the list. The claim is displayed with the status **Ready for Content Validation** with the options, *Edit*, *Content Validation*, *Initiate Supplier Process*, *Request Additional Information* and *Process Actions*.
4. Click the **Initiate Supplier Process** tab. Add values in all mandatory fields such as the supplier, purchase org, and supplier person responsible.
5. Click **Initiate Supplier Process** option. The statement displays the details.
6. Launch the **Manage Supplier Claims** application from the Launchpad.
7. Search the claim with the same claim number as customer claim.

The claim displays with the same claim number and new outgoing version.

8. Search a claim with the processing status *Ready for Content Validation*.
9. Select a claim from the list. The claim is displayed with the status **Ready for Content Validation** with the options, *Edit*, *Content Validation*, *Initiate Supplier Process*, *Request Additional Information* and *Process Actions*.
10. Validate that supplier process ID is created.

11. Click [Initiate Supplier Process](#).

Post a Customer Claim

Once a customer claim is successfully validated, it is posted to finance. A claim analyst can use the below procedure:

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL*, assigned and necessary authorizations to perform the task.
- A validated claim is available. For more information, refer [Validate a Customer Claim](#).

Procedure

1. Launch the *Manage Customer Claims* application from the Launchpad.
2. Search for claim with the processing status, *Content Validation Successful*.
3. Select the claim to view further details. The *Edit*, *Reject Claim*, and *Post to Finance* options display in the *Process Actions* dropdown on the page.
4. Choose [Post to Finance](#).

i Note

The accounting document linked to the incoming customer (IC) version displays in the *Process Flow* tab.

The accounting document provides a link from the customer warranty claim to the financial document. You need to maintain the general ledger (GL) accounts. For more information, refer [General Ledger \(GL\) Accounts](#).

i Note

You can use the *Edit* option to change or update details such as the person responsible, header and version note, and attachment.

5. Navigate to the [Output Management](#) tab and claim statement is available for print and for emailing.
6. Open the claim statement to view further details. The claim statement details should match the contents within the customer claim.

Reverse Posted Claim

A reversal of posted customer claim is performed when the initial posting is not correct and require rectification.

A claim analyst can use the below procedure to post reversal.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and necessary authorizations to perform the task.
- A claim that is posted to finance is available. For more information, refer [Post a Customer Claim](#)

Procedure

1. Launch the **Manage Customer Claims** application from the Launchpad.
2. Search for a customer claim that is posted go finance.
3. Select a claim to view further details. The option **Reverse Posting** should be enabled.
4. Choose **Reverse Posting**. Two new outgoing claimant versions (OC) is created. The latest active version is available for posting.
5. Use the *Versions* tab to view various versions of the claim.
 - a. Version 1: Incoming Customer (IC): version raised by the customer with the relevant claim details
 - b. Version 2: Outgoing Customer (OC): version received from the manufacturer. On posting to finance, a corresponding accounting document is created.
 - c. Version 3: Outgoing Version (OC) updated when reverse posting of the claim is done. The accounting document with details as in customer claim displays.
 - d. Version 4: Outing active version that can be posted again.
6. Use the *Process Flow* tab to view different versions of the claim.

Reject a Customer Claim

A claim analyst can use the below procedure to reject a customer claim.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and authorization to perform the task
- A valid customer claim is available. For more information, refer [Create a Customer Claim](#)

Procedure

1. Launch the **Manage Customer Claims** application from the Launchpad.
2. Select a claim with the processing status *Created* from the list or create a customer claim.

i Note

You can also search for a claim with the processing status *Error in Content Validation*. For more information, refer [Content Validation](#).

3. Select the customer claim to view the details. The *Edit*, *Validate on Submit*, and *Discard Claim* displays.
4. Choose **Validate on Submit**
 - In case there are no errors during validations, the claim status is set to *Submitted*. The option **Formal Validation** displays.
 - If there are errors identified during validations, you need to rectify and set the claim for validation again.
5. Choose **Formal Validation**. If there are errors identified during validation, you can reject the claim at this step. For this, you need to set the decision to *Rejected* within the *General Information* section, using the **Edit** option.

i Note

You can also reject a customer claim if errors are identified after the content validation.

6. Claim can be also rejected from the following other statuses:

- Formal Validation Successful
- Content Validation Successful
- Errors in Content Validation

7. Navigate to the **Output Management** tab and claim statement is available for print and for emailing.

8. Open the claim statement to view further details. The claim statement details should match the contents within the customer claim.

Reprocess a Customer Claim

As a claim analyst, you can reprocess a customer claim.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and authorization to perform the task.

Procedure

1. Launch the **Manage Customer Claims** application.
2. Search for the claim with processing status **Customer Response Received**.
3. Select the supplier claim to view the details. The *Edit*, *Reject Claim*, and *Posted to Finance* within the **Process Actions** option display on the page.
4. Choose **Reject Claim**. The processing status changes to *Claim Rejected*. The decision code needs to be set to *Rejected*.
5. Choose *Reprocess Claim* from the **Process Actions** option.

The processing status changes to *Supplier Response Received*.

Close a Customer Claim

A claim analyst can use the below procedure to close a customer claim.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and authorization to perform the task.
- A successfully validated claim is available. For more information, refer [Validate a Customer Claim](#)

Procedure

1. Launch the **Manage Customer Claims** application from the Launchpad.
2. Search a claim with the status **Claim Posted**.
3. Select a claim to view further details.
4. Choose *Close Claim*. The processing status changes to *Claim Closed*.

i Note

You can also close a rejected claim. For more information, refer [Reject a Customer Claim](#).

Reopen a Customer Claim

A claim analyst can use the below procedure to reopen a customer claim.

Prerequisites

- The claim analyst have the role, *SAP_BR_CLAIMS_ANALYST_COMPL* assigned and authorization to perform this task.
- A claim that is closed is available. For more information, refer [Close a Customer Claim](#)

Procedure

1. Launch the [Manage Customer Claims](#) application from the Launchpad.
2. Search for a claim with the processing status, *Claim Closed*.
3. Select the claim to view further details.
4. Choose [Reopen Claim](#). Reopening of claim sets the claim status to the previous status. Reopening a claim in the *Claim Rejected and Closed* status leads to *Claim Rejected* and reopening claims in *Claim Posted and Closed* status leads to *Claim Posted* status.

Manage a Master Warranty

With the [Manage Master Warranties](#) application, you can create master warranties which defines the terms and conditions for services a company performs when there are defects or problems in technical objects. Master warranties are required to assign individual warranty conditions to each warranty object and check during warranty claim processing if the object has a valid warranty.

Key Feature

- [Create a Master Warranty](#)
- [Update a Master Warranty](#)

Create a Master Warranty

You can use the below procedure to create a master warranty.

Prerequisites

- You have the role, *SAP_BR_MD_SPECIALIST_WRNTY* assigned and necessary authorizations to perform the task

Procedure

1. Launch the [Manage Master Warranties](#) application from the Launchpad.
2. Choose [Create](#).
3. In the [Header](#) section, enter or select:

- Description
- Warranty Type: this is a mandatory field.

4. Click **Create** within the *Terms and Conditions* section.

5. Within the *Warranty Counter* section, click **Add Counter** and enter:

- Warranty Counter
- Counter Description
- Warranty Counter Value
- Counter Unit of Measure

i Note

By default, four counters are available. You cannot add any additional counters.

You can view all the counters within the *Warranty Counter* section.

Within a master warranty, multiple warranty counters can exist for an item. Using the **Counter Link** option, you can define the warranty counters within an item.

- Select **Match All** from the dropdown to view all the warranty counters with all the parameters matching.
- In case you want to view only warranty counters with only one or more of the parameters matching, use the **Match Any** option.

i Note

You can delete only items and warranty counters. It is not possible to delete master warranties.

Update a Master Warranty

You use the below procedure to update master warranty details.

Prerequisites

- You have the role, *SAP_BR_MD_SPECIALIST_WRNTY* assigned and necessary authorizations to perform the task

Procedure

1. Launch the **Manage Master Warranties** application from the Launchpad.
2. Choose a master warranty from the list of create a new master warranty. To create, refer [Create a Master Warranty](#).
3. Click **Edit**.
4. Use the **Header** section to edit the master warranty description.
5. Use the **Item** section to add or edit details of the existing warranty counters associated with the item.

i Note

Atleast one counter must be added to an item.

6. Click **Apply**.

i Note

You cannot delete master warranties. It is possible to delete only items and warranty counters.

Overview of Customer Claims

With the analytical application, *Customer Warranty Claims Overview*, you can get an overview of all customer claims that are in process.

Prerequisites:

- You must be assigned the role, *SAP_BR_CLAIMS_ANALYST_COMPL*.

This application provides the following features:

- View three cards available:
 - Recently Submitted Customer Claims: Summary of recently submitted claims.
 - Accepted/Rejected Claims: Summary of approved and rejected claims for the current month, displayed in weeks. By default, the claims of last four weeks display.
 - Claims in Process: Summary of customer claims that are in process. The following statuses are predefined:
 - Submitted
 - Error in formal Validation and Content Validation
 - Additional Information Requested

Overview of Supplier Claims

With the analytical application, *Supplier Warranty Claims Overview*, you can get an overview of all supplier claims that are in process.

Prerequisites

- You must be assigned the role, *SAP_BR_CLAIMS_ANALYST_COMPL*.

This application provides the following features:

- View three cards available:
 - Recently Created Supplier Claims: Summary of recently created claims, which are sorted by creation date.
 - Approved/Rejected Supplier Claims: Summary of approved and rejected claims for the current month, displayed in calendar weeks.
 - Supplier Claims in Process: Summary of supplier claims that are in process. The following statuses are predefined:
 - Submitted
 - Error in Validation
 - Waiting for Supplier Response

Extensibility in Warranty Management

The applications of warranty claim are enabled with key extensibility.

Procedure

1. Launch the application [Custom fields and logic](#).
2. The following business contexts available. Choose as per your requirement:
 - WTY_WARRANTYCLAIM
 - WTY_WARRANTYCLAIMVERSION
 - WTY_WARRANTYCLAIMITEM
3. Enter customer fields details in the required business context.
4. Enable required underlying CDS views and publish.
5. Launch [Manage Supplier Claims](#) or [Manage Customer Claims](#) applications. Choose *Adapt UI* in settings.
6. Add customer fields in relevant section.
7. To do validation for the field, it requires to extend *Behaviour Definition of RA*.
8. Login to your extensibility development client.
9. Provide your customer logic as below

```

1 extension using interface I_WARRANTYCLAIMTP implementation in class zbp_r_wrntyclaimtp unique;
2
3 extend behavior for WarrantyClaim {
4   ///| field (features : instance ) ZZ1_WTY_HD_KEY1_WTH;
5 }
6
7 extend behavior for WarrantyClaimVersion {
8 }
9
10 extend behavior for WarrantyClaimItem {
11 }

```

CDS views for Warranty Management

The following CDS views are available for warranty management:

- [Warranty Claim Header](#)
- [Warranty Claim Item](#)
- [Warranty Claim Version](#)
- [Warranty Processing Status](#)
- [Warranty Claim Type](#)
- [Reference Object Type](#)
- [Warranty Claim Item Default Condition Type](#)

- [Claim Version Category for Warranty](#)
- [Warranty Item Type](#)
- [Warranty Claim Controlling Item Type](#)
- [Status of Parts to be Returned](#)
- [Status for Parts to Be Returned](#)
- [Coverage Type](#)
- [Warranty Claim Application Log](#)
- [Item Type Based on Claim Type](#)
- [Claim Category](#)
- [Warranty Item Type Catalog](#)
- [Warranty Claim Partner](#)
- [Warranty Decision Code](#)

Business End of Purpose (EoP) Check in Warranty Management

Use

Warranty management provides an end of purpose (EoP) check to determine whether business partner / customer and vendor/supplier data is still relevant for business activities in the application or can be blocked.

Application Name	Application Description	Business Partner Type
Manage Supplier Claims	Create warranty claims that are forwarded to the suppliers for reimbursement	Supplier
Manage Customer Claims	Create a warranty claim on behalf of a customer, which are validated and appropriately paid	Customer

EoP Check Implementation

The class [CL_CVP_AUTO_WTY_EOP_CHECK](#) is used to trigger end of purpose (EoP) that is assigned to the transaction, [CVP_PRE_EOP](#).