



Customer Service

Generated on: 2026-09-29 09:41:23 GMT+0000

SAP S/4HANA | 2025 FPS01 (Feb 2026)

Public

Original content: https://help.sap.com/docs/SAP_S4HANA_ON-PREMISE/f4a255a5de524e3992155767996fb1fd?locale=en-US&state=PRODUCTION&version=2025.001

Warning

This document has been generated from SAP Help Portal and is an incomplete version of the official SAP product documentation. The information included in custom documentation may not reflect the arrangement of topics in SAP Help Portal, and may be missing important aspects and/or correlations to other topics. For this reason, it is not for production use.

For more information, please visit <https://help.sap.com/docs/disclaimer>.

Move-in

Use

You use the move-in function to carry out most of the activities required to begin providing a business partner with a utility service. You create new, or change existing business master data. Most importantly, you allocate a contract to an installation.

In move-in processing, you establish whether a contract can be billed. From the move-in, you can also trigger the charges levied at the commencement of a utility service, as well as a welcome letter to the customer.

Prerequisites

To create a move-in, you require one or more installations that are vacant on the desired move-in date.

- In the case of an initial move-in, ensure that you have completed initial data creation, including creation of the installation(s).
- Devices can (but do not have to) be [installed](#) and allocated before move-in.
- If one of the installations is already allocated to a contract, this allocation must be reversed. To do this, process a move-out. An installation can only be allocated to one contract at any given time.

Features

Customer Contact

When a move-in is created, a corresponding customer contact is created automatically. This is automatically linked to the move-in document. You can find additional information in the section on [Customer contact](#).

Overall Check

When a contract is assigned the move-in status 05 (meter reading entered completely), you can verify that the contract can be billed.

Move-In Status

If you process or display a move-in document, the system also displays the move-in status of each contract. The move-in status informs the agent which stage of move-in processing has been reached.

The minimum is formed from the move-in status of the contracts and also displayed. In this way you can obtain information on the status of the entire move-in processing.

Move-In Documents

When you display the move-in documents for a business partner or a premise, the documents from the last three months appear. If no documents exist for this period then the system displays the documents from the last six months.

Once you have entered the move-in, move-out, or move-in/out, you can use the SAP Business Workflows to trigger and monitor

- The meter readings are unavailable
- The budget billing plan cannot be created, or
- The data required to print the welcome letter is incomplete

Move-In Charges

When you save the move-in document, the system posts the move-in charges automatically, provided you have configured the system accordingly in Customizing under [►Move-In/Out► Define System Parameters for Move-In and Move-Out. ►](#).

You can configure the system to post the charges to a contract or contract account. You configure how the system calculates the charges using the parameters [Charge category](#) and [Charge schema](#) . In this way, you can, for example, levy a move-in charge staggered to correspond with the number of contracts.

Reduced Layouts

In Customizing, you can define reduced layouts for the configurable tab on page on the move-in screen to hide some of the data on the individual tab pages. The layouts can now be stored in the special processing variants for the move-in/out. This enables agents to process move-ins and move-in/outs more quickly.

Budget Billing

A budget billing amount agreed with the customer is also taken in account if the move-in is entered by the master data generator. If a budget billing plan cannot be created for a contact in move-in processing then the BudgetBillingPlansFailed event of the MOVEINDOC BOR object type is triggered.

Activity Log

In Customizing you can configure the system to save the activity log for the move-in. You can then display it on the move-in screen. To do this choose [►Extras► Display Activity Log. ►](#)

Activities

Initial Screen

Based on the data you specified on the initial screen, the system automatically determines which of the following cases applies:

Exists before move-in	Is created during move-in
Business partner, contract account, installation	Contract
Business partner, installation	Contract account, contract
Installation	Business partner, contract account, contract

Move-in date

You can change the date of a move-in after it has been created without affecting the move-out that precedes it. To do this, choose [►Edit► Change Move-In Date ►](#).

Save

When you save the move-in, the initial move-in or move-in/out screen reappears. In Customizing under [Define Control Parameters at Document Level](#), you can configure the system so that when you save the data, a log is displayed containing information on the changes made to the data.

Certain move-in activities, for example, maintaining a budget billing plan, are based on the database changes made by the move-in. In these instances, you can, in Customizing under [Move-In/Out -> Move-In -> Define Control Parameters at Document Level](#) configure the system to either output a confirmation prompt or save the data automatically before the action is carried out.

You can also save your changes in the move-in without leaving the move-in screen. To do this, choose [Save and Hold](#).

Master Data (Move-In)

Use

During move-in processing, one or more contracts are created to commence on the specified move-in date. The installations you specified at the start of processing are allocated to these contracts.

If the move-in date is in a period in which one of the installations has already been billed then the move-in cannot be created.

You can save changes to business partner and contract account data as **scheduled** changes. This means that the changes are not activated until a future date. This date is determined by subtracting the interval period defined in Customizing from the move-in date. For more information on how to define the interval period, see Customizing under [SAP Utilities > Customer Service > Process Execution > Move-In/Move-Out > Define System Parameters for Move-in and Move-Out](#). Scheduled changes are activated by report BUSPCDACT (activation of scheduled change documents for an application object).

When a move-in is created, the tax jurisdiction code of the connection object address is copied to all the contracts of the move-in document, as well as to all the business partner addresses that were automatically created through the move-in.

Standard Business Partner Address

In Customizing ([SAP Utilities > Customer Service > Process Execution > Move-In/Out > Move-In > Define Move-In Control Parameters at Document Level](#)), you can configure the system so that the business partner receives the address of the premise he/she is moving into as the default address. If you want to process the move-in for different premises in one move-in document, the system uses the premise address of the installation that was entered first.

You can find additional information in the section on the [master data](#) component.

Using the Business Add-In (BAdI) ISU_MOVEIN_SETBPADDR, you can allocate a default value to the standard address.

Meter Reading Data (Move-In)

Use

When you create a move-in, the system proposes an existing meter reading result for all the billing-relevant registers allocated to the devices for billing purposes. Ensure you have configured the system accordingly in Customizing under [SAP Utilities > Device Management > Meter Reading > Basic Settings > Define Control Parameters for Meter Reading Data Processing](#).

- If you change the meter reading result, a new result is created with the meter reading reason **Move-in**.
- If the system does not propose a meter reading result, you can have it estimate a result or enter one manually. In both cases, the system creates a new meter reading result from the adopted/changed result and gives it the meter reading reason **Move-In**.
- If the system does not propose a meter reading result, and you do not enter one manually, a service notification or service order is created for the current register. For more information see [service notifications and orders](#).

You can also suppress the meter reading proposal or define an interval as required. If you do this, the system only makes a proposal if the meter reading result on which the proposal is based was taken during the interval. Ensure you have configured the system accordingly in Customizing under **SAP Utilities > Device Management > Meter Reading > Basic Settings > Define Control Parameters for Meter Reading Data Processing**. Ensure that you make an appropriate entry in the **Move-in prop. inter.** (Interval for determining default value) and the **Display default move-in value** checkbox alongside it.

You can find additional information on meter reading data processing in the section on the [meter reading](#) component.

Budget Billing Plan

Use

You can create a budget billing plan for every contract involved in a move-in, provided the **BB procedure** (budget billing plan active) field in the contract account contains the value 1 (Statistical procedure for budget billing collection) or 2 (Debit entry procedure for budget billing collection). You have the following options:

- Create budget billing plan manually

To do this, choose the **Budget billing plan** pushbutton in move-in processing.

- Create budget billing plan when data is saved

To have the system create a budget billing plan automatically when you save the move-in document, make the appropriate entry in the **Create budget billing plan** field in Customizing under **Move-In/Out > Move-In > Define Move-In Control Parameters on Contract Level**.

If necessary, you can also override the settings you have established in Customizing. To do this, choose **Extras > Control Parameters** in move-in processing.

You can choose whether to assign a budget billing amount that is valid for all due dates, or whether to have each amount calculated by the system.

The budget billing due dates are result from the Scheduling component. The printout date of the first budget billing due date cannot precede the system date. A joint budget billing plan is created for the contracts in the contract account for which you specified joint invoicing.

The budget billing cycle is determined from the portion, provided no alternative cycle has been entered in the contract data.

For more information see the section on the [Budget Billing Plan](#) component.

You can request a security deposit in move-in processing, or, provided certain conditions have been met, adopt the security deposit of an existing contract.

Re-Request Security Deposit

Customizing Settings

In Customizing under ► [Move-In/Out](#) ► [Move-In](#) ► [Define Move-In Control Parameters on Contract Level](#) ► you can configure the system so that security deposits are requested through move-in processing. You can request a cash security deposit, or arrange a non-cash security deposit with the customer.

- A cash security deposit is created for each contract. In doing this, this system posts a request document for a cash security deposit in FI-CA.
- A non-cash security deposit is created for all the contracts involved in the move-in, for which a non-cash deposit is to be created.

Entry Options on the Move-In Screen

On the move-in screen, on the tabstrip [Contract Data](#) , enter a reason for requesting the security deposit and the amount requested. Now, when you save the move-in document, the system automatically creates a security deposit. If you specified a reason for exempting the customer from a security deposit then one is not created. You can allocate a default value to the security deposit reason and amount using enhancement EC500001 (determine security deposit reason and amount).

For more information see the section on [Contract Accounts Receivable and Payable](#) (FI-CA) including [Security Deposits](#) .

Adopt Existing Security Deposits (Transfer)

In Customizing under [Define Move-In Control Parameters on Contract Level](#) , you can, using the [Security deposits](#) field, configure the system to transfer the security deposits of existing contracts to newly created contracts. This is done by means of Transfer Contracts. You can use this procedure if, for example, a business partner moves to a new premise in the supply territory, terminates his/her existing contracts for this reason and wishes the security deposits paid on these contracts to be adopted for the new contracts. You can transfer deposits in this way if the following transfer conditions have been met:

- You have entered a move-in/out in the system.
- You have selected the contracts so that both the move-in and move-out documents both contain one contract for each division, and each have the same number of contracts.
- In Customizing, under [Define Move-In Control Parameters on Contract Level](#) , you have defined whether the security deposits of a contract can be automatically transferred.
- Both the transfer contract and the new contract have been allocated to the same company code.

Using enhancement ECSBTI04 (IS-U move-in: determine transfer contract), you can override the transfer contract, or, if necessary suppress the transfer of security deposits.

Welcome Letter

- Create welcome letter manually

To do this, choose the **Welcome letter** pushbutton in move-in processing.

- Create welcome letter when data is saved

To have the system create a budget billing plan automatically when you save the move-in document, mark the **WL** checkbox (Create welcome letter automatically) in Customizing under ► **Move-In/Out** ► **Move-In** ► **Define Move-In Control Parameters at Document Level.** ►

If necessary, you can also override the settings you have established in Customizing. To do this, choose ► **Extras** ► **Control Parameters** ► in move-in processing.

When you create a welcome letter, specify an application form of the form class IS_U_CS_MOVE_IN_WELCOME_LETTER. In addition, you have to define the application form in Customizing under ► **Utilities Industry** ► **Customer Service** ► **Process Execution** ► **Move-In/Out** ► **Move-In** ► **Define Welcome Letter** ►. You can find more information on creating an application form in the section on the ► [Print Workbench](#) component.

Screen Layout

Use

In Customizing under ► **Move-In** ► **Configure Tabs for Move-In Screen** ►, you can configure various views for the data on the move-in screen. These views are composed of tabs that you can use to organize the data into different logical units based on your requirements.

You can maintain contract data in one of two ways:

- Individual maintenance

The system displays the data of one contract only.

- Overview maintenance

The system displays the data of up to five move-in documents allocated to the same contract.

For more information, see Customizing under ► **Move-In/Out** ► **Define System Parameters for Move-In and Move-Out** ►.

You can include standard and user-defined fields for the contract account and business partner in direct maintenance. To do this, use the following enhancements:

- EMBP003 (user subscreen in the business partner subscreen for move-in/out))
- EMDCA001 (user subscreen for IS-U contract account)
- EMDK0001 (IS-U utility contract: include subscreens and check fields)

Features

This function enables you to adjust the screen layout to best suit your requirements. The fields visible on the screen have been grouped into units that you can distribute among the individual tabs.

You have the following options:

- If you want to use the standard SAP layout, do not make any changes.
- If you want to define your own layout then establish the following settings:
 - a. In Customizing, choose [Move-In/Out](#) > [Move-In](#) > [Configure Tabs for Move-In Screen](#) . Here you can define your own layout.
 - b. Enter the layout in Customizing as a default layout in Customizing under [SAP Utilities](#) > [Basic Settings/Enterprise Structure](#) > [Define Default Layout for Tabs](#) .

Service Notifications and Orders

Use

In Customizing under [Device Management](#) > [Meter Reading](#) > [Basic Settings](#) > [Define Control Parameters fir Meter Reading Data Processing](#) , you can configure the system to create a service order or service notification for the move-in meter reading (provided that plausible meter readings do not already exist for the metering devices). You can establish this settings separately for each division. Customizing entries with an empty company code key are relevant to this process, since the system does not yet know the company code in move-in initial processing. You can use enhancement ECSBTMR1 (Assign default values for creation of service notifications/orders).

You can also do this in Customizing under [Device Management](#) > [Meter Reading](#) > [Basic Settings](#) > [Define Control Group for Creation of Multiple MR Orders](#) ., you define whether the system creates service notifications or service orders, and whether these or stored at device, device location or connection object level.

Alternatively, you can integrate the creation of service notifications and orders into a workflow, in which case creation is not immediate but postponed. You do this in Customizing under [Define System Parameters for Move-In and Move-Out](#) . Prerequisites for this are the method MoveInDocument.MeterReadingServiceInitiate (Trigger service management for meter reading) and the parameter DelayedMeterReadServ V in event MoveInDocument.Created for object type MOVEINDOC (move-in document).

If you reverse a move-in, the system adjusts the status of the service notifications/orders generated during move-in creation as follows:

- The status **Completed** is allocated to the service notifications.
- The status **Not executed** is allocated to service orders that were not released.
- The status **Technically completed** is allocated to service orders that were released.

If you change a move-in date, the system proceeds as though the move-in had been reversed and re-created for another date.

Features

On the move-in screen, you can have the system generate a service order or notification, regardless of the default settings you have made. If the parameter was set and the register results were completely entered (determined by the default settings), and you still want to create a service order/notification, then you must reset the register results using the **Reset** function key. Otherwise, the system saves the register results and a service notification/order is no longer required.