

DIPLOMATURA EN PROGRAMACION ABAP MÓDULO 10: PROGRAMACIÓN DE DIÁLOGO. MODULE POOL

Programación de Diálogo y Creación de Module Pools con ABAP

Side of the state of the state

Programación de Diálogo

E


ste módulo detalla los pasos para crear programas de diálogo del tipo *module pool* en *ABAP*.

Module Pool

Pasos para su creación


Los pasos para la creación de un module pool son los siguientes:

■ Crear el programa a través de la transacción SE38, de tipo module pool:



- Crear las pantallas a través de la transacción SE51 (Screen Painter). Cada una de ellas se denomina dynpro en SAP (dynamic program).
- Crear el diseño de la barra de tareas de la pantalla y asignar un título a través de la transacción SE41 (Menú Painter).
- Diseñar y desarrollar la lógica de proceso de las dynpros. Insertar el código correspondiente a los módulos PBO (Process Before Output) y PAI (Process Alter Input). En el módulo PBO se debe asociar la barra de tareas creado en el punto anterior.

Crear una transacción a través de la transacción SE93 que direccione la llamada al module pool creado.





Para ver cómo se estructura un module pool en SAP, seguiremos el siguiente ejemplo:

Module Pool: SAPMTZ60Gui-Status: TD0100/ TD0200

Dynpros: 0100-0200

Código de transacción: TZ60





Ejemplo de Module Pool

Para ejemplificar lo expuesto, vamos a proceder a la visualización del programa SAPMTZ60 a través de la SE38:

*&		 	_ *
*& Modulpool	SAPMTD60		*
* &	400		*
* &		 	_ *
* &			*
*& Display DATA of	table SPFLI		*
* &			*
*&		 	_ *
* Globale Daten	r		
INCLUDE MTZ60TOP.			
* PBO-Module			
INCLUDE MTZ60001.			
* PAI-Module			
INCLUDE MTZ60I01.			
INCLUDE MTZ60F01.			
*		 	_ *
* INCLUDE MTD40TOP			*
*		 	_ *
PROGRAM SAPMTZ60 MES	SSAGE-ID A&.		

```
Diplomatura en Programación Abap - módulo 10: PROGRAMACIÓN DE DIÁLOGO Y MODULE POOL
TABLES: SFLIGHT,
                                          " Flugdaten
        SPFLI,
                                          " Prüfung: Flughafen
        SAIRPORT,
                                          " Fluggesellschaft
        SCARR.
DATA: OK CODE (4),
      RCODE(5),
      LINE COUNT TYPE I.
CONTROLS: FLIGHTS TYPE TABLEVIEW USING SCREEN 200.
DATA INT FLIGHTS LIKE SFLIGHT OCCURS 1 WITH HEADER LINE.
INCLUDE MTD40001
     Module STATUS 0100 OUTPUT
     text
```

```
MODULE STATUS 0100 OUTPUT.
  SET PF-STATUS 'TD0100'.
  SET TITLEBAR '100'.
                          " STATUS 0100
ENDMODULE.
MODULE STATUS 0200 OUTPUT.
  SET PF-STATUS 'TD0200'.
  SET TITLEBAR '100'.
ENDMODULE.
*& Module DISPLAY FLIGHTS OUTPUT
* & -----
MODULE DISPLAY FLIGHTS OUTPUT.
  SFLIGHT-FLDATE = INT_FLIGHTS-FLDATE.
  SFLIGHT-PRICE
                 = INT FLIGHTS-PRICE.
  SFLIGHT-CURRENCY = INT FLIGHTS-CURRENCY.
  SFLIGHT-PLANETYPE = INT FLIGHTS-PLANETYPE.
  SFLIGHT-SEATSMAX = INT FLIGHTS-SEATSMAX.
  SFLIGHT-SEATSOCC = INT FLIGHTS-SEATSOCC.
                         " DISPLAY FLIGHTS OUTPUT
ENDMODULE.
  INCLUDE MTD40101
   Module USER_COMMAND_0100 INPUT
       Fetch data from SPFL or exit from transaction
MODULE USER COMMAND_0100 INPUT.
  CASE OK CODE.
   WHEN SPACE.
     AUTHORITY-CHECK OBJECT 'S CARRID'
            ID 'CARRID' FIELD 'LH'
```

```
ID 'ACTVT' FIELD '*'.
      IF SY-SUBRC NE 0. Message E009. ENDIF.
      SELECT SINGLE * FROM SPFLI
             WHERE CARRID
                            = SFLIGHT-CARRID
                               = SFLIGHT-CONNID.
             AND
                   CONNID
      IF SY-SUBRC NE 0.
         MESSAGE E005 WITH SFLIGHT-CARRID SFLIGHT-CONNID.
      SELECT * FROM SFLIGHT INTO TABLE INT FLIGHTS
                            WHERE CARRID = SFLIGHT-CARRID
                            AND
                                   CONNID = SFLIGHT-CONNID.
      IF SY-SUBRC NE 0.
         MESSAGE E006 WITH SFLIGHT-CARRID SFLIGHT-CONNID.
      ENDIF.
      FLIGHTS-TOP LINE = 1.
      DESCRIBE TABLE INT FLIGHTS LINES FLIGHTS-LINES.
      CLEAR OK CODE.
    WHEN 'CANC'.
      CLEAR OK CODE.
      SET SCREEN O. LEAVE SCREEN.
    WHEN 'EXIT'.
      CLEAR OK CODE.
      SET SCREEN 0. LEAVE SCREEN.
    WHEN 'BACK'.
      CLEAR OK CODE.
      SET SCREEN 0. LEAVE SCREEN.
  ENDCASE.
                            " USER COMMAND 0100 INPUT
ENDMODULE.
MODULE USER COMMAND 0200 INPUT.
  CASE OK CODE.
    WHEN 'CANC'.
      CLEAR OK CODE.
      SET SCREEN 100. LEAVE SCREEN.
    WHEN 'EXIT'.
      CLEAR OK CODE.
      SET SCREEN 0. LEAVE SCREEN.
    WHEN 'BACK'.
      CLEAR OK CODE.
      SET SCREEN 100. LEAVE SCREEN.
    WHEN 'NEW'.
      CLEAR OK CODE.
      SET SCREEN 100. LEAVE SCREEN.
    WHEN 'P--'.
      CLEAR OK CODE.
      PERFORM PAGING USING 'P--'.
    WHEN 'P-'.
      CLEAR OK CODE.
      PERFORM PAGING USING 'P-'.
    WHEN 'P+'.
      CLEAR OK CODE.
      PERFORM PAGING USING 'P+'.
    WHEN 'P++'.
      CLEAR OK CODE.
      PERFORM PAGING USING 'P++'.
  ENDCASE.
                            " USER COMMAND 0100 INPUT
ENDMODULE.
```

```
*& Module EXIT INPUT
      text
MODULE EXIT 0100 INPUT.
  CASE OK CODE.
   WHEN 'CANC'.
     CLEAR OK CODE.
      SET SCREEN O. LEAVE SCREEN.
   WHEN 'EXIT'.
     CLEAR OK CODE.
     SET SCREEN 0. LEAVE SCREEN.
  ENDCASE.
ENDMODULE.
                          " EXIT INPUT
MODULE READ TEXT 0100 INPUT.
  SELECT SINGLE * FROM SCARR WHERE CARRID = SFLIGHT-CARRID.
                          " READ TEXT 0100 INPUT
ENDMODULE.
*& Module SET LINE COUNT INPUT
       text
MODULE SET LINE COUNT INPUT.
 LINE COUNT = \overline{SY}-LOOPC.
                           " SET LINE COUNT
ENDMODULE.
*-----
***INCLUDE MTD60F01 .
      Form PAGING
FORM PAGING USING CODE.
  DATA: I TYPE I,
J TYPE I.
 CASE CODE.
    WHEN 'P--'. FLIGHTS-TOP LINE = 1.
    WHEN 'P-'. FLIGHTS-TOP_LINE = FLIGHTS-TOP LINE - LINE COUNT.
               IF FLIGHTS-TOP LINE LE O. FLIGHTS-TOP LINE = 1. ENDIF.
    WHEN P+V. I = FLIGHTS-TOP LINE + LINE COUNT.
               J = FLIGHTS-LINES - LINE COUNT + 1.
               IF J LE 0. J = 1. ENDIF.
               IF I LE J. FLIGHTS-TOP LINE = I.
                       FLIGHTS-TOP LINE = J.
               ELSE.
               ENDIF.
    WHEN 'P++'. FLIGHTS-TOP LINE = FLIGHTS-LINES - LINE_COUNT + 1.
               IF FLIGHTS-TOP LINE LE 0. FLIGHTS-TOP LINE = 1. ENDIF.
  ENDCASE.
ENDFORM.
                           " PAGING
```

Continuamos luego con la visualización del programa SAPMTZ60 (dynpro 0100) a través de la SE51:

```
PROCESS BEFORE OUTPUT.

MODULE STATUS_0100.

*

PROCESS AFTER INPUT.

MODULE EXIT_0100 AT EXIT-COMMAND.

*

FIELD SFLIGHT-CARRID

MODULE READ_TEXT_0100 ON REQUEST.

*

MODULE USER_COMMAND_0100.
```

A colación de ellos, proseguimos con la visualización del programa SAPMTZ60 (dynpro0200) a través de la SE51:

```
PROCESS BEFORE OUTPUT.

MODULE STATUS_0200.

LOOP AT INT_FLIGHTS WITH CONTROL FLIGHTS CURSOR FLIGHTS-TOP_LINE.

MODULE DISPLAY_FLIGHTS.
ENDLOOP.

*
PROCESS AFTER INPUT.

*
LOOP AT INT_FLIGHTS.
MODULE SET_LINE_COUNT.
ENDLOOP.
MODULE USER COMMAND 0200.
```

A continuación, en la próxima Unidad, veremos todos los detalles y funcionalidades del Screen Painter y del Menú Painter. En tanto, los invitamos a realizar las actividades de la Unidad actual.