

www.devexpress.com



ExpressPrintingSystem v2.0

by Developer Express



Report Links

Copyright © 2001 Developer Express Inc.

Table of Contents

Table of Contents	2
TAbstractdxReportLinkDesigner Object	8
TAbstractdxReportLinkDesignWindow Object	9
TBasedxReportLink Object	10
TBasedxReportLink Properties	11
TBasedxReportLink Methods	24
TBasedxReportLink Events	45
TAbstractdxGridReportLink Object	49
TAbstractdxGridReportLink Properties	50
TAbstractdxGridReportLink Methods	64
TAbstractdxGridReportLink Events	64
TCustomdxGridReportLink Object	65
TCustomdxGridReportLink Properties	66
TCustomdxGridReportLink Methods	68
TCustomdxGridReportLink Events	68
TStddxGridReportLink Object	69
TStddxGridReportLink Properties	70
TStddxGridReportLink Methods	71
TStddxGridReportLink Events	71
TdxSGrReportLinkDesignWindow Object	72
TdxStringGridReportLink Object	73
TdxStringGridReportLink Properties	74
TdxStringGridReportLink Methods	77
TdxStringGridReportLink Events	78
TdxDGrReportLinkDesignWindow Object	79
TdxDrawGridReportLink Object	80

TdxDrawGridReportLink Properties	81
TdxDrawGridReportLink Methods	83
TdxDrawGridReportLink Events	85
TdxCustomListBoxReportLink Object	86
TdxCustomListBoxReportLink Properties	87
TdxCustomListBoxReportLink Methods	90
TdxCustomListBoxReportLink Events	91
TdxChlbxReportLinkDesignWindow Object	93
TdxCheckListBoxReportLink Object	94
TdxCheckListBoxReportLink Properties	95
TdxCheckListBoxReportLink Methods	97
TdxCheckListBoxReportLink Events	99
TdxLBxReportLinkDesignWindow Object	100
TdxListBoxReportLink Object	101
TdxListBoxReportLink Properties	102
TdxListBoxReportLink Methods	105
TdxListBoxReportLink Events	106
TAbstractdxRichEditReportLink Object	107
TAbstractdxRichEditReportLink Properties	108
TAbstractdxRichEditReportLink Methods	110
TAbstractdxRichEditReportLink Events	110
TdxRichEditReportLink Object	111
TdxRichEditReportLink Properties	112
TdxRichEditReportLink Methods	113
TdxRichEditReportLink Events	113
TrxRichEditReportLink Object	114
TrxRichEditReportLink Properties	115

TrxRichEditReportLink Methods	116
TrxRichEditReportLink Events	116
TCustomdxInspectorReportLink Object	117
TCustomdxInspectorReportLink Properties	118
TCustomdxInspectorReportLink Methods	127
TCustomdxInspectorReportLink Events	128
TdxInspectorReportLink Object	130
TdxInspectorReportLink Properties	131
TdxInspectorReportLink Methods	132
TdxInspectorReportLink Events	132
TdxDBInspectorReportLink Object	133
TdxDBInspectorReportLink Properties	134
TdxDBInspectorReportLink Methods	135
TdxDBInspectorReportLink Events	135
TdxOCReportLinkDesignWindow	136
TCustomdxOrgChartReportLink Object	137
TCustomdxOrgChartReportLink Properties	138
TCustomdxOrgChartReportLink Methods	141
TCustomdxOrgChartReportLink Events	143
TdxOrgChartReportLink	144
TdxOrgChartReportLink Properties	145
TdxOrgChartReportLink Methods	146
TdxOrgChartReportLink Events	146
TdxDBOrgChartReportLink	147
TdxDBOrgChartReportLink Properties	148
TdxDBOrgChartReportLink Methods	149
TdxDBOrgChartReportLink Events	149

TCustomdxTeeChartReportLink Object	150
TCustomdxTeeChartReportLink Properties	151
TCustomdxTeeChartReportLink Methods	152
TCustomdxTeeChartReportLink Events	153
TdxTeeChartReportLink Object	154
TdxTeeChartReportLink Properties	155
TdxTeeChartReportLink Methods	156
TdxTeeChartReportLink Events	156
TdxDBTeeChartReportLink Object	157
TdxDBTeeChartReportLink Properties	158
TdxDBTeeChartReportLink Methods	159
TdxDBTeeChartReportLink Events	159
TdxTLReportLinkDesignWindow	160
TCustomdxTreeListReportLink Object	161
TCustomdxTreeListReportLink Properties	162
TCustomdxTreeListReportLink Methods	173
TCustomdxTreeListReportLink Events	176
TdxTreeListReportLink Object	181
TdxTreeListReportLink Properties	182
TdxTreeListReportLink Methods	184
TdxTreeListReportLink Events	184
TdxDBTreeListControlReportLink Object	185
TdxDBTreeListControlReportLink Properties	186
TdxDBTreeListControlReportLink Methods	188
TdxDBTreeListControlReportLink Events	189
TdxDBGridReportLink Object	190
TdxDBGridReportLink Properties	191

TdxDBGridReportLink Methods	193
TdxDBGridReportLink Events	195
TdxDBTreeListReportLink Object	196
TdxDBTreeListReportLink Properties	197
TdxDBTreeListReportLink Methods	199
TdxDBTreeListReportLink Events	201
TCustomdxTreeViewReportLink Object	202
TCustomdxTreeViewReportLink Properties	203
TCustomdxTreeViewReportLink Methods	207
TCustomdxTreeViewReportLink Events	208
TdxTreeViewReportLink Object	210
TdxTreeViewReportLink Properties	211
TdxTreeViewReportLink Methods	212
TdxTreeViewReportLink Events	212
TdxTreeViewExReportLink Object	213
TdxTreeViewExReportLink Properties	214
TdxTreeViewExReportLink Methods	215
TdxTreeViewExReportLink Events	215
TdxDBTreeViewReportLink Object	216
TdxDBTreeViewReportLink Properties	217
TdxDBTreeViewReportLink Methods	218
TdxDBTreeViewReportLink Events	218
TdxFCReportLinkDesignWindow	219
TdxFlowChartReportLink Object	220
TdxFlowChartReportLink Properties	221
TdxFlowChartReportLink Methods	223
TdxFlowChartReportLink Events	225

TdxMasterViewReportLink Object	226
TdxMasterViewReportLink Properties	227
TdxMasterViewReportLink Methods	242
TdxMasterViewReportLink Events	243
Index	247

TAbstractdxReportLinkDesigner Object

Unit

dxPSCore

```
TAbstractdxReportLinkDesigner = class(TObject);
```

Description

The **TAbstractdxReportLinkDesigner** object controls the lifetime of the designer window and is used at design-time only.

Hierarchy

TObject

TAbstractdxReportLinkDesignWindow Object

TAbstractdxReportLinkDesignWindow is an abstract ancestor for all report link designers.

Unit

dxPSCore

```
TAbstractdxReportLinkDesignWindow = class(TForm);
```

Description

Report links use report link designers to customize report link properties before printing a component. A report link designer is a window used to customize report links. Every report link uses a specific designer.

Hierarchy

```

TObject
  TPersistent
    TComponent
      TControl
        TWinControl
          TScrollingWinControl
            TCustomForm
              TForm
```

TBasedxReportLink Object

TBasedxReportLink is an abstract report link. All other report links are based upon it.

Unit

dxPSCore

```
TBasedxReportLink = class(TComponent);
```

Description

This class is the common ancestor for all other report links. Use it to create your own report links.

Hierarchy

```

  TObject
    TPersistent
      TComponent
```

TBasedxReportLink Properties

TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	protected / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	protected / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	protected / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	protected / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

Active property

read / write

Creates a report.

```
property Active: Boolean;
```

Description

Use the **Active** property to generate the report.

See Also

TBasedxReportLink.SetActive

AssignedFormatValues property

read / write

Indicates which formats have been assigned to a report link.

type

```
TdxAssignedFormatValue = (fvDate, fvTime, fvPageNumber);
```

```
TdxAssignedFormatValues = set of TdxAssignedFormatValue;
```

```
property AssignedFormatValues: TdxAssignedFormatValues;
```

Description

The **TdxAssignedFormatValues** type defines a set of possible state flags for the **AssignedFormatValues** property. A report link uses assigned values except for default values when printing a component.

The following table outlines possible **TdxAssignedFormatValues** values and the meaning of each flag:

Value	Description
fvDate	Date format has been assigned.
fvTime	Time format has been assigned.
fvPageNumber	Page number format has been assigned.

The default value for this property is [].

Color property**read / write**

Specifies the background color of report cells.

property Color : TColor;

Description

Use this property to specify the background color of cells in a report. The **Color** property has no impact if the **Transparent** property is set to **True**. By default, the **Color** property equals **clWhite**.

Component property**read / write**

Returns the component to print.

property Component : TComponent;

Description

Use the **Component** property to access a component to print. You must also use this property to change the **Component** property of the report link.

ComponentPrinter property**read / write**

Specifies the printing component that uses a given designer.

property ComponentPrinter : TCustomdxComponentPrinter;

Description

Use this property to obtain the printing component of type TCustomdxComponentPrinter that a report link uses to print a specific component.

CurrentPage property**read / write**

Specifies the current page within a report.

property CurrentPage : **Integer**;

Description

This property is used to determine the current page within a report, when the preview form is closed. For instance, for test printing you can set the **CurrentPage** property to 1 and then print the first page.

See Also

TBasedxReportLink.PageCount

CurrentPrintStyle property

read only

Determines the current print style.

property CurrentPrintStyle: TBasedxPrintStyle;

Description

Use the **CurrentPrintStyle** property to obtain the current print style object that provides the basic style information (such as printer page and page setup parameters, etc) for a report link.

ReadOnly Property

Data property

read / write

Specifies additional arbitrary data.

property Data: **Pointer**;

Description

Use the **Data** property to assign additional data to the current report link. Since this property is a pointer to data, it can be of any type. For instance, you can assign a picture for each report link to use later in your application.

DateFormat property

read / write

Specifies date representation format.

property DateFormat: **Integer**;

Description

A user may display a header or footer that contains the date of the report. A report link has a set of predefined date formats that can be applied to a report. The **DateFormat** property specifies the zero-based index of the appropriate format.

Index	Example
0	2/14/01
1	Wednesday, Wednesday, February 14, 2001
2	Wednesday, February 14, 2001

3	2/14/2001
4	2001-02-14
5	14-Feb-01
6	2.14.01
7	Wednesday, Feb. 14, 01
8	2.14.2001
9	February, 01
10	Feb-01

The default value for this property is **0**.

DateTime property

read / write

Determines date and time of a specific report link.

```
property DateTime: TDateTime;
```

Description

Use the **DateTime** property to determine the appropriate date and time values for a report link. This property value is set automatically when a component is assigned to a report link. You can also change it manually. If the **AutoUpdateDateTime** property is set to **False**, this property value is used to display date and time within a report header/footer.

DesignerCaption property

read / write

Specifies the caption of a designer form.

```
property DesignerCaption : string;
```

Description

Use this property to set a specific caption for the report link designer.

DesignerHelpContext property

read / write

Provides the designer context number for use when calling context-sensitive online Help.

```
property DesignerHelpContext: THelpContext;
```

Description

Assign a value to the **DesignerHelpContext** property to determine which help topic appears when a user presses F1 to request help on a report link designer.

EmptyPagesCanExist property

read only

Specifies whether a report can contain empty pages.

```
property EmptyPagesCanExists: Boolean;
```

Description

If the **EmptyPagesCanExist** property is **True**, a report can contain empty pages; Otherwise, all pages are populated with a control's data. Set the **ShowEmptyPages** property to determine whether to display empty pages in a report.

See Also

TBasedxReportLink.ShowEmptyPages

Font property

[read / write](#)

Specifies report font.

property Font : TFont;

Description

Use the **Font** property to specify a report's font. It is set by default. Descendants can change the value to draw text using unique fonts.

FootersOnEveryPage property

[read / write](#)

Specifies whether footers are printed on every page of a report.

property FootersOnEveryPage: **Boolean**;

Description

Set the **FootersOnEveryPage** property to **True** to display footers on every page of a report.

The default value for this property is **False**

HeadersOnEveryPage property

[read / write](#)

Specifies whether headers are printed on every page of a report.

property HeadersOnEveryPage: **Boolean**;

Description

Set the **HeadersOnEveryPage** property to **True** to display headers on every page of a report.

The default value for this property is **False**.

Index property

[read / write](#)

Determines the index of a link.

property Index : **Integer**;

Description

Use the **Index** property to set or return the index (zero-based) of the report link.

IsCurrentLink property**read / write**

Determines whether a report link is active.

property IsCurrentLink : **Boolean**;

Description

Use the **IsCurrentLink** property to set or return the report link that is previewed by default.

PageCount property**read only**

Returns the number of report pages.

property PageCount : **Integer**;

Description

Use this property to obtain the total number of pages in a report.

See Also

TBasedxReportLink.CurrentPage

PageNumberFormat property**read / write**

Specifies page number format in a report.

type

TdxPageNumberFormat = (pnfNumeral, pnfChars, pnfUpperChars, pnfRoman, pnfUpperRoman);

property PageNumberFormat: TdxPageNumberFormat;

Description

A user may display a header or footer that contains page numbers. Use the **PageNumberFormat** property to specify the format of these page numbers when printed. Available values include:

Value	Description
pnfNumeral	Page numbers are in Arabic numerals.
pnfChars	Page numbers are characters in lower case.
pnfUpperChars	Page numbers are characters in upper case.
pnfRoman	Page numbers are Roman numerals in lower case.
pnfUpperRoman	Page numbers are Roman numerals in upper case.

RealPrinterPage property**read / write**

Determines a printer page object.

property RealPrinterPage: TdxPrinterPage;

Description

Use the **RealPrinterPage** property to determine the TdxPrinterPage object. This object is used to customize different attributes for report pages: Page margins, page size, etc.

RealScaleFactor property

read only

Returns the scale factor used to preview a report page.

property RealScaleFactor: **Integer**;

Description

Read the **RealScaleFactor** property to obtain the scale factor of a report preview.

ReadOnly Property

ScaleFonts property

read / write

Specifies whether to rescale report fonts.

property ScaleFonts: **Boolean**;

Description

Set the **ScaleFonts** property to **True** to rescale report fonts when changing the preview scale factor of a report. If this property is **False**, report font size remains fixed regardless of changes to preview scale factors.

The default value for this property is **True**.

ShowEmptyPages property

read / write

Specifies whether empty pages are displayed in a report.

property ShowEmptyPages: **Boolean**;

Description

Set the **ShowEmptyPages** property to **True** to display empty pages in a report. If this property is **False**, a report does not contain empty pages.

The default value for this property is **False**.

ShowPageHeader property

read / write

Determines whether to add a page header to a report.

property ShowPageHeader: **Boolean**;

Description

Set the **ShowPageHeader** to **True** if you wish to print a series of predefined text strings – such as page number, date, time, etc – at the top of a report page; Otherwise **False**.

The default value for this property is **True**.

StartPageIndex property**read / write**

Determines the index of the first report page.

property StartPageIndex: **Integer**;

Description

Use the **StartPageIndex** property to determine the number of the page from which page numeration begins in a report for the current report link.

The default value for this property is **1**.

StyleManager property**read / write**

Determines the style manager for a report link.

property StyleManager: TdxPrintStyleManager;

Description

Use the **StyleManager** property to determine which style manager is used to provide the basic style information for a report link.

TimeFormat property**read / write**

Specifies the manner in which time information is formatted within a report.

property TimeFormat: **Integer**;

Description

A report link has a set of predefined time formats that can be applied to a report. The **TimeFormat** property specifies a zero-based index of the available formats.

Index	Example
0	2:45 PM
1	2:45:58 PM
2	14:45
3	14:45:58

The default value for this property is **0**.

VisiblePageCount property**read only**

Returns the number of visible pages.

```
property VisiblePageCount: Integer;
```

Description

Use the **VisiblePageCount** property to obtain the total number of visible pages in a report.

ReadOnly Property

PrinterPage property**read / write**

Determines report page properties.

```
property PrinterPage: TdxPrinterPage;
```

Description

Use the **PrinterPage** property to customize report page properties, such as page size, margins, background color, brush, etc. For more information see TdxPrinterPage.

RebuildNeeded property**read only**

Determines whether to rebuild a report.

```
property RebuildNeeded : Boolean;
```

Description

When any property is changed, the report should be rebuilt to reflect the changes. The **RebuildNeeded** property defines whether any changes were made.

See Also

TBasedxReportLink.RebuildReport

ReportHeight property**read only**

Determines the height of a report.

```
property ReportHeight: Integer;
```

Description

Use the **ReportHeight** property to access the height of a report in pixels without binding to page settings. This may be useful when a user implements his or her own OnCustomDrawPage event handler to position a report on pages.

See Also

TBasedxReportLink.ReportWidth

ReportTitle property**read / write**

Determines report title properties.

property ReportTitle: TdxReportTitle;

Description

Use the **ReportTitle** property to customize report title properties, such as font, font color, vertical and horizontal alignment. For more information see TdxReportTitle.

Use the **ReportTitle** property to customize report title appearance. You may specify the report title text, the manner this text is displayed within report pages and change other title properties, such as font, font color, vertical and horizontal alignment, etc. For more information see the **TdxReportTitle** object.

See Also

TBasedxReportLink.ReportTitleMode; TBasedxReportLink.ReportTitleText; TdxReportTitle

ReportTitleMode property**read / write**

Specifies the manner in which a report title is displayed.

type

TdxReportTitleMode = (tmNone, tmOnFirstPage, tmOnEveryTopPage);


property ReportTitleMode : TdxReportTitleMode;

Description

Use the **ReportTitleMode** property to specify where to place a report title. The following values are available:

Values	Meaning
tmNone	Report title does not appear.
tmOnFirstPage	Report title appears on the first page only.
tmOnEveryTopPage	Report title appears on every top page of the report.

The default value for the **ReportTitleMode** property is **tmOnEveryTopPage**. In this mode report titles are situated as displayed in the picture:

**See Also**

TBasedxReportLink.ReportTitle; TBasedxReportLink.ReportTitleText

ReportTitleText property**read / write**

Determines a report's title.

property ReportTitleText : string;

Description

Use the **ReportTitleText** property to specify the text displayed in a report's title.

See Also

TBasedxReportLink.ReportTitle; TBasedxReportLink.ReportTitleMode

ReportWidth property**read only**

Determines the width of a report.

property ReportWidth: **Integer**;

Description

Use the **ReportWidth** property to access the width of a report in pixels without binding to page settings. This may be useful when a user implements his or her own OnCustomDrawPage event handler to position a report on pages.

See Also

TBasedxReportLink.ReportHeight


ShowDesigner property**read / write**

Displays the **Report Designer** window.


property ShowDesigner : **Boolean**;

Description

By default, this property is **False**. It is used at design-time only (as pictured below).



Press the button within the Object Inspector to display the **Report Designer** window:



ShowPageFooter property

[read / write](#)

Determines whether to add page footer to the report.

property ShowPageFooter : **Boolean**;

Description

Set **ShowPageFooter** to **True** if you wish the date and the current page number to be printed at the bottom of the report pages; Otherwise **False**. The default value for this property is **True**.

ShrinkToPageWidth property

[read / write](#)

Determines whether to shrink a report to fit within the bounds of a page.

property ShrinkToPageWidth : **Boolean**;

Description

Set **ShrinkToPageWidth** to **True** if you wish to fit a report within the horizontal bounds of a page. The default value for this property is **False**.

See Also*TBasedxReportLink.UsingShrinkToPageWidthMode***Transparent property****read / write**

Determines whether cells are filled with the default color.

property Transparent : **Boolean**;

Description

If **True**, cells are filled neither with the default report link color nor with the fixed color. Instead, the report background is used. By default, the **Transparent** property is **True**.

See Also*TBasedxReportLink.Color*

TBasedxReportLink Methods

TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
ConstructReport	protected	LinkClass	public
Create	public	LinkModified	protected
DefaultDateFormat	public	LoadFromRegistry	public
DefaultPageNumberFormat	public	MakeDelimiters	protected
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public
InternalRestoreFromOriginal	protected		

BuildPageSetupMenu method

Builds a page setup menu in an application.

Builds a page setup menu in an application.

```
procedure BuildPageSetupMenu(ARootItem: TComponent; AData: Pointer;
  AIncludeDefineItem: Boolean {$IFDEF DELPHI4} = True {$ENDIF});
```

Description

Call the **BuildPageSetupMenu** method to embed a page setup menu in your application.


The *ARootItem* determines a component in which a page setup menu is embedded. This component can be of any type that supports displaying a list of print styles or the "define print style" button.

The *AData* pointer may contain a pointer to any additional arbitrary data.

Set the *AIncludeDefineItem* parameter to **True** to display the "define print style" button or **False** to hide it.

The following examples demonstrate how to use this method.

1. Using the BuildPageSetupMenu method with the standard Delphi menu system



Drop a TdxPrintStyleManager component on a form.

Assign the following code to the OnChangeCurrentStyle event handler:

```
procedure TfmPS2Main.dxPrintStyleManager1ChangeCurrentStyle(Sender :
TObject);
var
    I: Integer;
Begin
    with miFilePageSetup do
        for I := 0 to Items.Count - 1 do
            Items[I].Checked :=
                TBasedxPrintStyle(Items[I].Tag) =
dxPrintStyleManager1.CurrentStyle;
end;
```


Assign the following code to the OnStyleListChanged event handler:

```
procedure TfmPS2Main.dxPrintStyleManager1StyleListChanged(Sender: TObject);
begin
    miFilePageSetup.Clear;
    dxComponentPrinter1.CurrentLink.BuildPageSetupMenu(miFilePageSetup, nil,
True);
end;
```

2. Using the BuildPageSetupMenu method with the ExpressBars menu system

Drop a TdxPrintStyleManager component on a form.

When you use the ExpressBars as your Menu/Toolbar system you must add the dxPSPrVwAdv module in you 'uses' clause.



Assign the following code to the OnChangeCurrentStyle event handler (bliPrintStyles is a TdxBarListItem object):

```
procedure TfmPS2Main.dxPrintStyleManager1ChangeCurrentStyle(
    Sender: TObject);
begin
    bliPrintStyles.ItemIndex := dxPrintStyleManager1.CurrentStyleIndex;
end;
```

Assign the following code to the OnStyleListChanged event handler (bbDefinePrintStyles is a TdxBarButton object):

```
procedure TfmPS2Main.dxPrintStyleManager1StyleListChanged(Sender: TObject);
begin
    dxComponentPrinter1.CurrentLink.BuildPageSetupMenu(bliPrintStyles,
    bbDefinePrintStyles, True);
end;
```

CheckToDesign method

Checks whether to display the **Report Design** window.

```
function CheckToDesign: Boolean;
```

Description

Use the **CheckToDesign** method to determine whether there is a designer for a specific component class.

See Also

TBasedxReportLink.DesignerExists; TBasedxReportLink.DesignReport

ConstructReport method

Builds a report.

```
procedure ConstructReport(AReportCells : TdxReportCells); virtual;  
abstract;
```

Description

The **ConstructReport** method creates the contexts of a report. You must never call it directly. Descendants must override this method to construct a report according to specific properties of a printed component.

Create method

Creates an instance of type TBasedxReportLink.

```
constructor Create(AOwner : TComponent); override;
```

Description

This method creates a TBasedxReportLink object and initializes its properties. Descendants can override this method to allocate any additional memory. The allocated memory should be released when destroying the object.

See Also

TBasedxReportLink.Destroy

DefaultDateFormat method

Returns the default date format.

```
function DefaultDateFormat: Integer;
```

Description

Use the **DefaultDateFormat** method to determine the date format of a report link when the **DateFormat** property is not explicitly set. The **DefaultDateFormat** method returns the date format of the component printer to which a report link belongs.

The **DefaultDateFormat** method returns a zero-based index of the appropriate format.

Index	Example
0	2/14/01
1	Wednesday, February 14, 2001
2	February 14, 2001
3	2/14/2001

4	2001-02-14
5	14-Feb-01
6	2.14.01
7	Wednesday, Feb. 14, 01
8	2.14.2001
9	February , 01
10	Feb-01

DefaultPageNumberFormat method

Returns the default page number format in a report.

type

TdxPageNumberFormat = (pnfNumeral, pnfChars, pnfUpperChars, pnfRoman, pnfUpperRoman);

function DefaultPageNumberFormat: TdxPageNumberFormat;

Description

Use the **DefaultPageNumberFormat** method to determine the page number format of a report link when the **PageNumberFormat** property is not explicitly set. The **DefaultPageNumberFormat** method returns the page number format of the component printer to which a report link belongs.

Available values include:

Value	Description
pnfNumeral	Page numbers are in Arabic numerals.
pnfChars	Page numbers characters in lower case.
pnfUpperChars	Page numbers characters in upper case.
pnfRoman	Page numbers are Roman numerals in lower case.
pnfUpperRoman	Page numbers are Roman numerals in upper case.

DefaultTimeFormat method

Returns the default time format.

function DefaultTimeFormat: **Integer**;

Description

Use the **DefaultTimeFormat** method to determine the time format of a report link when the **TimeFormat** property is not explicitly set. The **DefaultTimeFormat** method returns the time format of the component printer to which a report link belongs.

The DefaultTimeFormat method returns a zero-based index of the appropriate format.

Index	Example
0	2:45 PM
1	2:45:58 PM

2	14:45
3	14:45:58

DesignerExists method

Determines whether a specific component class includes a designer.

```
class function DesignerExists(AComponentClass : TComponentClass ): Boolean;
```

Description

The **DesignerExists** method defines whether there is a designer for a specific component class defined by the *AComponentClass* parameter. **DesignerExist** returns **True**, if such a designer exists.

See Also

TBasedxReportLink.CheckToDesign; *TBasedxReportLink.DesignReport*

DesignReport method

Displays the **Report Designer** window.

```
function DesignReport: Boolean;
```

Description

Call the **DesignReport** method to display the **Report Designer** window for a given component at runtime.

See Also

TBasedxReportLink.CheckToDesign; *TBasedxReportLink.DesignerExists*

Destroy method

Destroys an instance of *TBasedxReportLink*.

```
destructor Destroy; override;
```

Description

This method destroys a *TBasedxReportLink* object. Descendants can override this method to release any additional memory allocated when creating a *TBasedxReportLink* object.

See Also

TBasedxReportLink.Create

DestroyReport method

Destroys a report link.

```
procedure DestroyReport;
```

Description

The **DestroyReport** method sets the Active property to False. It works similarly to the Active property of the TDataSet object.

DoChangeComponent method

Generates the OnChangeComponent event.

```
procedure DoChangeComponent; dynamic;
```

Description

This method is called when changing the Component property of TBasedxReportLink. Descendants can override it to perform specific actions before/after calling the OnChangeComponent event handler.

See Also

TBasedxReportLink.Component; TBasedxReportLink.OnChangeComponent

DoProgress method

Tracks the progress of report creation.

```
procedure DoProgress(Value : Double);
```

Description

Call the **DoProgress** method to obtain the completed portion of an entire job.

DrawCheckBox method

Draws a check box item in a report.

```
procedure DrawCheckBox(Canvas: TCanvas; var R: TRect; Checked, Enabled,  
FlatBorder: Boolean);
```

Description

The **DrawCheckBox** method is designed for drawing a check box on a report's surface. Use this method when performing your own custom drawing.

Parameter	Meaning
Canvas	Determines the drawing surface.
R	Specifies the bound rectangle for drawing.
Checked	Specifies whether the drawn check box is checked (True).
Enabled	Specifies whether the drawn check box is enabled (True).
FlatBorder	Specifies whether the drawn check box has a flat border (True).

DrawEdge method

Draws an edge object in a report.

type

```
TdxCellEdgeMode = (cemSingle, cem3DEffects, cemShadow);
TdxCellEdgeStyle = (cesNone, cesSunken, cesRaised);
TdxCellSide = (csLeft, csTop, csRight, csBottom);
TdxCellSides = set of TdxCellSide;

procedure DrawEdge(Canvas: TCanvas; var R: TRect; EdgeMode:
TdxCellEdgeMode; InnerEdge, OuterEdge: TdxCellEdgeStyle; Sides:
TdxCellSides{$IFDEF DELPHI4} = [csLeft..csBottom]{$ENDIF});
```

Description

The **DrawEdge** method is designed for drawing an edge object on a report's surface. Use this method when performing your own custom drawing.

The *Canvas* parameter determines the drawing surface.

The *R* parameter specifies the bound rectangle for drawing.

The *EdgeMode* parameter specifies the manner in which this edge is drawn. Possible values include:

Value	Description
<i>cemSingle</i>	Edge represents a single line.
<i>cem3DEffects</i>	Edge has a 3D look.
<i>cemShadow</i>	Edge is shadowed.

The *InnerEdge* and *OuterEdge* parameters specify the style of inner and outer edges accordingly. Possible values include:

Value	Description
<i>cesNone</i>	No edge.
<i>cesSunken</i>	Edge is sunken.
<i>cesRaised</i>	Edge is raised.

The *Sides* parameter specifies which edges are drawn. Possible values include:

Value	Description
<i>csLeft</i>	Left edge is drawn.
<i>csTop</i>	Top edge is drawn.
<i>csRight</i>	Right edge is drawn.
<i>csBottom</i>	Bottom edge is drawn.

DrawGraphic method

Draws a graphic object in a report.

```
procedure DrawGraphic(Canvas: TCanvas; var R: TRect; const ClipRect: TRect;
ImageList: {$IFDEF DELPHI4}TCustomImageList {$ELSE}TImageList {$ENDIF};
ImageIndex: Integer; Graphic: TGraphic; GraphicTransparent, Transparent:
Boolean; BkColor: TColor);
```

Description

The **DrawGraphic** method is designed for drawing a graphic object on a report's surface. Use this method when performing your own custom drawing.

The *Canvas* parameter determines the drawing surface.

The *R* parameter specifies the bound rectangle for drawing.

The *ClipRect* parameter specifies the bound rectangle to be drawn.

The *ImageList* parameter specifies the list of images from which graphics are acquired.

The *ImageIndex* parameter specifies the zero-based index of an image within this image list. If you do not use an image list, the *Graphic* parameter allows you to specify the desired image.

Set the *GraphicTransparent* parameter to **True** to print with transparency.

The *BkColor* parameter specifies the background color of an image.

DrawPageFooter method

Draws a page footer in a report.

type

```
TdxPageTitlePart = (tpLeft, tpCenter, tpRight);
```

```
TdxPageTitleParts = set of TdxPageTitlePart;
```

```
procedure DrawPageFooter(APageIndex: Integer; ARect: TRect; ATitleParts:
TdxPageTitleParts; ADrawBackground: Boolean);
```

Description

The **DrawPageFooter** method is intended to draw the page footer on a report's surface. Use this method when performing your own custom drawing.

The *APageIndex* parameter specifies the index of the page for which the footer is drawn.

The *ARect* parameter specifies the bound rectangle for drawing.

The *ATitleParts* parameter specifies which page region a footer is drawn. Possible values include:

Value	Description
tpLeft	Footer is drawn within the left footer region.
tpCenter	Footer is drawn within the center of the page footer region.
tpRight	Footer is drawn within the right footer region.

Set the *ADrawBackground* parameter to **True** to print footer background.

DrawPageHeader method

Draws a page header in a report.

type

```
TdxPageTitlePart = (tpLeft, tpCenter, tpRight);
TdxPageTitleParts = set of TdxPageTitlePart;
procedure DrawPageHeader(APageIndex: Integer; ARect: TRect; ATitleParts:
TdxPageTitleParts; ADrawBackground: Boolean);
```

Description

The **DrawPageHeader** method is intended to draw the page header on a report's surface. Use this method when performing your own custom drawing.

The *APageIndex* parameter specifies the index of the page for which the header is drawn.

The *ARect* parameter specifies the bound rectangle for drawing.

The *ATitleParts* parameter specifies in which page region a header is drawn. Possible values include:

Value	Description
tpLeft	Header is drawn within the left header region.
tpCenter	Header is drawn within center of the page header region.
tpRight	Header is drawn within the right header region.

Set the *ADrawBackground* parameter to **True** to print header background.

DrawSortMark method

Draws a sorting mark (arrow) in a report.

type

```
TdxCellSortOrder = (csoNone, csoUp, csoDown);
procedure DrawSortMark(Canvas: TCanvas; var R: TRect; SortOrder:
TdxCellSortOrder; Mono: Boolean);
```

Description

The **DrawSortMark** method is intended to draw sort order arrows on a report's surface. Use this method when performing your own custom drawing.

The *Canvas* parameter determines the drawing surface.

The *R* parameter specifies the bound rectangle for drawing.

The *SortOrder* parameter specifies sorting arrow type. Possible values include:

Value	Description
csoNone	Sorting arrow is not drawn.
csoUp	Sorting arrow pointing upwards (ascending order).
csoDown	Sorting arrow pointing downwards (descending order).

The *Mono* parameter specifies the manner in which the sorting arrow is drawn; if **True**, the sorting arrow is absolutely flat; if **False**, the sorting arrow is drawn with 3D effects.

DrawText method

Draws text in a report.

type

```

TdxTextAlignX = (taLeft, taCenterX, taRight);
TdxTextAlignY = (taTop, taCenterY, taBottom);

procedure DrawText(Canvas: TCanvas; var R: TRect; AIndent: Integer; const
  Text: string; Font: TFont; BkColor: TColor; TextAlignX: TdxTextAlignX;
  TextAlignY: TdxTextAlignY; FillBackground, Multiline, EndEllipsis:
  Boolean);

```

Description

The **DrawText** method is intended for drawing text on a report's surface. Use this method when performing your own custom drawing.

The *Canvas* parameter determines the drawing surface.

The *R* parameter specifies the bound rectangle for drawing.

The *AIndent* parameter determines text indent relative to the bound rectangle.

The *Text* parameter specifies the text string to draw.

The *Font* parameter specifies text font.

The *BkColor* parameter specifies the background color.

The *TextAlignX* parameter specifies horizontal text alignment, whether it is aligned to the left, right, or centered.

The *TextAlignY* parameter specifies vertical text alignment, whether it is aligned to the top, bottom, or centered.

Set the *FillBackground* parameter to **True** to print the background.

Set the *MultiLine* parameter to **True** to allow text printing across several lines.

Set the *EndEllipsis* parameter to print ellipsis ('...') when text does not fit inside the boundaries of a bound rectangle.

GetFilteredStyles method

Retrieves a list of available print styles.

```

procedure GetFilteredStyles(AStrings: TStrings);

```

Description

The **GetFilteredStyles** method is used to obtain a list of print styles that can be applied to a report. Some print styles defined in the style manager may not be supported by a report link. The **GetFilteredPapers** method generates the **OnFilterStyle** event. By writing implementation for this event a developer can filter out which print styles are to be supported. If no handler for this event has been implemented, all the print styles are supported.

See Also

TBasedxReportLink.OnFilterStyle

GetPageColRowCount method

Determines the number of pages used by a report image, both horizontally and vertically.


```

procedure GetPageColRowCount(var APageColCount, APageRowCount: Integer);

```

Description

The **GetPageColRowCount** method calculates the number of pages used by report images on the basis of current page settings (page size, margins etc.). Once this method is executed, the *APageColCount* parameter contains the number of 'column' pages and the *APageRowCount* parameter contains the numbers of 'row' pages. For instance, the **GetPageColRowCount** method returns 2 in the *APageColCount* parameter and 2 in the *APageRowCount* parameter:



GetSupportedComponentList method

Returns a list of all classes supported by the link.

```
class procedure GetSupportedComponentList(AList : TList);
```

Description

Use the **GetSupportedComponentList** method to ascertain all classes that are supported by the current link.

InternalRestoreDefaults method

Restores default settings for a report.

```
procedure InternalRestoreDefaults; virtual;
```

Description

The **InternalRestoreDefaults** method is used internally to return to default report settings. Descendants can override the **InternalRestoreDefaults** method to restore settings particular to a given report link.

InternalRestoreFromOriginal method

Restores original component settings for a report.

```
procedure InternalRestoreFromOriginal; virtual;
```

Description

The **InternalRestoreFromOriginal** method is used internally to return to original component view settings. Descendants can override the **InternalRestoreFromOriginal** method to restore settings particular to a component of the report link.

IsEmptyReport method

Ascertain whether a report is empty.

```
function IsEmptyReport : Boolean; virtual;
```

Description

The **IsEmptyReport** method returns **True** there are no generated pages in the report; Otherwise **False**.

IsSupportedCompClass method

Determines whether a specific component class is supported by a given report link.

type

```
TComponentClass = class of TComponent;
class function IsSupportCompClass(AComponentClass : TComponentClass):
Boolean;
```

Description

One report link can support several components for printing. For instance, you can override TStringGrid to expand its functionality and use a new grid in your application. If your new class does not differ much from the standard TStringGrid, you can use the same report link for printing. Use the **IsSupportCompClass** method to determine whether a specific component is supported by a given report link. If a specific component is supported, the **IsSupportCompClass** method returns **True**.

LinkClass method

Returns a report link class.

type

```
TdxReportLinkClass = class of TBasedxReportLink;
class function LinkClass: TdxReportLinkClass;
```

Description

Use the **LinkClass** method to obtain the class of a report link.

See Also

TBasedxReportLink.LinkModified

LinkModified method

Determines whether a link was modified.

```
procedure LinkModified(Value : Boolean ); virtual;
```

Description

Use the **LinkModified** method to track changes made to an appropriate link. The *Value* parameter is **True** if the link is modified; otherwise, **False**.

See Also

TBasedxReportLink.LinkClass

LoadFromRegistry method

Loads report link settings from the Registry.

```
procedure LoadFromRegistry(const ARegistryPath: string);
```

Description

Call the **LoadFromRegistry** method to obtain report link settings from the Registry path specified by the *ARegistryPath* parameter. Remember to save appropriate data to the Registry beforehand using the **SaveToRegistry** method.

MakeDelimiters method

Creates delimiters for report pages.

```
procedure MakeDelimiters(AReportCells : TdxReportCells; AHorzDelimiters,  
AVertDelimiters : TList); virtual; abstract;
```

Description

The **MakeDelimiters** method creates bounds that limit report pages. The *AHorzDelimiters* and *AVertDelimiters* parameters specify horizontal and vertical delimiters. When splitting report pages, cells are not split. Descendants can override this method to force report delimiters to behave in a specific manner.

PageReady method

Indicates whether report pages have been generated.

```
function PageReady(APageIndex : Integer): Boolean;
```

Description

Call the **PageReady** method to determine whether the page specified by the *APageIndex* parameter has been generated. This method returns **True** to the *TBasedxReportLink* object.

PageSetup method

Used to activate the **PageSetup** dialog box.

```
function PageSetup: Boolean;
```

Description

This method calls the dxPageSetup method.

See Also

dxPageSetup; TCustomdxComponentPrinter.PageSetup

PageSetupEx method

Displays the "**PageSetup**" dialog window.

```
function PageSetupEx(AActivePageIndex: Integer; APreviewBtnClicked,  
APrintBtnClicked: PBoolean): Boolean;
```

Description

The **PageSetupEx** function is called to display the "**PageSetup**" dialog window.

The *AActivePageIndex* parameter specifies which page of the "**PageSetup**" dialog window is displayed by default.

The *APreviewBtnClicked* and *APrintBtnClicked* parameters specify whether to display the "**Preview...**" and "**Print Preview...**" buttons in this dialog window. These parameters allow a developer to determine which of these buttons was pressed.

Note: If the used parameter is not *nil*, the corresponding button is displayed.

Preview method

Activates the preview form.

```
procedure Preview(Modal : Boolean );
```

Description

Call the **Preview** method to display the preview form on screen. If the *Modal* parameter is True, then the preview form appears as a modal form. The **Preview** method of the *TBasedxReportLink* class sets the active link, calls the *Preview* method of the *TCustomdxComponentPrinter* class and inspects if a valid component is assigned.

See Also

TCustomdxComponentPrinter.Preview

Print method

Prints a report.

type

```
TdxPrintDialogData = ^TdxPrintDialogData;
```

```
procedure Print(AShowDialog : Boolean; APrintDialogData :  
PdxPrintDialogData);
```

Description

Call the **Print** method to print a report to the default printer. The *AShowDialog* parameter determines whether to activate a print dialog before printing. If *AShowDialog* is **True**, the print dialog is active. The *PdxPrintDialogData* parameter is a pointer to the structure that describes properties of a print dialog. The **Print** method of the *TBasedxReportLink* class checks if any valid component is assigned, sets the active link and calls the *Print* method of the *TCustomdxComponentPrinter* class.

Note: *TdxPrintDialogData* is used internally to define printing attributes. Use the *PrintEx*, *PrintPage*, *PrintPages* and *PrintPagesEx* methods instead of the *Print* method.

See Also

TCustomdxComponentPrinter.Print

PrintEx method

Prints report pages.

type

```
TdxPageNumbers = (pnAll, pnEven, pnOdd);
```

```
procedure PrintEx(APageNums : TdxPageNumbers; ACopies : Integer; ACollate : Boolean);
```

Description

Use this method to print all pages in specific range. The *APageNums* parameter specifies pages to print:

pnAll	Prints all pages.
pnEven	Prints only even pages.
pnOdd	Prints only odd pages.

The *ACopies* parameter specifies the number of report copies to print. If the *ACollate* parameter is **True**, then report pages are collated. Unlike the *PrintPagesEx* method, the **PrintEx** method prints all pages of a specific subset. For instance, it prints all even or all odd pages. The **PrintEx** method of the *TBasedxReportLink* class checks if any valid component is assigned, sets the active link and calls the *PrintEx* method of the *TCustomdxComponentPrinter* class.

Note: Include *dxPrnDlg* in the *uses* section of a unit to use type *TdxPageNumbers*.

See Also

TCustomdxComponentPrinter.PrintEx

PrintPages method

Prints specified report pages.

```
procedure PrintPages(const APageIndexes : array of Integer);
```

Description

Use the **PrintPages** method to print specified report pages. The *APageIndexes* parameter specifies the pages to print. Unlike the **Print** method, the **PrintPages** method allows users to print individual pages. Use the **Print** method to print all pages. The **PrintPages** method of the *TBasedxReportLink* class checks if any valid component is assigned, sets the active link and calls the **PrintPages** method of the *TCustomdxComponentPrinter* class.

See Also

TCustomdxComponentPrinter.PrintPages

PrintPagesEx method

Prints specific report pages.

type

```
TdxPageNumbers = (pnAll, pnEven, pnOdd);
```

```
procedure PrintPagesEx(const APageIndexes : array of Integer; ApageNums :  
TdxPageNumbers; ACopies : Integer; ACollate : Boolean);
```

Description

Unlike the **PrintEx** method, the **PrintPagesEx** method provides printing of individual pages within a range. The *APageIndexes* parameter specifies pages to print. *APageNums* determines range of pages to print:

pnAll	Prints all pages.
pnEven	Prints only even pages.
pnOdd	Prints only odd pages.

ACopies specifies the number of copies to print.

ACollate determines whether to collate printed pages. If *ACollate* is **False**, pages are not collated.

The **PrintPagesEx** method of the *TBasedxReportLink* class checks if any valid component is assigned, sets the active link and calls the **PrintPagesEx** method of the *TCustomdxComponentPrinter* class.

Include ***dxPrnDlg*** in the **uses** section of a unit to use type **TdxPageNumbers**.

See Also

TCustomdxComponentPrinter.PrintPagesEx

RebuildReport method

Rebuilds the contents of a report.

```
procedure RebuildReport;
```

Description

This method is useful when it's necessary to re-build a report after making changes to printed components (such as changing data in cells or changing cell layouts). Use the **RebuildReport** method to completely re-build a report. Call the **RebuildReport** method to update a report's contents.

See Also

TBasedxReportLink.RebuildNeeded

RestoreDefaults method

Restores predefined values for report link properties.

```
procedure RestoreDefaults; virtual;
```

Description

This method resets report link properties to their predefined values. Use this method to quickly restore default values. All changes made to properties will be discarded.

See Also

TBasedxReportLink.InternalRestoreDefaults

RestoreFromOriginal method

Restores original component values for report link properties.

```
procedure RestoreFromOriginal; virtual;
```

Description

This method resets report link properties to the original component values. Use this method to quickly restore original component view settings. All changes made to properties will be discarded.

See Also

TBasedxReportLink.InternalRestoreFromOriginal

SaveToRegistry method

Saves report link settings to the Registry.

```
procedure SaveToRegistry(const ARegistryPath: string);
```

Description

Call the **SaveToRegistry** method to store report link settings to the Registry path specified by the *ARegistryPath* parameter. You can later load these settings from the Registry using the **LoadFromRegistry** method.

SetActive method

Initiates report generation.

```
procedure SetActive;
```

Description

The **SetActive** method is the write method of the Active property.

See Also

TBasedxReportLink.Active

ShowDateTimeFormatsDlg method


Displays the "Change Date and Time Formats" dialog window.

Displays the "Change Date and Time Formats" dialog window.

```
function ShowDateTimeFormatsDlg: Boolean;
```

Description

Call the **ShowDateTimeFormatsDlg** method to display a dialog window wherein you can change the date and time formats for a specific report link.




ShowPageNumberFormatsDlg method

Displays the "Change Page Numbering Format" dialog window.

```
function ShowPageNumberFormatsDlg: Boolean;
```

Description

Call the **ShowPageNumberFormatsDlg** method to display a dialog window where you can change the page number format and the first page number.




ShowTitlePropertiesDlg method

Displays the "Report Title" dialog window.

```
function ShowTitlePropertiesDlg: Boolean;
```

Description

Call the **ShowTitlePropertiesDlg** method to display a dialog window wherein you can change a report title, its color, font and alignment. Using this window you can also specify whether to display a title on every page, on the first page only, or not at all.



UsingShrinkToPageWidthMode method

Shrinks a report to fit within the bounds of a page

```
function UsingShrinkToPageWidthMode : Boolean;
```

Description

The **UsingShrinkToPageWidthMode** method is called to set the **ShrinkToPageWidth** property to **True**.

See Also

TBasedxReportLink.ShrinkToPageWidth

TBasedxReportLink Events

TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

OnChangeComponent event

Occurs when the Component property changes.

type

```
TNotifyEvent = procedure(Sender: TObject) of object;
property OnChangeComponent: TNotifyEvent;
```

Description

Write an **OnChangeComponent** event handler to perform specific actions when changing the Component property.

See Also

TBasedxReportLink.Component

OnCustomDrawPageFooter event

Occurs when drawing a page footer.

type

```
TdxCustomDrawReportLinkHFEvent = procedure(Sender: TObject; ACanvas:
TCanvas; APageIndex: Integer; var ARect: TRect; ANom, ADenom: Integer; var
ADefaultDrawText, ADefaultDrawBackground: Boolean) of object;
property OnCustomDrawPageFooter: TdxCustomDrawReportLinkHFEvent;
```

Description

Write an **OnCustomDrawPageFooter** event handler to draw a custom report page footer for a specific report link.

The *ACanvas* parameter determines the drawing surface.

The *APageIndex* parameter specifies the index of the page for which the footer is drawn.

The *ARect* parameter specifies the bound rectangle for drawing.

When using custom draw methods, you must manage image repainting during zoom events. It is always necessary when previewing a report and necessary only for images when printing a report. The *ANom* and *ADenom* parameters determine the coefficient of magnification and demagnification accordingly.

The height of the report footer region is calculated automatically and depends upon the font used, but if the **Font.Size** property changes, you must also handle the **OnMeasureReportTitle** event to correct report title height.

To draw an image in a report footer you should also determine its actual height via the **OnMeasureReportTitle** event.

The *ADefaultDrawText* and *ADefaultDrawBackground* parameters specify whether to draw predefined footer text and background accordingly.

OnCustomDrawPageHeader event

Occurs when drawing a page header.

type

```
TdxCustomDrawReportLinkHFEvent = procedure(Sender: TObject; ACanvas: TCanvas; APageIndex: Integer; var ARect: TRect; ANom, ADenom: Integer; var ADefaultDrawText, ADefaultDrawBackground: Boolean) of object;
property OnCustomDrawPageHeader: TdxCustomDrawReportLinkHFEvent;
```

Description

Write an **OnCustomDrawPageHeader** event handler to draw a custom report page header for a specific report link.

The *ACanvas* parameter determines the drawing surface.

The *APageIndex* parameter specifies the index of the page for which the header is drawn.

The *ARect* parameter specifies the bound rectangle for drawing.

When using custom draw methods, you must manage image repainting during zoom events. It is always necessary when previewing a report and necessary only for images when printing a report. The *ANom* and *ADenom* parameters determine the coefficient of magnification and demagnification accordingly.

The height of the report header region is calculated automatically and depends upon the font used, but if the **Font.Size** property changes, you must also handle the **OnMeasureReportTitle** event to correct report title height.

To draw an image in a report header you should also determine its actual height via the **OnMeasureReportTitle** event.

The *ADefaultDrawText* and *ADefaultDrawBackground* parameters specify whether to draw predefined header text and background accordingly.

OnCustomDrawReportLinkTitle event

Occurs when drawing the report title.

type

```
TdxTextAlignX = ( taLeft, taCenterX, taRight );
TdxTextAlignY = ( taTop, taCenterY, taBottom );
TdxCustomDrawReportLinkTitleEvent = procedure(Sender : TBasedxReportLink; ACanvas : TCanvas; ARect : TRect; ANom, ADenom : Integer; var TextAlignX : TdxTextAlignX; var TextAlignY : TdxTextAlignY; var AColor : TColor; AFont : TFont; var ADone : Boolean) of object;
property OnCustomDrawReportLinkTitle: TdxCustomDrawReportLinkTitleEvent;
```

Description

Write an **OnCustomDrawReportLinkTitle** event handler to draw a specific report title. The *ACanvas* parameter determines the drawing surface. The *ARect* parameter specifies the bound rectangle for drawing.

When using custom draw methods, you must manage image repainting during zoom events. It is always necessary when previewing the report and necessary only for images when printing the report. The *ANom* and *ADenom* parameters determine the coefficient of magnification and demagnification accordingly. The *TextAlignX* and *TextAlignY* parameters specify horizontal and vertical alignment. The *AColor* parameter sets the font color for the report title. The *AFont* parameter sets the font for the report title. The *ADone* parameter determines whether the **OnCustomDrawReportLinkTitle** method processes the entire operation. The Height of the report title region is calculated automatically and depends on the font. To draw an image in the report title you should determine its real height via the *OnMeasureReportLinkTitle* event.

Available values for the *TextAlignX* parameter include:

Values	Meaning
taLeft	Text is left justified. All text lines are at the left edge of an item.
taCenterX	Text is centered within a cell.
taRight	Text is right justified. All text lines are aligned at the right edge of an item.

By default, the **TextAlignX** property value is **taCenterX**.

Available values the *TextAlignY* parameter include:

Values	Meaning
taTop	Text is aligned at the top edge of an item.
taCenterY	Text is vertically centered within a cell.
taBottom	Text is aligned at the bottom of an item's cell.

By default, the **TextAlignY** property value is equal to **taCenterY**.

See Also

TBasedxReportLink.DoCustomdrawReportTitle;TBasedxReportTitle.OnMeasureReportLinkTitle

OnDestroy event

Occurs when a report link is being destroyed.

property OnDestroy: TNotifyEvent;

Description

Write an **OnDestroy** event handler to perform specific actions when a report link is being destroyed.

OnFilterStyle event

Occurs when retrieving the list of available print styles.

type

```
TdxFilterStyleEvent = procedure(Sender: TBasedxReportLink; AStyle:
TBasedxPrintStyle; var ASupported: Boolean) of object;
property OnFilterStyle: TdxFilterStyleEvent;
```

Description

Write an **OnFilterStyle** event handler to filter the list of available print styles.

The *Sender* parameter specifies the report link for which the list of print styles is retrieved.

The *AStyle* parameter is used to access a print style object and acquire its information.

The *AsSupported* parameter specifies whether to include a print style in the list; if this parameter is set to **True**, the *AStyle* style is displayed among available print styles.

OnMeasureReportLinkTitle event

Occurs when drawing the report title before the OnCustomDrawReportLinkTitle event.

type

```
TdxMeasureReportLinkTitleEvent = procedure(Sender : TBasedxReportLink;
var AHeight : Integer) of object;
property OnMeasureReportLinkTitle: TdxMeasureReportLinkTitleEvent;
```

Description

Write an **OnMeasureReportLinkTitle** event handler when you wish to draw an image in the report title. Because the height of a report's title is calculated automatically and depends on the font used, you should specify the real height of the image using the *AHeight* parameter.

See Also

TBasedxReportLink.OnCustomDrawReportLinkTitle

TAbstractdxGridReportLink Object

TAbstractdxGridReportLink is an abstract ancestor for report links to the TStringGrid, TDrawGrid, TCheckListBox, and TListBox components.

Unit

dxPSGrLnks

TAbstractdxGridReportLink = **class**(TBasedxReportLink)

Description

TAbstractdxGridReportLink introduces the properties and methods used by its descendants to provide report links to the standard grid (TStringGrid, TDrawGrid) and list box (TCheckListBox, TListBox) components.

Do not create TAbstractdxGridReportLink instances. Instead, use a TAbstractdxGridReportLink descendant.

Hierarchy

- TObject
 - TPersistent
 - TComponent
 - TBasedxReportLink

TAbstractdxGridReportLink Properties

In TAbstractdxGridReportLink

DrawMode	public / read / write	IncludeFixed	protected / read / write
Effects3D	protected / read / write	Multiline	protected / read / write
EndEllipsis	protected / read / write	OddColor	protected / read / write
EvenColor	protected / read / write	OddFont	protected / read / write
EvenFont	protected / read / write	OnlySelected	protected / read / write
FixedColor	protected / read / write	RowAutoHeight	protected / read / write
FixedFont	protected / read / write	Soft3D	protected / read / write
FixedTransparent	protected / read / write	SupportedCustomDraw	public / read / write
GridLineColor	protected / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	public / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	public / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	public / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	public / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

DrawMode property

read / write

Determines the manner in which a component is displayed in a report.

type



```
TdxGridDrawMode = (gdmStrict, gdmOddEven, gdmChess, gdmBorrowSource);
```

property DrawMode: TdxGridDrawMode;

Description

Use the **DrawMode** property to select the manner in which a component is printed in a report.

Value	Description
gdmStrict	All colors look exactly as specified in the designer.
gdmOddEven	Used to differentiate the colors of even and odd rows of your report. These colors are specified by the EvenColor (for even lines) and OddColor (for odd lines) properties.
gdmChess	Used to differentiate report colors like a chess table. These colors are specified by the EvenColor (for even lines) and OddColor (for odd lines) properties.
gdmBorrowSource	Used when the report color scheme should look exactly as in an application despite any changes made in the designer.



The default value for this property is **gdmStrict**.

Effects3D property

[read / write](#)

Specifies whether grid fixed cells have a 3D look when printed.

property Effects3D: **Boolean**;

Description

Set the **Effects3D** property to **True** to display fixed grid cells 3 dimensionally in a report. Use the Soft3D property to specify the exact look & feel of raised cells. If the **Effects3D** property is **False**, 3D look is not applied to fixed grid cells.

	1	2	3
1	1	2	3
2	2	4	6
3	3	6	9

Effects3D = False

	1	2	3
1	1	2	3
2	2	4	6
3	3	6	9

Effects3D = True
Soft3D = False

The default value for this property is **False**.

See Also

TAbstractdxGridReportLink.Soft3D

EndEllipsis property

[read / write](#)

Specifies whether an ellipsis is displayed at the end of text.

property EndEllipsis: **Boolean**;

Description

When the **EndEllipsis** property is set to **True**, an ellipsis ('...') is drawn to indicate to users that text does not fit inside the boundaries of an appropriate region.

☐ AD - Andorra
☒ AE - United Arab Em...
☐ AF - Afghanistan
☒ AG - Antigua and B...
☐ AI - Anguilla
☐ AL - Albania

EndEllipsis = True

If the **EndEllipsis** property is **False**, text will be cut off at the rightmost end.

☐ AD - Andorra
☒ AE - United Arab Emirs
☐ AF - Afghanistan
☒ AG - Antigua and Bark
☐ AI - Anguilla
☐ AL - Albania

EndEllipsis = False

The default value for this property is **False**.

EvenColor property


[read / write](#)

Specifies the background color used for even rows in a report.

```
property EvenColor: TColor;
```

Description

Use the **EvenColor** property to specify the background color for even data rows of a printed component. This property is in effect only when the DrawMode property is set to **gdmOddEven** (or to **gdmChess** when printing the TDrawGrid or TStringGrid components).



The default value for this property is **clWhite**.

See Also

TAbstractdxGridReportLink.DrawMode; *TAbstractdxGridReportLink.EventFont;*
TAbstractdxGridReportLink.OddColor; *TAbstractdxGridReportLink.OddFont*

EvenFont property


[read / write](#)

Specifies even row font in a report.

```
property EvenFont: TFont;
```

Description

Use the **EvenFont** property to specify the text font of even data rows when printing a component. This property is in effect only when the DrawMode property is set to **gdmOddEven** (or to **gdmChess** when printing the TDrawGrid or TStringGrid components).



See Also

TAbstractdxGridReportLink.DrawMode; *TAbstractdxGridReportLink.EvenColor;*
TAbstractdxGridReportLink.OddColor; *TAbstractdxGridReportLink.OddFont*

FixedColor property


[read / write](#)

Specifies fixed cell color in a report.

property FixedColor: TColor;

Description

Use the **FixedColor** property to specify the background color of fixed rows and columns when printing standard grid components (TDrawGrid or TStringGrid). This color may differ from the original color. The **FixedColor** property is not in effect when the DrawMode property is set to **gdmBorrowSource**.



The default value for this property is **clSilver**.

See Also

TAbstractdxGridReportLink.DrawMode;
TAbstractdxGridReportLink.FixedTransparent;
TAbstractdxGridReportLink.OnlySelected

TAbstractdxGridReportLink.FixedFont;
TAbstractdxGridReportLink.IncludeFixed;


FixedFont property[read / write](#)

Specifies fixed cell font in a report.

property FixedFont: TFont;

Description

Use the **FixedFont** property to specify the font of fixed cells when printing standard grid components (TDrawGrid or TStringGrid). This font may differ from the original font. The **FixedFont** property is not in effect when the DrawMode property is set to **gdmBorrowSource**.

**See Also**

TAbstractdxGridReportLink.FixedColor;
TAbstractdxGridReportLink.FixedTransparent;
TAbstractdxGridReportLink.IncludeFixed; *TAbstractdxGridReportLink.OnlySelected*


FixedTransparent property[read / write](#)

Specifies whether fixed cells are transparent in a report.


property FixedTransparent: Boolean;

Description

Set the **FixedTransparent** property to **True** to display fixed cells transparently in a report when printing standard grid components (TDrawGrid or TStringGrid).



If the **FixedTransparent** property is **False**, fixed cells are printed using the component color. The **FixedTransparent** property is not in effect when the DrawMode property is set to **gdmBorrowSource**.



The default value for this property is **False**.

See Also

*TAbstractdxGridReportLink.FixedColor; TAbstractdxGridReportLink.FixedFont;
TAbstractdxGridReportLink.IncludeFixed; TAbstractdxGridReportLink.OnlySelected*

GridLineColor property


[read / write](#)

Specifies the line color of grid lines in a report.

property GridLineColor: TColor;

Description

Use the **GridLineColor** property to specify the color of grid lines in a report when printing standard grid components (TDrawGrid or TStringGrid). This color may differ from the original line color.



The default value for this property is **clBlack**.

IncludeFixed property


[read / write](#)

Specifies whether fixed cells are displayed in a report.


property IncludeFixed: **Boolean**;

Description

Set the **IncludeFixed** property to **True** to include fixed cells in a report when printing grid selected cells. The **IncludeFixed** property is in effect if the **OnlySelected** property is set to **True**.



If the **IncludeFixed** property is **False**, fixed cells are not displayed in a report when printing selected cells



The default value for this property is **True**.

See Also

*TAbstractdxGridReportLink.FixedColor; TAbstractdxGridReportLink.FixedFont;
TAbstractdxGridReportLink.FixedTransparent; TAbstractdxGridReportLink.OnlySelected*

Multiline property**read / write**

Specifies the manner in which data appears within a control cell when printing a report.

property Multiline: **Boolean**;

Description

Use the **Multiline** property to specify the manner in which data appears in a report. If the **Multiline** property is **False**, the portion of data that fits inside the boundaries of a cell is displayed. If the **MultiLine** property is set to **True**, data can occupy several lines.

The default value for this property is **False**.


OddColor property**read / write**

Specifies the background color for odd rows in a report.

property OddColor: **TColor**;

Description

Use the **OddColor** property to specify the background color of odd value rows when printing a component. This property is in effect only when the DrawMode property is set to **gdmOddEven** (or to **gdmChess** when printing the TDrawGrid or TStringGrid components).



The default value for this property is **clWhite**.

See Also

*TAbstractdxGridReportLink.DrawMode; TAbstractdxGridReportLink.EvenColor;
TAbstractdxGridReportLink.EvenFont; TAbstractdxGridReportLink.OddFont*


OddFont property**read / write**

Specifies the text font of odd rows in a report.

property OddFont: TFont;

Description

Use the **OddFont** property to specify the text font of odd value rows when printing a component. This property is in effect only when the DrawMode property is set to **gdmOddEven** (or to **gdmChess** when printing the TDrawGrid or TStringGrid components).

**See Also**

*TAbstractdxGridReportLink.DrawMode; TAbstractdxGridReportLink.EvenColor;
TAbstractdxGridReportLink.EvenFont; TAbstractdxGridReportLink.OddColor*

OnlySelected property**read / write**

Specifies whether a report includes selected cells only.

property OnlySelected: Boolean;

Description

Set the **OnlySelected** property to **True** to display only selected items in a report. If the **OnlySelected** property is **False**, the report includes all value items (cells) contained in the component.

The default value for this property is **False**.

See Also

TAbstractdxGridReportLink.IncludeFixed

RowAutoHeight property**read / write**

Determines whether to calculate cell height automatically.

property RowAutoHeight: **Boolean**;

Description

Setting the **RowAutoHeight** property to **True** forces all cells in a row to have the maximum height dependent upon the text font.

The default value for this property is **False**.

Soft3D property**read / write**

Specifies whether fixed grid cells have a slight 3D effect in a report.

property Soft3D: **Boolean**;

Description

Set the **Soft3D** property to **True** to draw fixed grid cells using a light 3D look in a report.

	1	2	3
1	1	2	3
2	2	4	6
3	3	6	9

Effects3D = True
Soft3D = True

	1
1	1
2	2

If the **Soft3D** property is **False**, fixed cell look & feel depends upon the Effects3D property.

	1	2	3
1	1	2	3
2	2	4	6
3	3	6	9

Effects3D = True
Soft3D = False

	1	2	3
1	1	2	3
2	2	4	6
3	3	6	9

Effects3D = False

The default value for this property is **True**.

SupportedCustomDraw property

read / write

Specifies whether a custom painting procedure is enabled.

property SupportedCustomDraw: **Boolean**;

Description

If the **SupportedCustomDraw** property is **False**, the default painting process is used to paint a component in a report. Set this property to **True** to use your own custom painting procedure.

The default value for this property is **False**.

See Also

TdxCustomListBoxReportLink.OnCustomDrawItem; *TdxDrawGridReportLink.OnCustomDrawCell*;
TdxStringGridReportLink.OnCustomDrawCell

TAbstractdxGridReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TAbstractdxGridReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TCustomdxGridReportLink Object

The **TCustomdxGridReportLink** object represents the base class used to print both the TStringGrid and TDrawGrid components.

Unit

dxPSGrLnks

```
TCustomdxGridReportLink = class(TAbstractdxGridReportLink)
```

Description

TCustomdxGridReportLink is a common ancestor for both the TdxStringGridReportLink and TdxDrawGridReportLink objects. It provides the functionality necessary to print the TStringGrid and TDrawGrid components.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
        AbstractdxGridReportLink
```

TCustomdxGridReportLink Properties

In TCustomdxGridReportLink

CustomGrid	protected / read only
Options	public / read / write

Derived from TAbstractdxGridReportLink

DrawMode	public / read / write	IncludeFixed	public / read / write
Effects3D	public / read / write	Multiline	protected / read / write
EndEllipsis	protected / read / write	OddColor	public / read / write
EvenColor	public / read / write	OddFont	public / read / write
EvenFont	public / read / write	OnlySelected	public / read / write
FixedColor	public / read / write	RowAutoHeight	protected / read / write
FixedFont	public / read / write	Soft3D	public / read / write
FixedTransparent	public / read / write	SupportedCustomDraw	public / read / write
GridLineColor	public / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	public / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	public / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	public / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	public / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	public / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

CustomGrid property

read only

Returns a TCustomGrid object.

property CustomGrid: TCustomGrid;

Description

This property returns a TCustomGrid object that contains all the functionality to control the look & feel of the TDrawGrid or TStringGrid components.

Options property

[read / write](#)

Specifies which grid lines are included in a report.

type

```
TdxGridPaintOption = (gpoBorder, gpoHorzLines, gpoVertLines,  
gpoFixedHorzLines, gpoFixedVertLines);
```

```
TdxGridPaintOptions = set of TdxGridPaintOption;
```

property Options: TdxGridPaintOptions;

Description

Use the **Options** property to specify the grid lines included in a report. Available options include:

Value	Description
gpoBorder	If active, borderlines are printed.
gpoHorzLines	If active, horizontal lines are printed.
gpoVertLines	If active, vertical lines are printed.
gpoFixedHorzLines	If active, horizontal lines for fixed columns are printed.
gpoFixedVertLines	If active, vertical lines for fixed columns are printed.

By default, all options are active.

TCustomdxGridReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TCustomdxGridReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TStdGridReportLink Object

The **TStdGridReportLink** object represents the class used to print both the TStringGrid and TDrawGrid components.

Unit

dxPStdGrLnk

```
TStdGridReportLink = class(TCustomGridReportLink)
```

Description

TStdGridReportLink is a common ancestor for both the TdxStringGridReportLink and TdxDrawGridReportLink objects. It provides some methods necessary to print the TStringGrid and TDrawGrid components.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
        AbstractdxGridReportLink
          TCustomGridReportLink
```

TStddxGridReportLink Properties

Derived from TCustomdxGridReportLink

CustomGrid	protected / read only
Options	public / read / write

Derived from TAbstractdxGridReportLink

DrawMode	public / read / write	IncludeFixed	public / read / write
Effects3D	public / read / write	Multiline	protected / read / write
EndEllipsis	protected / read / write	OddColor	public / read / write
EvenColor	public / read / write	OddFont	public / read / write
EvenFont	public / read / write	OnlySelected	public / read / write
FixedColor	public / read / write	RowAutoHeight	protected / read / write
FixedFont	public / read / write	Soft3D	public / read / write
FixedTransparent	public / read / write	SupportedCustomDraw	public / read / write
GridLineColor	public / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	public / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	public / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	public / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	public / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	public / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

TStddxGridReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TStddxGridReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxSGrReportLinkDesignWindow Object

Unit

dxPSSgrLnk

```
TdxSGrReportLinkDesignWindow = class(TAbstractdxReportLinkDesignWindow);
```

Description

The **TdxSGrReportLinkDesignWindow** object is used as the designer of the TdxStringGridReportLink object. It appears as a window that provides customization of reports created via the TdxStringGridReportLink object.

Hierarchy

```
Object
  TPersistent
    TComponent
      TControl
        TWinControl
          TScrollingWinControl
            TCustomForm
              TForm
                TAbstractdxReportLinkDesigner
```

TdxStringGridReportLink Object

TdxStringGridReportLink is a report link used to print the TStringGrid component.

Unit

dxPStdGrLnk

```
TdxStringGridReportLink = class(TStddxGridReportLink);
```

Description

Used to print the TStringGrid component. The **TdxStringGridReportLink** object uses a designer of type TdxSGrReportLinkDesignWindow to customize the layout of pages with TStringGrid data.

Hierarchy

```
TBasedxReportLink
  TAbstractdxGridReportLink
    TCustomdxGridReportLink
      TStddxGridReportLink
```

TdxStringGridReportLink Properties

TdxStringGridReportLink

StringGrid	public / read only	TextAlignY	published / read / write
TextAlignX	published / read / write		

Derived from TCustomdxGridReportLink

CustomGrid	protected / read only
Options	published / read / write

Derived from TAbstractdxGridReportLink

DrawMode	published / read / write	IncludeFixed	published / read / write
Effects3D	published / read / write	Multiline	published / read / write
EndEllipsis	published / read / write	OddColor	published / read / write
EvenColor	published / read / write	OddFont	published / read / write
EvenFont	published / read / write	OnlySelected	published / read / write
FixedColor	published / read / write	RowAutoHeight	published / read / write
FixedFont	published / read / write	Soft3D	published / read / write
FixedTransparent	published / read / write	SupportedCustomDraw	published / read / write
GridLineColor	published / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	published / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

StringGrid property

read only

Determines a TStringGrid object printed within a report.

```
property StringGrid: TStringGrid;
```

Description

This property returns the **TStringGrid** object printed by a printing component.

TextAlignX property

[read / write](#)

Specifies horizontal text alignment in a cell.

type

```
TdxTextAlignX = ( taLeft, taCenterX, taRight );
```

```
property TextAlignX : TdxTextAlignX;
```

Description

Use the **TextAlignX** property to specify horizontal text alignment. Available values include:

Values	Meaning
taLeft	Text is left justified. All Text lines are aligned by the left edge of a cell.
taCenterX	Text is centered within a cell.
taRight	Text is right justified. All text lines are aligned by the right edge of a cell.

By default, the **TextAlignX** property value is **taLeft**.

See Also

*TdxStringGridReportLink.InternalRestoreDefaults;TdxStringGridReportLink.TextAlignY;
TdxStringGridReportLink.InternalRestoreFromOriginal*

TextAlignY property

[read / write](#)

Specifies vertical text alignment in a cell.

type

```
TdxTextAlignY = ( taTop, taCenterY, taBottom );
```

```
property TextAlignY : TdxTextAlignY;
```

Description

Use the **TextAlignY** property to specify vertical text alignment in a cell. Available values include:

Values	Meaning
taTop	Text is aligned at the top of a cell.
taCenterY	Text is vertically centered within a cell.

taBottom Text is aligned at the bottom of a cell.

By default, the **TextAlignY** property value is **taCenterY**.

See Also

TdxStringGridReportLink.InternalRestoreDefaults;TdxStringGridReportLink.TextAlignX;
TdxStringGridReportLink.InternalRestoreFromOriginal

TdxStringGridReportLink Methods

TdxStringGridReportLink

InternalRestoreDefaults **protected**

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
ConstructReport	protected	LinkClass	public
Create	public	LinkModified	protected
DefaultDateFormat	public	LoadFromRegistry	public
DefaultPageNumberFormat	public	MakeDelimiters	protected
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public
InternalRestoreFromOriginal	protected		

InternalRestoreDefaults method

Restores default report settings.

procedure InternalRestoreDefaults; **override**;

Description

The **InternalRestoreDefaults** method is used internally to restore default report settings specific to the string grid report link.

See Also

TdxStringGridReportLink.InternalRestoreFromOriginal

TdxStringGridReportLink Events

TdxStringGridReportLink

OnCustomDrawCell published

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

OnCustomDrawCell event

Occurs when drawing a cell.

type

```
TdxTextAlignX = (taLeft, taCenterX, taRight);
TdxTextAlignY = (taTop, taCenterY, taBottom);
TdxCustomDrawTextCellEvent = procedure(Sender: TBasedxReportLink; ACol, ARow:
Integer; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect; var AText:
string; AFont: TFont; var AColor: TColor; var ATextAlignX: TdxTextAlignX;
var ATextAlignY: TdxTextAlignY; var ADone: Boolean) of object;
property OnCustomDrawCell: TdxCustomDrawTextCellEvent;
```

Description

Write an **OnCustomDrawCell** event handler to draw a cell. The *ACanvas* parameter determines the drawing canvas.

Value	Description
ABoundsRect	Rectangular cell area including borders.
AClientRect	Rectangular cell area excluding borders.
ACol	Column of a cell.
ARow	Row of a cell.
AText	Context of a cell. It can be changed, if necessary.
AColor	Specifies background color. It can be changed, if necessary.
AFont	Font of a cell. It can be changed, if necessary.
ATextAlignX	Horizontal text alignment within a cell. It can be changed, if necessary.
ATextAlignY	Vertical text alignment within a cell. It can be changed, if necessary.
ADone	Determines whether the OnCustomDrawCell event handler entirely draws a cell. If <i>ADone</i> is True , the default drawing procedure is not called.

Note: This property is only accessible if the **SupportedCustomDraw** property is set to **True**.

TdxDGrReportLinkDesignWindow Object

Unit

dxPSDGrLnk

```
TdxDGrReportLinkDesignWindow = class(TAbstractdxReportLinkDesignWindow);
```

Description

The **TdxDGrReportLinkDesignWindow** object is used as a designer of the TdxDrawGridReportLink object. The **TdxDGrReportLinkDesignWindow** object appears as a window that provides customization of reports created via the TdxDrawGridReportLink object.

Hierarchy

```
Object
  TPersistent
    TComponent
      TControl
        TWinControl
          TScrollingWinControl
            TCustomForm
              TForm
                TAbstractdxReportLinkDesigner
```

TdxDrawGridReportLink Object

TdxDrawGridReportLink is a report link to print the TDrawGrid component.

Unit

dxPSStdGrLnk

```
TdxDrawGridReportLink = class(TStddxGridReportLink);
```

Description

The **TdxDrawGridReportLink** object allows you to print the TDrawGrid component. It uses the TdxDGrReportLinkDesignWindow object to customize report page layout.

Hierarchy

```

  TObject
    TPersistent
      TComponent
        TBasedxReportLink
          TAbstractdxGridReportLink
            TCustomdxGridReportLink
              TStddxGridReportLink
```

TdxDrawGridReportLink Properties

TdxDrawGridReportLink

DefaultDrawing	published / read / write
DrawGrid	public / read only

Derived from TCustomdxGridReportLink

CustomGrid	protected / read only
Options	published / read / write

Derived from TAbstractdxGridReportLink

DrawMode	published / read / write	IncludeFixed	published / read / write
Effects3D	published / read / write	Multiline	protected / read / write
EndEllipsis	protected / read / write	OddColor	published / read / write
EvenColor	published / read / write	OddFont	public / read / write
EvenFont	published / read / write	OnlySelected	published / read / write
FixedColor	published / read / write	RowAutoHeight	protected / read / write
FixedFont	published / read / write	Soft3D	published / read / write
FixedTransparent	published / read / write	SupportedCustomDraw	published / read / write
GridLineColor	published / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	published / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write		

DefaultDrawing property

read / write

Specifies whether grid cells are drawn automatically.

property DefaultDrawing: **Boolean**;

Description

Set the **DefaultDrawing** property to **True** to automatically draw grid cells. Set the **DefaultDrawing** property to **False** to provide custom drawing events with the help of an **OnCustomDrawCell** event handler.

The default value for this property is **True**.

See Also

TdxDrawGridReportLink.OnCustomDrawCell

DrawGrid property

read only

Determines a **TDrawGrid** object printed within a report.

property DrawGrid: TDrawGrid;

Description

This property returns a **TDrawGrid** object printed by a printing component.

TdxDrawGridReportLink Methods

TdxDrawGridReportLink

InternalRestoreDefaults	protected
InternalRestoreFromOriginal	protected

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
ConstructReport	protected	LinkClass	public
Create	public	LinkModified	protected
DefaultDateFormat	public	LoadFromRegistry	public
DefaultPageNumberFormat	public	MakeDelimiters	protected
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public

InternalRestoreDefaults method

Restores default report settings.

procedure InternalRestoreDefaults; **override**;

Description

The **InternalRestoreDefaults** method is used internally to restore default report settings specific to the draw grid report link: The GridLineColor property is set to **clBtnShadow**, all options are enabled.

See Also

TdxDrawGridReportLink.InternalRestoreFromOriginal

InternalRestoreFromOriginal method

Restores original component settings for a report.

procedure InternalRestoreFromOriginal; **override**;

Description

The **InternalRestoreFromOriginal** method is used internally to return the draw grid component's view settings, such as fixed color and enabled options, to its original state.

See Also

TdxDrawGridReportLink.InternalRestoreFromOriginal

TdxDrawGridReportLink Events

In TdxDrawGridReportLink

OnCustomDrawCell published

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

OnCustomDrawCell event

Occurs when drawing a cell.

type

```
TdxCustomDrawCellEvent = procedure(Sender: TBasedxReportLink; ACol, ARow: Integer; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect) of object;
property OnCustomDrawCell: TdxCustomDrawCellEvent;
```

Description

Write an **OnCustomDrawCell** event handler to draw a cell. The *ACanvas* parameter determines the drawing surface.

Value	Description
ABoundsRect	Rectangular cell area including borders.
AClientRect	Rectangular cell area excluding borders.
ACol	Column of a cell.
ARow	Row of a cell.

Note: This property is only accessible if the **SupportedCustomDraw** property is set to **True**.

TdxCustomListBoxReportLink Object

The **TdxCustomListBoxReportLink** object represents the base class used to print both the TListBox and TCheckListBox components.

Unit

dxPSGrLnks

```
TdxCustomListBoxReportLink = class(TAbstractdxGridReportLink)
```

Description

TdxCustomListBoxReportLink is a common ancestor for both the TdxListBoxReportLink and TdxCheckListBoxReportLink objects. It provides the functionality necessary to print the TListBox and TCheckListBox components.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
        AbstractdxGridReportLink
```

TdxCustomListBoxReportLink Properties

In TdxCustomListBoxReportLink

AutoWidth	public / read / write	TextAlignY	public / read / write
CustomListBox	protected / read / write	Width	public / read / write
TextAlignX	public / read / write		

Derived from TAbstractdxGridReportLink

DrawMode	public / read / write	IncludeFixed	protected / read / write
Effects3D	protected / read / write	Multiline	protected / read / write
EndEllipsis	public / read / write	OddColor	protected / read / write
EvenColor	protected / read / write	OddFont	protected / read / write
EvenFont	protected / read / write	OnlySelected	public / read / write
FixedColor	protected / read / write	RowAutoHeight	protected / read / write
FixedFont	protected / read / write	Soft3D	protected / read / write
FixedTransparent	protected / read / write	SupportedCustomDraw	public / read / write
GridLineColor	public / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	public / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	public / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	public / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	public / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

CustomListBox property

read / write

Returns a TCustomListBox object.

```
property CustomListBox: TCustomListBox;
```

Description

This property returns a TCustomListBox object that is the base class for list-box objects. TCustomListBox descendants inherit the basic functionality of TCustomListBox.

AutoWidth property**read / write**

Specifies whether list box items automatically size themselves to the width of their text.

property AutoWidth: **Boolean**;

Description

Set the **AutoWidth** property to **True** to entirely display text within list box items in a report. If list box item width is larger than the longest text width, it does not change. If the **AutoWidth** property is set to **False**, list box item width does not change as well.

The default value for this property is **True**.

TextAlignX property**read / write**

Specifies horizontal text alignment within an item.

type

TdxTextAlignX = (taLeft, taCenterX, taRight);

property TextAlignX: TdxTextAlignX;

Description

Use the **TextAlignX** property to specify horizontal text alignment for an item. Available values include:

Value	Description
taLeft	Text is left justified.
taCenterX	Text is centered within a cell.
taRight	Text is right justified.

The default value for this property is **taLeft**.

TextAlignY property**read / write**

Specifies vertical text alignment.

type

TdxTextAlignY = (taTop, taCenterY, taBottom);

property TextAlignY: TdxTextAlignY;

Description

Use the **TextAlignY** property to specify vertical text alignment within an item. Available values include:

Value	Description
taTop	Text is aligned to the top edge of an item.
taCenterY	Text is vertically centered within a cell.
taBottom	Text is aligned to the bottom of an item cell.

The default value for this property is **taCenterY**.

Width property

[read / write](#)

Specifies the horizontal size of a list box in pixels.

property Width: **Integer**;

Description

Use the **Width** property to specify list box width in a report.

TdxCustomListBoxReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TdxCustomListBoxReportLink Events

In TdxCustomListBoxReportLink

OnCustomDrawItem **protected**

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

OnCustomDrawItem event

Occurs when drawing a specific item within a list box control.

type

```
TdxTextAlignX = (taLeft, taCenterX, taRight);
TdxTextAlignY = (taTop, taCenterY, taBottom);
TdxCustomDrawItemEvent = procedure(Sender: TBasedxReportLink; Index:
Integer; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect; var AText:
string; AFont: TFont; var AColor: TColor; var ATextAlignX: TdxTextAlignX;
var ATextAlignY: TdxTextAlignY; var ADone: Boolean) of object;
```

property OnCustomDrawItem: TdxCustomDrawItemEvent;

Description

Write an **OnCustomDrawItem** event handler to draw a specific listbox item based on your specific requirements. The *ACanvas* parameter determines the drawing surface.

Parameter	Meaning
ACanvas	Determines canvas for drawing.
ABoundsRect	Specifies rectangle including borders for drawing.
AClientRect	Specifies rectangle excluding borders for drawing.
AText	Determines text that is drawn within an item.
AFont	Specifies the font.
AColor	Specifies the background color of an item.
ATextAlignX	Specifies horizontal text alignment within an item.
ATextAlignY	Specifies vertical text alignment within an item.
ADone	Determines whether the OnCustomDrawItem event handler entirely draws an item. If ADone is True , the default drawing procedure is not called.

Available values for *ATextAlignX* include:

taLeft	Text is left justified.
taCenterX	Text is centered within an item.

taRight Text is right justified.

Available values for *ATextAlignY* include:

taTop Text is aligned to the top edge of an item.

taCenterY Text is vertically centered within an item.

taBottom Text is aligned to the bottom edge of an item.

In order to specify the color, font, text or alignment, used for drawing the header of a specific column, set proper values for the *AColor*, *AFont*, *AText*, *ATextAlignX* or *ATextAlignY* parameters and set *ADone* to **False** within the **OnCustomDrawItem** event handler.

TdxChlBxReportLinkDesignWindow Object

Unit

dxPSChlBxLnk

```
TdxCLbReportLinkDesigner = class(TAbstractdxReportLinkDesignWindow);
```

Description

TdxCLbReportLinkDesigner is used as a designer for the TdxCheckListBoxReportLink object. The **TdxCLbReportLinkDesigner** object appears as a window that provides customization of the report created with the help of the TdxCheckListBoxReportLink object.

Hierarchy

```
Object
  TPersistent
    TComponent
      TControl
        TWinControl
          TScrollingWinControl
            TCustomForm
              TForm
                TAbstractdxReportLinkDesigner
```

TdxCheckListBoxReportLink Object

TdxCheckListBoxReportLink is a report link used to print a TCheckListBox component.

Unit

dxPSChlbxLnk

```
TdxCheckListBoxReportLink = class(TdxCustomListBoxReportLink);
```

Description

The **TdxCheckListBoxReportLink** object allows you to print a TCheckListBox component. The **TdxCheckListBoxReportLink** object uses the TdxChlbxReportLinkDesignWindow object to customize pages created from the TCheckListBox component.

Hierarchy

```

  TObject
    TPersistent
      TComponent
        TBasedxReportLink
          TAbstractdxGridReportLink
            TdxCustomListBoxReportLink
```

TdxCheckListBoxReportLink Properties

TdxCheckListBoxReportLink

CheckListBox	public / read only	Options	published / read / write
--------------	--------------------	---------	--------------------------

Derived from TdxCustomListBoxReportLink

AutoWidth	public / read / write	TextAlignY	public / read / write
CustomListBox	protected / read / write	Width	published / read / write
TextAlignX	public / read / write		

Derived from TAbstractdxGridReportLink

DrawMode	public / read / write	IncludeFixed	protected / read / write
Effects3D	protected / read / write	Multiline	published / read / write
EndEllipsis	published / read / write	OddColor	published / read / write
EvenColor	published / read / write	OddFont	published / read / write
EvenFont	published / read / write	OnlySelected	public / read / write
FixedColor	protected / read / write	RowAutoHeight	published / read / write
FixedFont	protected / read / write	Soft3D	protected / read / write
FixedTransparent	protected / read / write	SupportedCustomDraw	published / read / write
GridLineColor	public / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

CheckListBox property

read only

Specifies the check list box whose items are to be printed.

property CheckListBox : TCheckListBox;

Description

This property specifies the TCheckListBox object for which a report is generated.

Options property

[read / write](#)

Determines the look of a check list box in a report.

type

TdxCheckListBoxPaintOption = (chlbxpoBorder, chlbxpoHorzLines, chlbxpoFlatCheckMarks);

TdxCheckListBoxPaintOptions = **set of** TdxCheckListBoxPaintOption;

property Options : TdxCheckListBoxPaintOptions;

Description

Use the **Options** property to specify which type of check list box lines is included in the report. Available values include:

Values	Meaning
chlbxpoBorder	If active, border lines are included.
chlbxpoHorzLines	If active, horizontal lines between items are printed.
chlbxpoFlatCheckMarks	If active, check boxes appear flat in the report. Otherwise, they have 3D borders.

The default value for the **Options** property is [chlbxpoBorder, chlbxpoHorzLines, chlbxpoFlatCheckMarks].

See Also

TdxCheckListBoxReportLink.InternalRestoreDefaults;

TdxCheckListBoxReportLink.InternalRestoreFromOriginal

TdxCheckListBoxReportLink Methods

TdxCheckListBoxReportLink

InternalRestoreDefaults	protected	InternalRestoreFromOriginal	protected
-------------------------	------------------	-----------------------------	------------------

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
ConstructReport	protected	LinkClass	public
Create	public	LinkModified	protected
DefaultDateFormat	public	LoadFromRegistry	public
DefaultPageNumberFormat	public	MakeDelimiters	protected
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public

InternalRestoreDefaults method

Restores default report settings.

procedure InternalRestoreDefaults; **override**;

Description

The **InternalRestoreDefaults** method is used internally to restore default report settings specific to the check list box report link: The **GridLineColor** property is set to **clBtnShadow**, all options are enabled, horizontal alignment is set to **taLeft**, and vertical alignment is set to **taCenterY**.

See Also

TdxCheckListBoxReportLink.InternalRestoreFromOriginal

InternalRestoreFromOriginal method

Restores original component settings for a report.

procedure InternalRestoreFromOriginal; **override**;

Description

The **InternalRestoreFromOriginal** method is used internally to return the check list box component's view settings, such as whether check boxes include 3D borders or appear flat in a report, to its original state.

See Also

TdxCheckListBoxReportLink.InternalRestoreDefaults

TdxCheckListBoxReportLink Events

Derived from TdxCustomListBoxReportLink

OnCustomDrawItem published

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxLbxReportLinkDesignWindow Object

Unit

dxPSLbxLnk

```
TdxLbxReportLinkDesignWindow = class(TAbstractdxReportLinkDesignWindow);
```

Description

The **TdxLbxReportLinkDesignWindow** object is used as a designer for the TdxListBoxReportLink object. It appears as a window that provides customization of reports created via the TdxListBoxReportLink object.

Hierarchy

```
Object
  TPersistent
    TComponent
      TControl
        TWinControl
          TScrollingWinControl
            TCustomForm
              TForm
                TAbstractdxReportLinkDesigner
```

TdxListBoxReportLink Object

TdxListBoxReportLink is a report link to print the TListBox component.

Unit

dxPSLbxLnk

```
TdxListBoxReportLink = class(TdxCustomListBoxReportLink);
```

Description

Use TdxListBoxReportLink to print the TListBox component. The **TdxListBoxReportLink** object uses a designer of type **TdxLbxReportLinkDesignWindow** to customize pages with data from the TListBox component.

Hierarchy

```

TObject
  TPersistent
    TComponent
      TBasedxReportLink
        TAbstractdxGridReportLink
          TdxCustomListBoxReportLink
```

TdxListBoxReportLink Properties

TdxListBoxReportLink

ListBox	public / read only	PaintItemsGraphics	published / read / write
Options	published / read / write	TransparentGraphics	published / read / write

Derived from TdxCustomListBoxReportLink

AutoWidth	public / read / write	TextAlignY	public / read / write
CustomListBox	protected / read / write	Width	published / read / write
TextAlignX	public / read / write		

Derived from TAbstractdxGridReportLink

DrawMode	public / read / write	IncludeFixed	protected / read / write
Effects3D	protected / read / write	Multiline	published / read / write
EndEllipsis	published / read / write	OddColor	published / read / write
EvenColor	published / read / write	OddFont	published / read / write
EvenFont	published / read / write	OnlySelected	public / read / write
FixedColor	protected / read / write	RowAutoHeight	published / read / write
FixedFont	protected / read / write	Soft3D	protected / read / write
FixedTransparent	protected / read / write	SupportedCustomDraw	published / read / write
GridLineColor	public / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

ListBox property

read only

Determines the list box, whose items are printed within a report.

```
property ListBox : TListBox;
```

Description

This property returns the TListBox component printed by a printing component.

Options property

read / write

Specifies the type of list box lines included in a report.

type

```
TdxListBoxPaintOption = (lbxpoBorder, lbxpoHorzLines);
```

```
TdxListBoxPaintOptions = set of TdxListBoxPaintOption;
```

```
property Options : TdxListBoxPaintOptions;
```

Description

Use the **Options** property to specify which list box lines are printed. The following values are available:

Values	Meaning
lbxpoBorder	If active, borderlines are printed.
lbxpoHorzLines	If active, horizontal lines are printed.

The default value for the **Options** property is [lbxpoBorder, lbxpoHorzLines].

See Also

TdxListBoxReportLink.InternalRestoreDefaults

PaintItemsGraphics property

read / write

Determines whether graphics associated with items are printed.

```
property PaintItemsGraphics : Boolean;
```

Description

You can associate images with list box items via the **Objects** property of items (as list box items are of type TStrings). If images are associated with items, then you may wish to print these images in your report. Set the **PaintItemsGraphics** property to **True** to print images associated with items:

var

```
pic : TBitmap;
```

```
{ . . . }
```

```
begin
{ . . . }
    // associates an image with the first list box item
    pic := TBitmap.Create;
{ . . . }
    pic.LoadFromFile('c:\Chemic.bmp');
    ListBox1.Items.Objects[0] := pic;
{ . . . }
    // sets the PaintItemsGraphics property to True
    TdxListBoxReportLink( dxComponentPrinter1Link1).PaintItemsGraphics :=
True;
    // builds a report and
    // calls Preview to show the PaintItemsGraohics effect
    dxComponentPrinter1.RebuildReport;
    dxComponentPrinter1.Preview(False, dxComponentPrinter1Link1);
{ . . . }
pic.Free;
end
```

The default value for the **PaintItemsGraphics** property is **False**.

TransparentGraphics property

[read / write](#)

Specifies whether images associated with items are transparent within a report.

property TransparentGraphics: **Boolean**;

Description

Set the **TransparentGraphics** property to **True** to draw graphics transparently in a report when printing standard list box components.

The default value for this property is **False**.

TdxListBoxReportLink Methods

TdxListBoxReportLink

InternalRestoreDefaults **protected**

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
ConstructReport	protected	LinkClass	public
Create	public	LinkModified	protected
DefaultDateFormat	public	LoadFromRegistry	public
DefaultPageNumberFormat	public	MakeDelimiters	protected
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public
InternalRestoreFromOriginal	protected		

InternalRestoreDefaults method

Restores default report settings.

```
procedure InternalRestoreDefaults; override;
```

Description

The **InternalRestoreDefaults** method is used internally to restore default report settings specific to the list box report link: The GridLineColor property is set to **clBtnShadow**, all options are enabled, horizontal alignment is set to **taLeft**, and vertical alignment is set to **taCenterY**, the OnlySelected and PaintItemsGraphics properties are set to **False**.

TdxListBoxReportLink Events

Derived from TdxCustomListBoxReportLink

OnCustomDrawItem	published
------------------	-----------

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TAbstractdxRichEditReportLink Object

TAbstractdxRichEditReportLink is an abstract ancestor for report links to the TRichEdit and TrxRichEdit components.

Unit

dxPSRELnk

```
TAbstractdxRichEditReportLink = class(TBasedxReportLink)
```

Description

TAbstractdxRichEditReportLink introduces the properties used by its descendants to provide report links to the standard TRichEdit component and to TrxRichEdit components. Do not create instances of **TAbstractdxRichEditReportLink**. Instead, use a **TAbstractdxRichEditReportLink** descendant.

Hierarchy

```
Object
  TPersistent
    TComponent
      TBasedxReportLink
```

TAbstractdxRichEditReportLink Properties

In TAbstractdxRichEditReportLink

OnlySelected	published / read / write	RichEditVersion	published / read / write
REHandle	public / read only		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	protected / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	protected / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	protected / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	protected / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

REHandle property

read only

property REHandle: HWND;

Description

The **REHandle** property returns a pointer to the window handle of a rich edit control.

OnlySelected property

read / write

Determines whether only selected text is printed.

property OnlySelected: Boolean;

Description

If the **OnlySelected** property is **True**, the report contains only selected text of a rich edit.

The default value for this property is **False**.

RichEditVersion property**read / write**

Determines the rich edit version.

type

```
TdxRichEditVersion = 1..2;
```

property RichEditVersion: TdxRichEditVersion;

Description

Use the **RichEditVersion** property to determine the version of a rich edit component used in your applications:

- 1 – for the standard Delphi **TRichEdit** component implemented via Riched32.dll;
- 2, 3 – for third party rich edit components. In this case you should use Riched20.dll.

The default value for this property is **1**.

TAbstractdxRichEditReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TAbstractdxRichEditReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxRichEditReportLink Object

TdxRichEditReportLink is a report link used to print a rich edit component.

Unit

dxPSRELnk

```
TdxRichEditReportLink = class(TAbstractdxRichEditReportLink)
```

Description

The **TdxRichEditReportLink** object allows you to print a rich edit component. The **TdxRichEditReportLink** object does not use any designer window. You may customize the pages created from the rich edit component in the Page Setup dialog or via the Print Preview window.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
        AbstractdxRichEditReportLink
```

TdxRichEditReportLink Properties

In TdxRichEditReportLink

RichEdit public / read only

Derived from TAbstractdxRichEditReportLink

OnlySelected	published / read / write	RichEditVersion	published / read / write
REHandle	public / read only		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	protected / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	protected / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	protected / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	protected / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

RichEdit property

read only

Determines the rich edit control printed within a report.

property RichEdit: TRichEdit;

Description

This property returns the TRichEdit object printed by a printing component.

TdxRichEditReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TdxRichEditReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TrxRichEditReportLink Object

TrxRichEditReportLink is a report link used to print a TrxRichEdit component.

Unit

dxPSrxRELnk

```
TrxRichEditReportLink = class(TAbstractdxRichEditReportLink)
```

Description

The **TrxRichEditReportLink** object allows you to print a TrxRichEdit component. The **TrxRichEditReportLink** object does not use any designer window. You may customize pages created from the TrxRichEdit component in the Page Setup dialog or via the Print Preview window.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
        AbstractdxRichEditReportLink
```

TrxRichEditReportLink Properties

In TrxRichEditReportLink

rxRichEdit public / read only

Derived from TAbstractdxRichEditReportLink

OnlySelected	published / read / write	RichEditVersion	published / read / write
REHandle	public / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	protected / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	protected / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	protected / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	protected / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

rxRichEdit property

read only

Determines the rich edit whose text is printed within a report.

property rxRichEdit: TrxRichEdit;

Description

This property returns a TrxRichEdit object printed by a printing component.

TrxRichEditReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TrxRichEditReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TCustomdxInspectorReportLink Object

The TCustomdxInspectorReportLink object represents the base class used to print both the TdxInspector and TdxDBInspector components.

Unit

dxPSdxInsLnk

```
TCustomdxInspectorReportLink = class(TBasedxReportLink)
```

Description

TCustomdxInspectorReportLink is a common ancestor for both the TdxInspectorReportLink and TdxDBInspectorReportLink objects. It provides the functionality necessary to print the TdxInspector and TdxDBInspector components.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
```

TCustomdxInspectorReportLink Properties

In TCustomdxInspectorReportLink

AutoNodesExpand	published / read / write	GroupFont	published / read / write
AutoWidth	published / read / write	GroupColor	published / read / write
FixedTransparent	published / read / write	OddColor	published / read / write
FixedColor	published / read / write	OddFont	published / read / write
FixedFont	published / read / write	Options	published / read / write
GridLineColor	published / read / write	SupportedCustomDraw	published / read / write

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExist	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

AutoNodesExpand property



read / write

Specifies whether nodes are expanded when printing an Inspector component.

property AutoNodesExpand: **Boolean**;

Description

Set the AutoNodesExpandproperty to **True** to force nodes to expand when printing a report. If the AutoNodesExpand property is **False**, Inspector rows are printed as is. Below are two examples where the AutoNodesExpand property is set to **True** and **False** accordingly.



The default value for this property is **False**.

See Also

TCustomdxInspectorReportLink.AutoWidth

AutoWidth property

[read / write](#)

Specifies whether Inspector columns are automatically resized.

property AutoWidth: **Boolean**;

Description

Set the AutoWidth property to **True** to automatically resize Inspector column width according to its text width. If column width is wider than the longest text width, it is not changed; Otherwise, it resizes to the longest column. If the AutoWidth property is set to **False**, Inspector column width is not changed.

The default value for this property is **False**.

See Also

TCustomdxInspectorReportLink.AutoNodesExpand

FixedTransparent property


[read / write](#)

Specifies whether fixed cells are drawn transparently.

property FixedTransparent: **Boolean**;

Description

If the FixedTransparent property is **True**, Inspector fixed cells (such as caption column cells, category cells) are drawn transparently within the report.



The default value for this property is **False**.

See Also

TCustomdxInspectorReportLink.FixedColor

FixedColor property

[read / write](#)

Specifies fixed cell color in a report.

property FixedColor: TColor;

Description

Use the FixedColor property to specify the color of Inspector fixed cells (such as caption column cells) in a report. This color may differ from the original color.

The default value for this property is **clSilver**.

See Also

TCustomdxInspectorReportLink.FixedFont; TCustomdxInspectorReportLink.FixedTransparent

FixedFont property

[read / write](#)

Specifies fixed cell font in a report.

property FixedFont: TFont;

Description

Use the FixedFont property to specify the font of Inspector fixed cells (such as caption column cells) in a report. This font may differ from the original font.

See Also

TCustomdxInspectorReportLink.FixedColor; TCustomdxInspectorReportLink.FixedTransparent

GridLineColor property


[read / write](#)

Specifies Inspector line color in a report.

property GridLineColor: TColor;

Description

Use the GridLineColor property to specify the color of TdxInspector or TdxDBInspector component lines in a report. This color may differ from the original line color.



The default value for this property is **clBlack**.

See Also

TCustomdxInspectorReportLink.GroupColor; *TCustomdxInspectorReportLink.GroupFont*;
TCustomdxInspectorReportLink.GridLineColor

GroupFont property

[read / write](#)

Specifies category cell fonts in a report.

property GroupFont: TFont;

Description

Category cells are cells that represent new category rows within the Inspector. Use the Font property to specify the font of category cells in a report. For instance, the following code changes the category cell font to italic:

```
TCustomdxInspectorReportLink(dxComponentPrinter1Link1).GroupFont.Style :=
  [fsItalic];
```

See Also

TCustomdxInspectorReportLink.GroupColor

GroupColor property


[read / write](#)

Specifies the color used for category cells in a report.

property GroupColor: TColor;

Description

Category cells are cells that represent new category rows within the Inspector. The GroupColor property determines the background color for category cells in a report.



The default value for this property is **clSilver**.

See Also

TCustomdxInspectorReportLink.GroupFont

OddColor property


[read / write](#)

Specifies the color used for odd rows within a report.

property OddColor: TColor;

Description

You can easily differentiate odd and even rows of your report to make it more readable. This property is only available if Draw Mode is set to Odd/Even Rows Mode.



The default value for this property is **clWhite**.

See Also

TCustomdxInspectorReportLink.OddFont

OddFont property


[read / write](#)

Specifies odd row font in a report.

property OddFont: TFont;

Description

The OddFont property is used to specify the font applied to odd rows. This property is only available if Draw Mode is set to Odd/Even Rows Mode.



See Also

TCustomdxInspectorReportLink.OddColor

Options property

[read / write](#)

Determines Inspector look & feel in a report.

type

```
TdxInspectorPaintOption = (ipoBorder, ipoHorzLines, ipoVertLines, ipoFlatCheckMarks);
```

```
TdxInspectorPaintOptions = set of TdxInspectorPaintOption;
```


property Options: TdxInspectorPaintOptions;

Description

Use the Optionsproperty to determine which elements of the TdxInspector or TdxDBInspector component are included in a report. Available options are as follows:

Value	Description	
ipoBorder	If active, borderlines are printed.	True
ipoHorzLines	If active, horizontal lines are printed.	True
ipoVertLines	If active, vertical lines are printed.	True
ipoFlatCheckMarks	If active, node boxes appear flat in a report. Otherwise, they have 3D borders.	True

Example:



See Also

*TCustomdxInspectorReportLink.FixedColor; TCustomdxInspectorReportLink.FixedFont;
TCustomdxInspectorReportLink.GridLineColor; TCustomdxInspectorReportLink.GroupColor*

SupportedCustomDraw property

[read / write](#)

Specifies whether custom drawing events are enabled.

property SupportedCustomDraw: **Boolean**;

Description

Use this property either enable or disable the custom drawing of a component. The default value for this property is **False**.

See Also

*TCustomdxInspectorReportLink.OnCustomDrawCaption;
TCustomdxInspectorReportLink.OnCustomDrawValue*

TCustomdxInspectorReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TCustomdxInspectorReportLink Events

In TCustomdxInspectorReportLink

OnCustomDrawCaption	published
OnCustomDrawValue	published

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

OnCustomDrawCaption event

Occurs when drawing a caption cell.

type

```
TdxTextAlignX = (taLeft, taCenterX, taRight);
TdxTextAlignY = (taTop, taCenterY, taBottom);

TdxInspectorReportLinkCustomEvent = procedure(Sender: TBasedxReportLink;
ARow: TdxInspectorRow; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect;
var AText: string; var AColor: TColor; AFont: TFont; var ATextAlignX:
TdxTextAlignX; var ATextAlignY: TdxTextAlignY; var ADone: Boolean) of
object;
```

property OnCustomDrawCaption: TdxInspectorReportLinkCustomEvent;

Description

Write an OnCustomDrawCaption event handler to draw the contents of all or specific caption cells in the Inspector. The ACanvas parameter determines the drawing surface. The ARect parameter indicates location of a cell on the canvas:

Value	Description
ACanvas	Determines canvas for drawing.
ARow	Specifies the index of the row that contains the selected cell.
ABoundsRect	Specifies the rectangle including borders for drawing.
AClientRect	Specifies the rectangle excluding borders for drawing.
AText	Determines text drawn as a column caption. It can be changed, if necessary.
AColor	Specifies column color. It can be changed, if necessary.
AFont	Specifies the font for drawing column caption. It can be changed, if necessary.
ATextAlignX	Specifies text alignment within a column. It can be changed, if necessary.
ATextAlignY	Specifies text alignment within a column. It can be changed, if necessary.
ADone	Determines whether the OnCustomDrawCell event handler entirely draws a column. If ADone is True, the default drawing procedure is not called.

In order to specify the color, font, text or alignment, used for drawing the header of a particular column, set proper values for AColor, AFont, AText, ATextAlignX or ATextAlignY parameters and set ADone to **False** within the OnCustomDrawCaption event handler.

See Also

TCustomdxInspectorReportLink.SupportedCustomDraw;
TCustomdxInspectorReportLink.OnCustomDrawValue

OnCustomDrawValue event

Occurs when drawing a row value.

type

```
TdxTextAlignX = (taLeft, taCenterX, taRight);
TdxTextAlignY = (taTop, taCenterY, taBottom);
TdxInspectorReportLinkCustomEvent = procedure(Sender: TBasedxReportLink;
ARow: TdxInspectorRow; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect;
var AText: string; var AColor: TColor; AFont: TFont; var ATextAlignX:
TdxTextAlignX; var ATextAlignY: TdxTextAlignY; var ADone: Boolean) of
object;
property OnCustomDrawValue: TdxInspectorReportLinkCustomEvent;
```

Description

Write an OnCustomDrawValue event handler to draw column contents of all Inspector rows.

Value	Description
ACanvas	Determines canvas for drawing.
ARow	Specifies the index of the row that contains the selected cell.
ABoundsRect	Specifies the rectangle including borders for drawing.
AClientRect	Specifies the rectangle excluding borders for drawing.
AText	Determines text drawn as a column caption. It can be changed, if necessary.
AColor	Specifies column color. It can be changed, if necessary.
AFont	Specifies the font for drawing a column caption. It can be changed, if necessary.
ATextAlignX	Specifies text alignment within a column. It can be changed, if necessary.
ATextAlignY	Specifies text alignment within a column. It can be changed, if necessary.
ADone	Determines whether the OnCustomDrawCell event handler entirely draws a column. If ADone is True, the default drawing procedure is not called.

In order to specify the color, font, text or alignment, used for drawing the cell of a particular column, set the appropriate values for AColor, AFont, AText, ATextAlignX or ATextAlignY parameters and set ADone to **False** within the OnCustomDrawValue event handler.

See Also

TCustomdxInspectorReportLink.OnCustomDrawCaption;
TCustomdxInspectorReportLink.SupportedCustomDraw;

TdxInspectorReportLink Object

TdxInspectorReportLink is a report link used to print a TdxInspector component.

Unit

dxPSdxInsLnk

TdxInspectorReportLink = **class**(TCustomdxInspectorReportLink)

Description

The TdxInspectorReportLink object allows you to print a TdxInspector component. In order to customize the pages created from the TdxInspector component, the TdxInspectorReportLink object uses a designer of type **TdxInspectorDesignWindow**.

Hierarchy

- TObject
 - TPersistent
 - TComponent
 - TBasedxReportLink
 - TCustomdxInspectorReportLink

TdxInspectorReportLink Properties

In TdxInspectorReportLink

Inspector **public / read only**

Derived from TCustomdxInspectorReportLink

AutoNodesExpand	published / read / write	GroupFont	published / read / write
AutoWidth	published / read / write	GroupColor	published / read / write
FixedTransparent	published / read / write	OddColor	published / read / write
FixedColor	published / read / write	OddFont	published / read / write
FixedFont	published / read / write	Options	published / read / write
GridLineColor	published / read / write	SupportedCustomDraw	published / read / write

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExist	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

Inspector property

read only

Determines the non data-aware Inspector whose content is printed via the ExpressPrinting System.

property Inspector: TdxInspector;

Description

The Inspector property returns the TdxInspector object for which a report is generated.

See Also

TdxDBInspectorReportLink.DBInspector

TdxInspectorReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TdxInspectorReportLink Events

Derived from TCustomdxInspectorReportLink

OnCustomDrawCaption	published
OnCustomDrawValue	published

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxDBInspectorReportLink Object

TdxDBInspectorReportLink is a report link used to print a TdxDBInspector component.

Unit

dxPSdxDBInsLnk

```
TdxDBInspectorReportLink = class(TCustomdxInspectorReportLink)
```

Description

Use the TdxDBInspectorReportLink object to print a TdxDBInspector component. In order to customize the pages created from the TdxDBInspector component, this object uses a designer of type TdxInspectorDesignWindow.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
        TCustomdxInspectorReportLink
```

TdxDBInspectorReportLink Properties

In TdxDBInspectorReportLink

DBInspector public / read only

Derived from TCustomdxInspectorReportLink

AutoNodesExpand	published / read / write	GroupFont	published / read / write
AutoWidth	published / read / write	GroupColor	published / read / write
FixedTransparent	published / read / write	OddColor	published / read / write
FixedColor	published / read / write	OddFont	published / read / write
FixedFont	published / read / write	Options	published / read / write
GridLineColor	published / read / write	SupportedCustomDraw	published / read / write

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExist	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read only	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read only	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

DBInspector property

read only

Determines the data-aware Inspector used for printing items within a report.

property DBInspector: TdxDBInspector;

Description

Use the DBInspector property to get access to the printed object of type TdxDBInspector.

TdxDBInspectorReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TdxDBInspectorReportLink Events

Derived from TCustomdxInspectorReportLink

OnCustomDrawCaption	published
OnCustomDrawValue	published

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxOCReportLinkDesignWindow

Unit

dxPSdxOCLnk

```
TdxOCReportLinkDesignWindow = class(TAbstractdxReportLinkDesignWindow);
```

Description

The **TdxOCReportLinkDesignWindow** object is used as the designer for TdxOrgChartReportLink and TdxDBOrgChartReportLink objects. It appears as a window that provides customization of a report created via these objects.

Hierarchy

```
Object
  Persistent
    Component
      Control
        WinControl
          ScrollingWinControl
            CustomForm
              Form
                AbstractdxReportLinkDesigner
```

TCustomdxOrgChartReportLink Object

The **TCustomdxOrgChartReportLink** object represents the base class used to print both the TdxOrgChart (ExpressOrgChart) and TdxDBOrgChart (ExpressDBOrgChart) components.

Unit

dxPSdxOCLnk

```
TCustomdxOrgChartReportLink = class(TBasedxReportLink);
```

Description

TCustomdxOrgChartReportLink is a common ancestor for both the TdxOrgChartReportLink and TdxDBOrgChartReportLink objects. It provides the functionality necessary to print the **ExpressOrgChart** and **ExpressDBOrgChart**.

Hierarchy

```
Object
  TPersistent
    TComponent
      TBasedxReportLink
```

TCustomdxOrgChartReportLink Properties

TCustomdxOrgChartReportLink

BorderColor	public / read / write	OrgChart	protected / read only
DrawBorder	public / read / write	TransparentColor	public / read / write
FullExpand	public / read / write	UseMetafile	public / read / write

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	public / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	protected / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	protected / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	public / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

BorderColor property

read / write

Specifies border line color in a report.

property BorderColor : TColor;

Description

Use the **BorderColor** property to specify the color of the border displayed around the ExpressOrgChart or ExpressDBOrgChart in a report. This color may differ from the object's line color. By default, the **BorderColor** property value is **clBlack**.

DrawBorder property

read / write

Determines whether to print a border around the ExpressOrgChart or ExpressDBOrgChart.

property DrawBorder: Boolean;

Description

Use the **DrawBorder** property to include or exclude a border from your report. The default value for this property is False and a border is not printed in a report.

FullExpand property**read / write**

Determines whether chart objects are expanded.

property FullExpand: **Boolean**;

Description

Use the **FullExpand** property to collapse or expand chart objects. The default value for this property is False.

OrgChart property**read only**

Determines the TdxOrgChart (ExpressOrgChart) component to be printed by a printing component.

property OrgChart : TdxOrgChart;

Description

This property returns the TdxOrgChart (ExpressOrgChart) object for which a report is created.

TransparentColor property**read / write**

Specifies the transparent color applied to the TdxOrgChart or TdxDBOrgChart component.

property TransparentColor: TColor;

Description

Use this property to specify the color of a component that is transparent within a report. The **TransparentColor** property is in effect only when the **UseMetafile** property is set to **False**.

The default value for this property is **clWindow**.

See Also

TCustomdxOrgChartReportLink.UseMetafile

UseMetafile property**read / write**

Specifies whether to store a printed chart object as a metafile graphic.

property UseMetafile: **Boolean**;

Description

Set the **UseMetafile** property to **True** to draw chart object contents as a metafile graphics when printing a report. Unlike a bitmap, a metafile guarantees device independence and higher quality (especially when scaling a report). Note, however, that metafiles are generally drawn slower than

bitmaps. If the **UseMetafile** property is **False**, chart object contents are drawn as a bitmap. The default value for this property is **True**.

Note: The **TransparentColor** property is in effect only when the **UseMetafile** property is set to **False**.

See Also

TCustomdxOrgChartReportLink.TransparentColor

TCustomdxOrgChartReportLink Methods

TCustomdxOrgChartReportLink

ConstructReport	protected	PrepareConstruct	protected
InternalRestoreDefaults	protected	UnprepareConstruct	protected

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public
InternalRestoreFromOriginal	protected		

ConstructReport method

Builds a report.

```
procedure ConstructReport(AReportCells : TdxReportCells); override;
```

Description

The **ConstructReport** method creates the contents of a report based on specific properties of a OrgChart component.

InternalRestoreDefaults method

Restores default report settings.

```
procedure InternalRestoreDefaults; override;
```

Description

The **InternalRestoreDefaults** method is used internally to restore default report settings specific to the OrgChart report link: The BorderColor property is set to **clBlack**; The DrawBorder property is set to False. The FullExpand property is set to False.

PrepareConstruct method

Prepares a report.

```
procedure PrepareConstruct; virtual;
```

Description

You should never call this procedure directly. Descendants must override this method to prepare a report for printing based on specific properties of the printed component.

UnPrepareConstruct method

```
procedure PrepareConstruct; virtual;
```

Description

You should never call this procedure directly. Descendants must override this method to prepare a report for printing based on specific properties of a printed component.

TCustomdxOrgChartReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxOrgChartReportLink

TdxOrgChartReportLink is a report link to print the TdxOrgChart (ExpressOrgChart) component.

Unit

dxPSdxOCLnk

```
TdxOrgChartReportLink = class(TCustomdxOrgChartReportLink);
```

Description

The **TdxOrgChartReportLink** object allows you to print the TdxOrgChart component. It uses the TdxOCReportLinkDesignWindow object to customize report page layout.

Hierarchy

```
Object
  TPersistent
    TComponent
      TBasedxReportLink
        TCustomdxOrgChartReportLink
```

TdxOrgChartReportLink Properties

Derived from TCustomdxOrgChartReportLink

BorderColor	published / read / write	OrgChart	published / read / write
DrawBorder	published / read / write	TransparentColor	published / read / write
FullExpand	published / read / write	UseMetafile	published / read / write

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	protected / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	protected / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

TdxOrgChartReportLink Methods

Derived from TCustomdxOrgChartReportLink

ConstructReport	protected	PrepareConstruct	protected
InternalRestoreDefaults	protected	UnprepareConstruct	protected

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public
InternalRestoreFromOriginal	protected		

TdxOrgChartReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxDBOrgChartReportLink

TdxDBOrgChartReportLink represents a report link to print the TdxDBOrgChart (ExpressOrgChart – Data Aware Edition) component.

Unit

dxPSdxOCLnk

```
TdxOrgChartReportLink = class(TCustomdxOrgChartReportLink);
```

Description

The **TdxDBOrgChartReportLink** object allows you to print the TdxDBOrgChart component. It uses the TdxOCReportLinkDesignWindow object to customize report page layout.

Hierarchy

```
Object
  TPersistent
    TComponent
      TBasedxReportLink
        TCustomdxOrgChartReportLink
```

TdxDBOrgChartReportLink Properties

TdxDBOrgChartReportLink

DBOrgChart public / read only

Derived from TCustomdxOrgChartReportLink

BorderColor	published / read / write	OrgChart	protected / read only
DrawBorder	published / read / write	TransparentColor	published / read / write
FullExpand	published / read / write	UseMetafile	published / read / write

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	protected / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	protected / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

DBOrgChart property

read only

Determines the TdxDBOrgChart (ExpressOrgChart) component to be printed by a printing component.

property DBOrgChart : TdxDBOrgChart;

Description

This property returns the TdxDBOrgChart (ExpressDBOrgChart) object for which a report is created.

TdxDBOrgChartReportLink Methods

Derived from TCustomdxOrgChartReportLink

ConstructReport	protected	PrepareConstruct	protected
InternalRestoreDefaults	protected	UnprepareConstruct	protected

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public
InternalRestoreFromOriginal	protected		

TdxDBOrgChartReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TCustomdxTeeChartReportLink Object

The **TCustomdxTeeChartReportLink** object represents the base class used to print both the TChart and TDBChart components.

Unit

dxPSTCLnk

```
TCustomdxTeeChartReportLink = class(TBasedxReportLink);
```

Description

TCustomdxTeeChartReportLink is a common ancestor for both the TdxTeeChartReportLink and TdxDBTeeChartReportLink objects.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
```

TCustomdxTeeChartReportLink Properties

TCustomdxTeeChartReportLink

Chart protected / read only

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	protected / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	protected / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	protected / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	protected / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

Chart property

read only

Determines the TChart component to be printed by a printing component.

property Chart : TChart;

Description

This property returns the TChart object for which a report is created.

TCustomdxTeeChartReportLink Methods

TCustomdxTeeChartReportLink

ConstructReport **protected**

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public
InternalRestoreFromOriginal	protected		

ConstructReport method

Builds a report.

procedure ConstructReport(*AReportCells* : TdxReportCells); **override**;

Description

The **ConstructReport** method creates the contents of a report based on specific properties of a TeeChart component.

TCustomdxTeeChartReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxTeeChartReportLink Object

TdxTeeChartReportLink is a report link to print the TChart component.

Unit

dxPSTCLnk

```
TdxTeeChartReportLink = class(TCustomdxTeeChartReportLink);
```

Description

The **TdxTeeChartReportLink** object allows you to print the TChart component.

Hierarchy

```
Object
  TPersistent
    TComponent
      TBasedxReportLink
        TCustomdxTeeChartReportLink
```

TdxTeeChartReportLink Properties

Derived from TCustomdxTeeChartReportLink

Chart **public / read only**

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	protected / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	protected / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	protected / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	protected / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

TdxTeeChartReportLink Methods

Derived from TCustomdxTeeChartReportLink

ConstructReport **protected**

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public
InternalRestoreFromOriginal	protected		

TdxTeeChartReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxDBTeeChartReportLink Object

TdxDBTeeChartReportLink represents a report link designed to print the TDBChart component.

Unit

dxPSDBTCLnk

```
TdxDBTeeChartReportLink = class(TCustomdxTeeChartReportLink);
```

Description

The **TdxTeeChartReportLink** object allows you to print the TChart component.

Hierarchy

```
Object
  TPersistent
    TComponent
      TBasedxReportLink
        TCustomdxTeeChartReportLink
```

TdxDBTeeChartReportLink Properties

TdxDBTeeChartReportLink

DBChart public / read only

Derived from TCustomdxTeeChartReportLink

Chart protected / read only

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	protected / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	protected / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	protected / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	protected / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

DBChart property

read only

Determines the TDBChart component to be printed by the printing component.

property DBChart : TDBChart;

Description

This property returns the TDBChart object for which a report is created.

TdxDBTeeChartReportLink Methods

Derived from TCustomdxTeeChartReportLink

ConstructReport **protected**

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public
InternalRestoreFromOriginal	protected		

TdxDBTeeChartReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxTLReportLinkDesignWindow

Unit

dxTLLnk

```
TdxTLReportLinkDesignWindow = class(TAbstractdxReportLinkDesignWindow);
```

Description

The **TdxTLReportLinkDesignWindow** object is used as the designer for TdxDBGridReportLink and TdxTreeListReportLink objects. It appears as a window that provides customization of a report created via these objects.

Hierarchy

```
Object
  TPersistent
    TComponent
      TControl
        TWinControl
          TScrollingWinControl
            TCustomForm
              TForm
                TAbstractdxReportLinkDesigner
```

TCustomdxTreeListReportLink Object

The **TCustomdxTreeListReportLink** object represents the base class used to print both the TdxTreeList (ExpressQuantumTreeList) and TdxDBGrid components (ExpressQuantumGrid).

Unit

dxPSdxTILnk

```
TCustomdxTreeListReportLink = class(TBasedxReportLink);
```

Description

TCustomdxTreeListReportLink is a common ancestor for both the TdxTreeListReportLink and TdxDBGridReportLink objects. It provides the functionality necessary to print the **ExpressQuantumGrid** and **ExpressQuantumTreeList**.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
```

TCustomdxTreeListReportLink Properties

TCustomdxTreeListReportLink

AutoNodesExpand	published / read / write	GroupNodeFont	published / read / write
BandColor	published / read / write	HeaderColor	published / read / write
BandFont	published / read / write	HeaderFont	published / read / write
BandsOnEveryPage	published / read / write	HorzDelimitByBands	published / read / write
CustomTreeList	protected / read only	OddColor	published / read / write
DrawMode	published / read / write	OddFont	published / read / write
EvenColor	published / read / write	OnlySelected	published / read / write
EvenFont	published / read / write	Options	published / read / write
ExpandLevel	published / read / write	PreviewColor	published / read / write
ExtendedColorManage	published / read / write	PreviewFont	published / read / write
ExtendedSelect	published / read / write	PreviewLineCount	published / read / write
FixedTransparent	published / read / write	RowFooterColor	published / read / write
FooterFont	published / read / write	RowFooterFont	published / read / write
GraphicAsTextValue	published / read / write	SupportedCustomDraw	published / read / write
GridLineColor	published / read / write	UseColumnFont	published / read / write
GroupNodeColor	published / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	published / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	published / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

AutoNodesExpand property

read / write

Specifies whether nodes are expanded when printing a tree list or a grid component.

property AutoNodesExpand: **Boolean**;

Description

Set the **AutoNodesExpand** property to **True** to force all nodes to expand when printing a report. If the **AutoNodesExpand** property is **False**, all tree list (grid) items are printed as is.

The default value for this property is **False**.

BandColor property

[read / write](#)

Specifies the background color of a band in a report.

property BandColor : TColor;

Description

Use the **BandColor** property to specify the background color of band headers in a report. This color may differ from the band color in the **TreeList**. By default, this property is **clSilver**.

See Also

TCustomdxTreeListReportLink.BandFont

BandFont property

[read / write](#)

Determines the band font in a report.

property BandFont : TFont;

Description

Use the **BandFont** property to specify the font of band header text in a report. This font may differ from the font used in TdxTreeList or TdxDBGrid components. This property is useful to emphasize bands on black and white printers.

See Also

TCustomdxTreeListReportLink.BandColor

BandsOnEveryPage property

[read / write](#)

Specifies whether bands are displayed on every report page.

property BandsOnEveryPage: **Boolean**;

Description

Set the **BandsOnEveryPage** property to **True** to display bands on every page when printing a report. If this property is **False**, only the first report page contains bands.

The default value for this property is **True**.

CustomTreeList property**read only**

Returns a **TCustomdxTreeListControl** object.

property CustomTreeList: TCustomdxTreeListControl;

Description

This property returns a **TCustomdxTreeListControl** object that is the base class for tree list and grid objects. **TCustomdxTreeListControl** descendants inherit the basic functionality of **TCustomdxTreeListControl**.

DrawMode property**read / write**

Determines the manner in which a component is displayed in a report.

type

TdxTreeListDrawMode = (tldmStrict, tldmOddEven, tldmBorrowSource);

property DrawMode: TdxTreeListDrawMode;

Description

Use the **DrawMode** property to select the manner in which a component is printed in a report. Please refer to the table below for more information.

Value	Description
tldmStrict	Used when all colors should look exactly as they are specified in the designer despite any manipulations applied to the control within your application.
tldmOddEven	Used to differentiate even/odd row colors within your report. These colors are specified in the EvenColor (for even lines) and OddColor (for odd lines) properties.
tldmBorrowSource	Used to print a component using a WYSWYG approach. Designer settings are ignored when printing a report - All settings are borrowed from the source component.

When the **DrawMode** property is set to **tldmBorrowSource**, the color set in the designer will be ignored and application colors will be used during printing.

The default value for this property is **tldmStrict**.

EvenColor property**read / write**

Specifies the background color used for even rows in a report.

property EvenColor: TColor;

Description

Use the **EvenColor** property to specify the background color for even rows. This property is in effect only in **Odd/Even Rows Mode**.

The default value for this property is **clWhite**.

See Also

TCustomdxTreeListReportLink.DrawMode; TCustomdxTreeListReportLink.OddColor

EvenFont property

[read / write](#)

Specifies even row font in a report.

property EvenFont: TFont;

Description

Use the **EvenFont** property to specify the text font of even rows when printing a component. This property is in effect only when the **DrawMode** property is set to **tldmOddEven**.

See Also

TCustomdxTreeListReportLink.DrawMode; TCustomdxTreeListReportLink.OddFont

ExpandLevel property

[read / write](#)

Specifies the number of levels to print.

property ExpandLevel : Integer;

Description

Use the **ExpandLevel** property to specify the number of node levels to print. For instance, if the **ExpandLevel** property value is equal to 3, then the report will contain only nodes for the first three levels. Set this property to -1 to print all levels. The default value for the **ExpandLevel** property is -1.

ExtendedColorManage property

[read / write](#)

Determines whether to use a component's color palette.

property ExtendedColorManage : Boolean;

Description

Each column in a TdxTreeList or TdxDBGrid component includes a Color property and with the help of this property, it can include its own unique color. If the **ExtendedColorManage** property is **True**, then the original color of columns is used. The default value for this property is **False**.

ExtendedSelect property

[read / write](#)

Specifies the manner in which selected nodes are printed.

property ExtendedSelect : Boolean;

Description

This property is valid if the OnlySelected property is **True**. If the **ExtendedSelect** property is **True**, then all selected nodes are printed with their parents as they are displayed on screen, that is if a node among the selected items is not expanded, it will be not be printed as expanded. If the **ExtendedSelect** property is **False**, all nodes, located at the same level with that selected, will be printed in expanded mode. The default value for this property is **True**.

In the following instance:

ID	PurchaseDate	Address	State	PaymentAmount
+ City : New York				
+ City : Los Angeles				
+ City : Kingsville				
+ City : Johnsonville				
+ City : Homesville				
- City : Hillsville				
+ CustomerName : Alfred Newman (SUM=84,00)				
+ CustomerName : Bobbie Valentine (SUM=218,00)				
+ CustomerName : Christa Christie (SUM=97,00)				
- CustomerName : Frank Frankson (SUM=599,00)				
39	21.02.00	939 Center Street	OH	1358.
131	13.02.00	900 Newman Center	MI	1218.
147	24.01.00	121 Media Center Drive	OK	1188.
150	13.01.00	933 Heart St. Suite 1	GA	778.
162	31.12.99	900 Newman Center	NY	708.
168	21.01.00	900 Newman Center	NJ	788.
+ CustomerName : James Johnson (SUM=290,00)				
+ CustomerName : Jennie Valentine (SUM=196,00)				
+ CustomerName : Karen Holmes (SUM=274,00)				
+ CustomerName : Ricardo Menendez (SUM=183,00)				
+ CustomerName : Sam Hill (SUM=105,00)				
+ City : Chicago				
+ City : Cartersville				
+ City : Atlanta				

If the **ExtendedSelect** property is **True**, the data pictured below will be printed:

ID	PurchaseDate	Address	State	PaymentAmount	HomePhone	Company
City : Hillsville						
CustomerName : Frank Frankson (SUM=599,00)						
39	21.02.00	939 Center Street	OH	1358.	(029)020-9090	Newman Systems
131	13.02.00	900 Newman Center	MI	1218.	(339)339-3939	Newman Systems
CustomerName : Sam Hill (SUM=105,00)						

If the **ExtendedSelect** property is **False**, the data pictured below will be printed:

ID	PurchaseDate	Address	State	PaymentAmount	HomePhone	Company
City : Hillsville						
CustomerName : Frank Frankson (SUM=599,00)						
39	21.02.00	939 Center Street	OH	1358.	(029)020-9090	Newman Systems
131	13.02.00	900 Newman Center	MI	1218.	(339)339-3939	Newman Systems
147	24.01.00	121 Media Center Drive	OK	1188.	(923)022-0834	Menedez Develo...
150	13.01.00	933 Heart St. Suite 1	GA	778.	(339)339-3939	Hill Corporation
162	31.12.99	900 Newman Center	NY	708.	(923)022-0834	Holmes World
168	21.01.00	900 Newman Center	NJ	788.	(029)020-9090	Doe Enterprises
CustomerName : Sam Hill (SUM=105,00)						
123	29.12.99	349 Graphic Design Lane	NY	1058.	(930)930-3093	Valentine Hearts

See Also

TCustomdxTreeListReportLink.OnlySelected

FixedTransparent property

[read / write](#)

Specifies whether fixed cells are drawn transparently.

property FixedTransparent : **Boolean**;

Description

If the **FixedTransparent** property is **True**, fixed cells such as headers, footers, row footers and group nodes are drawn transparently. By default, the **FixedTransparent** property is **False**.

FooterFont property

[read / write](#)

Specifies footer cells font.

property FooterFont : TFont;

Description

Use the **FooterFont** property to determine font used for footer cells in a report.

GraphicAsTextValue property

[read / write](#)

Determines the text that appears in place of an image in a graphic column.

property GraphicAsTextValue: string;

Description

If the **tlpoGraphicAsText** option is active, all images in graphic columns are replaced with text. Use the **GraphicAsTextValue** property to specify this text.

GridLineColor property

[read / write](#)

Specifies the line color of an **ExpressQuantumTreeList** or **ExpressQuantumGrid** in a report.

property GridLineColor : TColor;

Description

Use the **GridLineColor** property to specify the color of TdxTreeList or TdxDBGrid component lines in a report. This color may differ from the original line color. The default value for the **Color** property is **clBlack**.

GroupNodeColor property

[read / write](#)

Specifies the color of group nodes in a report.

property GroupNodeColor : TColor;

Description

The **GroupNodeColor** property is applicable only to the TdxDBGridReportLink component. Group nodes are nodes with child nodes. This property determines the background color of group nodes in a report. By default, the **GroupNodeColor** property is **clSilver**.

GroupNodeFont property

[read / write](#)

Specifies group node font in a report.

property GroupNodeFont: TFont;

Description

The **GroupNodeFont** property is applicable only to the **TdxDBGridReportLink** component. Group nodes are nodes with child nodes. This property specifies group node font in a report.

HeaderColor property

[read / write](#)

Specifies the background color of headers in a report.

property HeaderColor : TColor;

Description

Use this property to specify the background color for column headers in a report. By default, the **HeaderColor** property value is **clSilver**. If the FixedTransparent property is **True**, the **HeaderColor** property has no effect and column headers are drawn transparently.

See Also

TCustomdxTreeListReportLink.HeaderFont

HeaderFont property

[read / write](#)

Determines headers font.

property HeaderFont : TFont;

Description

Use this property to specify the font of column headers. This font may differ from the font used in a TdxTreeList or TdxDBGrid component.

See Also

TCustomdxTreeListReportLink.HeaderColor

HeaderFont property[read / write](#)

Determines whether to split the **ExpressQuantumTreeList** or **ExpressQuantumGrid** by bands.

property HorzDelimitByBands : **Boolean**;

Description

If the **HorzDelimitByBands** property value is **True**, the **ExpressQuantumTreeList** or **ExpressQuantumGrid** is split horizontally by bands, otherwise by columns. The default value for this property is **True**.

OddColor property[read / write](#)

Specifies the background color of odd rows in a report.

property OddColor: TColor;

Description

Use the **OddColor** property to specify the color of odd rows. This property is in effect only when the **DrawMode** property is set to **tldmOddEven**.

The default value for this property is **clWhite**.

See Also

TCustomdxTreeListReportLink.DrawMode; TCustomdxTreeListReportLink.EvenColor

OddFont property[read / write](#)

Specifies odd row font.

property OddFont: TFont;

Description

Use the **OddFont** property to specify the font of odd rows.

See Also

TCustomdxTreeListReportLink.DrawMode; TCustomdxTreeListReportLink.EvenFont

OnlySelected property[read / write](#)

Determines whether only selected rows are printed.

property OnlySelected : **Boolean**;

property is **False**, thus all rows are included in the report.

Description

If the **OnlySelected** property is True, then the report contains only selected rows of a TdxTreeList or TdxDBGrid component. By default, the **OnlySelected**

See Also

TCustomdxTreeListReportLink.ExtendedSelect

Options property

[read / write](#)

Determines which elements of a TdxTreeList or TdxDBGrid component are included in a report.

type

```
TdxTreeListPaintOption = (tlpoBands, tlpoHeaders, tlpoFooters,
tlpoRowFooters, tlpoPreview, tlpoPreviewGrid, tlpoGrid, tlpoFlatCheckmarks,
tlpoImages, tlpoStateImages, tlpoTransparentColumnGraphic,
tlpoGraphicAsText);
```

```
TdxTreeListPaintOptions = set of TdxTreeListPaintOption;
```

property Options: TdxTreeListPaintOptions;

Description

Use the **Options** property to determine which elements of a TdxTreeList or TdxDBGrid component are included in a report:

Options	Description
tlpoBands	If active, bands are included.
tlpoHeaders	If active, both band and column headers are included.
tlpoFooters	If active, footer cells are included.
tlpoFlatCheckmarks	If active, check boxes are drawn flat; otherwise they have a three-dimensional display.
tlpoRowFooters	If active, row footers are included.
tlpoPreview	If active, the printing component includes the preview section in the report.
tlpoPreviewGrid	If active, the printing component draws additional structures. For more information see the TdxTreeList or TdxDBGrid component. This option is effective only if the tlpoGrid is active.
tlpoGrid	If active, grid lines are drawn in the report.
tlpoImages	If active, images drawn to the left of a node are included in the report.
tlpoStateImages	If active, state images drawn to the left of a node are included in the report.
tlpoTransparentColumnGraphic	If active, images in a graphics column are transparent.
tlpoGraphicAsText	If active, images in a graphics column are presented by text, determined by the GraphicAsTextValue property.

By default, the following options are active: **tlpoBands**, **tlpoHeaders**, **tlpoFooters**, **tlpoFlatCheckmarks**, **tlpoRowFooters**, **tlpoPreview**, **tlpoPreviewGrid**, **tlpoGrid**, **tlpoImages**, **tlpoStatelmages**.

PreviewColor property

[read / write](#)

Specifies the background color of the preview section.

property PreviewColor : TColor;

Description

Use this property to specify the background color of the report preview section. By default, the **PreviewColor** property is **clWhite**.

See Also

TCustomdxTreeListReportLink.PreviewFont

PreviewFont property

[read / write](#)

Specifies the preview font.

property PreviewFont : TFont;

Description

Use the **PreviewFont** property to specify the font used for the report preview section.

See Also

TCustomdxTreeListReportLink.PreviewColor

PreviewLineCount property

[read / write](#)

Determines the height of the component preview section.

property PreviewLineCount: **Integer**;

Description

Use the **PreviewLineCount** property to specify the number of rows displayed in the preview section of a grid (TreeList, DB TreeList).

The default value for this property is **-1**.

RowFooterColor property

[read / write](#)

Specifies the background color of the row footer.

property RowFooterColor : TColor;

Description

Use this property to specify the background color of report row footer cells. By default, the **RowFooterColor** property is **clSilver**.

See Also

TCustomdxTreeListReportLink.RowFooterFont

RowFooterFont property**read / write**

Specifies the font of a row footer's cell text.

property PreviewFont : TFont;

Description

Use the **RowFooterFont** property to specify the text font of report row footer cells.

See Also

TCustomdxTreeListReportLink.RowFooterColor

SupportedCustomDraw property**read / write**

Specifies whether custom drawing events are enabled.

property SupportedCustomDraw: **Boolean**;

Description

If the **SupportedCustomDraw** property is **False**, the default painting process is used to paint a component in a report. Set this property to **True** to perform custom drawing of a component.

The default value for this property is **False**.

UseColumnFont property**read / write**

Determines whether to use original column fonts.

property UseColumnFont : **Boolean**

Description

Each column of a TdxTreeList or TdxDBGrid component includes the Font property and with the help of this property, can have its own unique font. If the **UseColumnFont** property is **True**, then the report will use original column fonts. The default value for this property is **False**.

TCustomdxTreeListReportLink Methods

TCustomdxTreeListReportLink

ConstructReport	protected	IsDBTreeListLink	public
InternalRestoreDefaults	protected	IsTreeListLink	public
InternalRestoreFromOriginal	protected	MakeDelimiters	protected
IsDBGridLink	public		

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public

ConstructReport method

Builds a report.

```
procedure ConstructReport(AReportCells : TdxReportCells); override;
```

Description

The **ConstructReport** method creates the contents of a report based on specific properties of the TdxTreeList or TdxDBGrid component.

InternalRestoreDefaults method

Restores default report settings.

```
procedure InternalRestoreDefaults; override;
```

ExpressPrintingSystem v2 by Developer Express

Report Links

Description

The **InternalRestoreDefaults** method is used internally to restore default report settings specific to the TdxTreeList or TdxDBGrid report link.

See Also

TCustomdxTreeListReportLink.InternalRestoreFromOriginal

InternalRestoreFromOriginal method

Restores original component settings for a report.

```
procedure InternalRestoreFromOriginal; override;
```

Description

The **InternalRestoreFromOriginal** method is used internally to return the TdxTreeList or TdxDBGrid component's view settings, such as different types of font and enabled options, to its original state.

See Also

TCustomdxTreeListReportLink.InternalRestoreDefaults

IsDBGridLink method

Determines whether the report link is used to print the TdxDBGrid component.

```
function IsDBGridLink : Boolean; virtual; abstract;
```

Description

Returns **True** if the printing component works with the TdxDBGrid component.

IsDBTreeListLink method

Determines whether a report link is used to print a **TdxDBTreeList** component.

```
function IsDBTreeList : Boolean; virtual; abstract;
```

Description

Returns **True**, if the ExpressPrinting System is linked to a TdxDBTreeList component.

See Also

TCustomdxTreeListReportLink.IsDBGridLink; *TCustomdxTreeListReportLink.IsTreeListLink*

IsTreeListLink method

Determines whether the report link is used to print the TdxTreeList component.

```
function IsTreeListLink : Boolean; virtual; abstract;
```

Description

Returns **True** if the printing component works with the TdxTreeList component.

MakeDelimiters method

Creates delimiters for report pages.

```
procedure MakeDelimiters(AReportCells : TdxReportCells; AHorzDelimiters,  
AVertDelimiters : TList); override;
```

Description

The **MakeDelimiters** method creates bounds that limit report pages. The *AHorzDelimiters* and *AVertDelimiters* parameters specify horizontal and vertical delimiters. When splitting report pages, cells are not split.

TCustomdxTreeListReportLink Events

TCustomdxTreeListReportLink

OnCustomDrawBandCell	protected	OnCustomDrawHeaderCell	protected
OnCustomDrawCell	protected	OnCustomDrawPreviewCell	protected
OnCustomDrawFooterCell	protected	OnCustomDrawRowFooterCell	protected

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

OnCustomDrawBandCell event

Occurs when drawing a band cell.

type

```
TdxTextAlignX = (taLeft, taCenterX, taRight);
```

```
TdxTextAlignY = (taTop, taCenterY, taBottom);
```

```
TdxTLReportLinkCustomDrawBandCellEvent = procedure(Sender: TBasedxReportLink;
  ACanvas: TCanvas; ABoundsRect, AClientRect: TRect; ABand: TdxTreeListBand;
  var AText: string; var AColor: TColor; AFont: TFont; var ATextAlignX:
  TdxTextAlignX; var ATextAlignY: TdxTextAlignY; var ADone: Boolean) of
object;
property OnCustomDrawBandCell: TdxTLReportLinkCustomDrawBandCellEvent;
```

Description

Write an **OnCustomDrawBandCell** event handler to draw a band cell. The *ACanvas* parameter determines the drawing surface.

Value	Description
ABoundsRect	Rectangular cell area including borders.
AClientRect	Rectangular cell area excluding borders.
ABand	Band of a cell.
AText	Context of a cell. It can be changed, if necessary.
AColor	Specifies background color. It can be changed, if necessary.
AFont	Font of a cell. It can be changed, if necessary.
ATextAlignX	Horizontal text alignment within a cell. It can be changed, if necessary.
ATextAlignY	Vertical text alignment within a cell. It can be changed, if necessary.
ADone	Determines whether the OnCustomDrawBandCell event handler entirely draws a band cell. If <i>ADone</i> is True , the default drawing procedure is not called.

Note: This property is only accessible if the **SupportedCustomDraw** property is set to **True**.

OnCustomDrawCell event

Occurs when drawing a cell.

type

```
TdxTextAlignX = (taLeft, taCenterX, taRight);
TdxTextAlignY = (taTop, taCenterY, taBottom);
TdxTLReportLinkCustomDrawCellEvent = procedure(Sender: TBasedxReportLink;
ACanvas: TCanvas; ABoundsRect, AClientRect: TRect; ANode: TdxTreeNode;
AColumn: TdxTreeListColumn; var AText: string; var AColor: TColor; AFont:
TFont; var ATextAlignX: TdxTextAlignX; var ATextAlignY: TdxTextAlignY; var
ADone: Boolean) of object;
property OnCustomDrawCell: TdxTLReportLinkCustomDrawCellEvent;
```

Description

Write an **OnCustomDrawCell** event handler to draw a cell. The *ACanvas* parameter determines the drawing surface.

Value	Description
ABoundsRect	Rectangular cell area including borders.
AClientRect	Rectangular cell area excluding borders.
ANode	Node of a cell.
AColumn	Column of a cell.
AText	Context of a cell. It can be changed, if necessary.
AColor	Specifies background color. It can be changed, if necessary.
AFont	Font of a cell. It can be changed, if necessary.
ATextAlignX	Horizontal text alignment within a cell. It can be changed, if necessary.
ATextAlignY	Vertical text alignment within a cell. It can be changed, if necessary.
ADone	Determines whether the OnCustomDrawBandCell event handler entirely draws a cell. If <i>ADone</i> is True , the default drawing procedure is not called.

Note: This property is only accessible if the **SupportedCustomDraw** property is set to **True**.

OnCustomDrawFooterCell event

Occurs when drawing a footer cell.

type

```
TdxTextAlignX = (taLeft, taCenterX, taRight);
TdxTextAlignY = (taTop, taCenterY, taBottom);
TdxTLReportLinkCustomDrawFooterCellEvent = procedure(Sender:
TBasedxReportLink; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect;
ANode: TdxTreeNode; AColumn: TdxTreeListColumn; var AText: string; var
AColor: TColor; AFont: TFont; var ATextAlignX: TdxTextAlignX; var
ATextAlignY: TdxTextAlignY; var ADone: Boolean) of object;
property OnCustomDrawFooterCell: TdxTLReportLinkCustomDrawFooterCellEvent;
```

Description

Write an **OnCustomDrawFooterCell** event handler to draw a footer cell. The *ACanvas* parameter determines the drawing surface.

Value	Description
ABoundsRect	Rectangular cell area including borders.
AClientRect	Rectangular cell area excluding borders.
ANode	Node of a cell.
AColumn	Column of a cell.
AText	Context of a cell. It can be changed, if necessary.
AColor	Specifies background color of a footer cell. It can be changed, if necessary.
AFont	Font of a cell. It can be changed, if necessary.
ATextAlignX	Horizontal text alignment within a cell. It can be changed, if necessary.
ATextAlignY	Vertical text alignment within a cell. It can be changed, if necessary.
ADone	Determines whether the OnCustomDrawBandCell event handler entirely draws a footer cell. If <i>ADone</i> is True , the default drawing procedure is not called.

Note: This property is only accessible if the **SupportedCustomDraw** property is set to **True**.

OnCustomDrawHeaderCell event

Occurs when drawing a header cell.

type

```
TdxTextAlignX = (taLeft, taCenterX, taRight);
TdxTextAlignY = (taTop, taCenterY, taBottom);
TdxTLReportLinkCustomDrawHeaderCellEvent = procedure(Sender:
  TBasedxReportLink; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect;
  AColumn: TdxTreeListColumn; var AText: string; var AColor: TColor; AFont:
  TFont; var ATextAlignX: TdxTextAlignX; var ATextAlignY: TdxTextAlignY; var
  ASorted: TdxCellSortOrder; var ADone: Boolean) of object;
```

property OnCustomDrawHeaderCell: TdxTLReportLinkCustomDrawHeaderCellEvent;

Description

Write an **OnCustomDrawHeaderCell** event handler to draw a header cell. The *ACanvas* parameter determines the drawing surface.

Value	Description
ABoundsRect	Rectangular cell area including borders.
AClientRect	Rectangular cell area excluding borders.
AColumn	Column of a cell.
AText	Context of a cell. It can be changed, if necessary.
AColor	Specifies background color of a footer cell. It can be changed, if necessary.
AFont	Font of a cell. It can be changed, if necessary.

ATextAlignX	Horizontal text alignment within a cell. It can be changed, if necessary.
ATextAlignY	Vertical text alignment within a cell. It can be changed, if necessary.
ASorted	Specifies the order cells are sorted (ascending order, descending order, unsorted).
ADone	Determines whether the OnCustomDrawBandCell event handler entirely draws a header cell. If ADone is True , the default drawing procedure is not called.

Note: This property is only accessible if the **SupportedCustomDraw** property is set to **True**.

OnCustomDrawPreviewCell event

Occurs when drawing a preview cell.

type

```
TdxTLReportLinkCustomDrawPreviewCellEvent = procedure(Sender:
  TBasedxReportLink; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect;
  ANode: TdxTreeNode; var AText: string; var AColor, ATextColor: TColor;
  AFont: TFont; var ADone: Boolean) of object;
```

```
property OnCustomDrawPreviewCell: TdxTLReportLinkCustomDrawPreviewCellEvent;
```

Description

Write an **OnCustomDrawPreviewCell** event handler to draw a preview cell. The **ACanvas** parameter determines the drawing surface.

Value	Description
ABoundsRect	Rectangular cell area including borders.
AClientRect	Rectangular cell area excluding borders.
ANode	Node of a cell.
AText	Context of a cell. It can be changed, if necessary.
AColor	Specifies background color of a cell. It can be changed, if necessary.
ATextColor	Specifies text color of a cell. It can be changed, if necessary.
AFont	Font of a cell. It can be changed, if necessary.
ADone	Determines whether the OnCustomDrawBandCell event handler entirely draws a preview cell. If ADone is True , the default drawing procedure is not called.

Note: This property is only accessible if the **SupportedCustomDraw** property is set to **True**.

OnCustomDrawRowFooterCell event

Occurs when drawing a row footer cell.

type

```
TdxTextAlignX = (taLeft, taCenterX, taRight);
TdxTextAlignY = (taTop, taCenterY, taBottom);
```

```

TdxTLReportLinkCustomDrawRowFooterCellEvent = procedure(Sender:
  TBasedxReportLink; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect;
  ANode: TdxTreeNode; AColumn: TdxTreeListColumn; AFooterIndex: Integer;
  var AText: string; var AColor: TColor; AFont: TFont; var ATextAlignX:
  TdxTextAlignX; var ATextAlignY: TdxTextAlignY; var ADone: Boolean) of
  object;
property OnCustomDrawRowFooterCell: TdxTLReportLinkCustomDrawRowFooterCellEvent;

```

Description

Write an **OnCustomDrawRowFooterCell** event handler to draw a row footer cell. The *ACanvas* parameter determines the drawing surface.

Value	Description
ABoundsRect	Rectangular cell area including borders.
AClientRect	Rectangular cell area excluding borders.
ANode	Node of a cell.
AColumn	Column of a cell.
AFooterIndex	Specifies footer index.
AText	Context of a cell. It can be changed, if necessary.
AColor	Specifies background color of a cell. It can be changed, if necessary.
AFont	Font of a cell. It can be changed, if necessary.
ATextAlignX	Horizontal text alignment within a cell. It can be changed, if necessary.
ATextAlignY	Vertical text alignment within a cell. It can be changed, if necessary.
ADone	Determines whether the OnCustomDrawBandCell event handler entirely draws a preview cell. If <i>ADone</i> is True , the default drawing procedure is not called.

Note: This property is only accessible if the **SupportedCustomDraw** property is set to **True**.

TdxTreeListReportLink Object

TdxTreeListReportLink is a report link used to print a TdxTreeList component.

Unit

dxPSdxTLLnk

```
TdxTreeListReportLink = class(TCustomdxTreeListReportLink);
```

Description

Used to print a TdxTreeList component. The **TdxTreeListReportLink** object applies a designer of type TdxTLReportLinkDesignWindow to customize the page layout with TdxTreeList data.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
        TCustomdxTreeListReportLink
```

TdxTreeListReportLink Properties

TdxTreeListReportLink

TreeList

public / read only

Derived from TCustomdxTreeListReportLink

AutoNodesExpand	published / read / write	HeaderColor	published / read / write
BandColor	published / read / write	HeaderFont	published / read / write
BandFont	published / read / write	HorzDelimitByBands	published / read / write
BandsOnEveryPage	published / read / write	GridLineColor	published / read / write
CustomTreeList	protected / read only	OddColor	published / read / write
DrawMode	published / read / write	OddFont	published / read / write
EvenColor	published / read / write	OnlySelected	published / read / write
EvenFont	published / read / write	Options	published / read / write
ExpandLevel	published / read / write	PreviewColor	published / read / write
ExtendedColorManage	published / read / write	PreviewFont	published / read / write
ExtendedSelect	published / read / write	PreviewLineCount	published / read / write
FixedTransparent	published / read / write	RowFooterColor	published / read / write
FooterFont	published / read / write	RowFooterFont	published / read / write
GraphicAsTextValue	published / read / write	SupportedCustomDraw	published / read / write
GroupNodeColor	published / read / write	UseColumnFont	published / read / write
GroupNodeFont	published / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	published / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	published / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

TreeList property**read only**

Specifies the **ExpressQuantumTreeList** control.

```
property TreeList : TdxTreeList;
```

Description

This property returns the TdxTreeList component printed by a printing component.

TdxTreeListReportLink Methods

Derived from TCustomdxTreeListReportLink

ConstructReport	protected	IsDBTreeListLink	public
InternalRestoreDefaults	protected	IsTreeListLink	public
InternalRestoreFromOriginal	protected	MakeDelimiters	protected
IsDBGGridLink	public		

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public

TdxTreeListReportLink Events

Derived from TCustomdxTreeListReportLink

OnCustomDrawBandCell	published	OnCustomDrawHeaderCell	published
OnCustomDrawCell	published	OnCustomDrawPreviewCell	published
OnCustomDrawFooterCell	published	OnCustomDrawRowFooterCell	published

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxDBTreeListControlReportLink Object

TdxDBTreeListControlReportLink is a report link used to print a TdxDBTreeList component.

Unit

dxPSdxDBCtrlLnk

```
TdxDBTreeListControlReportLink = class(TCustomdxTreeListReportLink)
```

Description

The TdxDBTreeListControlReportLink object allows you to print a TdxDBTreeList component.

Hierarchy

```
Object
  TPersistent
    TComponent
      TBasedxReportLink
        TCustomdxTreeListReportLink
```

TdxDBTreeListControlReportLink Properties

In TdxDBTreeListControlReportLink

DBTreeListControl protected / read only

Derived from TCustomdxTreeListReportLink

AutoNodesExpand	published / read / write	HeaderColor	published / read / write
BandColor	published / read / write	HeaderFont	published / read / write
BandFont	published / read / write	HorzDelimitByBands	published / read / write
BandsOnEveryPage	published / read / write	GridLineColor	published / read / write
CustomTreeList	protected / read only	OddColor	published / read / write
DrawMode	published / read / write	OddFont	published / read / write
EvenColor	published / read / write	OnlySelected	published / read / write
EvenFont	published / read / write	Options	published / read / write
ExpandLevel	published / read / write	PreviewColor	published / read / write
ExtendedColorManage	published / read / write	PreviewFont	published / read / write
ExtendedSelect	published / read / write	PreviewLineCount	published / read / write
FixedTransparent	published / read / write	RowFooterColor	published / read / write
FooterFont	published / read / write	RowFooterFont	published / read / write
GraphicAsTextValue	published / read / write	SupportedCustomDraw	published / read / write
GroupNodeColor	published / read / write	UseColumnFont	published / read / write
GroupNodeFont	published / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExist	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	published / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	published / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

DBTreeListControl property**read only**

Determines the DBTreeListControl object to be used for printing items within a report.

property DBTreeListControl: TCustomdxDBTreeListControl;

Description

Use the DBTreeListControl property to get access to the printed object of type TCustomdxDBTreeListControl.

TdxDBTreeListControlReportLink Methods

In TdxDBTreeListControlReportLink

IsTreeListLink **public**

Derived from TCustomdxTreeListReportLink

ConstructReport	protected	IsDBGridLink	public
InternalRestoreDefaults	protected	IsDBTreeListLink	public
InternalRestoreFromOriginal	protected	MakeDelimiters	protected

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public

IsTreeListLink method

Determines whether a report link is used to print a TdxTreeList component.

```
function IsTreeListLink: Boolean; override;
```

Description

Call this method to determine whether a report link is used to print a TdxTreeList component. In this instance this method returns **True**.

TdxDBTreeListControlReportLink Events

Derived from TCustomdxTreeListReportLink

OnCustomDrawBandCell	protected	OnCustomDrawHeaderCell	protected
OnCustomDrawCell	protected	OnCustomDrawPreviewCell	protected
OnCustomDrawFooterCell	protected	OnCustomDrawRowFooterCell	protected

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxDBGridReportLink Object

TdxDBGridReportLink represents a report link used to print the TdxDBGrid component.

Unit

dxPSdxDBGrLnk

```
TdxDBGridReportLink = class(TdxDBTreeListControlReportLink);
```

Description

Used to print the TdxDBGrid component. The **TdxDBGridReportLink** object uses a designer of type TdxTLReportLinkDesignWindow to customize the page layout with TdxDBGrid data.

Hierarchy

```
Object
  TPersistent
    TComponent
      TBasedxReportLink
        TCustomdxTreeListReportLink
          TdxDBTreeListControlReportLink
```

TdxDBGridReportLink Properties

TdxDBGridReportLink

DBGrid public / read only

Derived from TdxDBTreeListControlReportLink

DBTreeListControl protected / read only

Derived from TCustomdxTreeListReportLink

AutoNodesExpand	published / read / write	HeaderColor	published / read / write
BandColor	published / read / write	HeaderFont	published / read / write
BandFont	published / read / write	HorzDelimitByBands	published / read / write
BandsOnEveryPage	published / read / write	GridLineColor	published / read / write
CustomTreeList	protected / read only	OddColor	published / read / write
DrawMode	published / read / write	OddFont	published / read / write
EvenColor	published / read / write	OnlySelected	published / read / write
EvenFont	published / read / write	Options	published / read / write
ExpandLevel	published / read / write	PreviewColor	published / read / write
ExtendedColorManage	published / read / write	PreviewFont	published / read / write
ExtendedSelect	published / read / write	PreviewLineCount	published / read / write
FixedTransparent	published / read / write	RowFooterColor	published / read / write
FooterFont	published / read / write	RowFooterFont	published / read / write
GraphicAsTextValue	published / read / write	SupportedCustomDraw	published / read / write
GroupNodeColor	published / read / write	UseColumnFont	published / read / write
GroupNodeFont	published / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	published / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	published / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

DBGrid property**read only**

Specifies an **ExpressQuantumGrid** control.

property DBGrid : TdxDBGrid;

Description

This property returns the TdxDBGrid component printed by a printing component.

TdxDBGridReportLink Methods

TdxDBGridReportLink

IsDBGridLink	public	IsTreeListLink	public
IsDBTreeListLink	public		

Derived from TdxDBTreeListControlReportLink

IsTreeListLink	public
----------------	--------

Derived from TCustomdxTreeListReportLink

ConstructReport	protected	InternalRestoreFromOriginal	protected
InternalRestoreDefaults	protected	MakeDelimiters	protected

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public

IsDBGridLink method

Determines whether a report link is used to print the TdxDBGrid component.

```
function IsDBGridLink : Boolean; override;
```

Description

Returns **True**.

See Also

TdxDBGridReportLink.IsTreeListLink; TdxDBGriReportLink.IsDBTreeListLink

IsDBTreeListLink method

Determines whether a report link is used to print a TdxDBTreeList component.

```
function IsDBTreeListLink : Boolean; override;
```

Description

Returns **False**.

See Also

TdxDBGridReportLink.IsTreeListLink; TdxDBGriReportLink.IsDBGridLink

IsTreeListLink method

Determines whether a report link is used to print the TdxTreeList component.

```
function IsTreeListLink : Boolean; override;
```

Description

Returns **False**.

See Also

TdxDBGriReportLink.IsDBGridLink; TdxDBGriReportLink.IsDBTreeListLink

TdxDBGridReportLink Events

Derived from TCustomdxTreeListReportLink

OnCustomDrawBandCell	published	OnCustomDrawHeaderCell	published
OnCustomDrawCell	published	OnCustomDrawPreviewCell	published
OnCustomDrawFooterCell	published	OnCustomDrawRowFooterCell	published

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxDBTreeListReportLink Object

TdxDBTreeListReportLink represents a report link used to print a TdxDBTreeList component.

Unit

dxPSdxDBTLLnk

```
TdxDBTreeListReportLink = class(TCustomdxTreeListReportLink);
```

Description

Used to print a TdxDBTreeList component. The **TdxDBTreeListReportLink** object uses a designer, of type TdxTLReportLinkDesignWindow, to customize page layout with TdxDBTreeList data.

Hierarchy

```
Object
  TPersistent
    TComponent
      TBasedxReportLink
        TCustomdxTreeListReportLink
```

TdxDBTreeListReportLink Properties

TdxDBTreeListReportLink

DBTreeList public / read only

Derived from TdxDBTreeListControlReportLink

DBTreeListControl protected / read only

Derived from TCustomdxTreeListReportLink

AutoNodesExpand	published / read / write	HeaderColor	published / read / write
BandColor	published / read / write	HeaderFont	published / read / write
BandFont	published / read / write	HorzDelimitByBands	published / read / write
BandsOnEveryPage	published / read / write	GridLineColor	published / read / write
CustomTreeList	protected / read only	OddColor	published / read / write
DrawMode	published / read / write	OddFont	published / read / write
EvenColor	published / read / write	OnlySelected	published / read / write
EvenFont	published / read / write	Options	published / read / write
ExpandLevel	published / read / write	PreviewColor	published / read / write
ExtendedColorManage	published / read / write	PreviewFont	published / read / write
ExtendedSelect	published / read / write	PreviewLineCount	published / read / write
FixedTransparent	published / read / write	RowFooterColor	published / read / write
FooterFont	published / read / write	RowFooterFont	published / read / write
GraphicAsTextValue	published / read / write	SupportedCustomDraw	published / read / write
GroupNodeColor	published / read / write	UseColumnFont	published / read / write
GroupNodeFont	published / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	published / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	published / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

DBTreeList property**read only**

Specifies an **ExpressQuantumDBTreeList** control.

property DBGrid : TdxDBGrid;

Description

This property returns the TdxDBTreeList component printed by a printing component.

GraphicAsTextValue property**read / write**

Determines the text that appears in place of an image, within a graphic column.

property GraphicAsTextValue : string;

Description

If the **tlpoGraphicAsText** option is active, all images in graphic columns are substituted with the text. Use the **GraphicAsTextValue** property to specify this text.

TdxDBTreeListReportLink Methods

TdxDBTreeListReportLink

IsDBGridLink	public	IsDBTreeListLink	public
--------------	--------	------------------	--------

Derived from TdxDBTreeListControlReportLink

IsTreeListLink	public
----------------	--------

Derived from TCustomdxTreeListReportLink

ConstructReport	protected	InternalRestoreFromOriginal	protected
InternalRestoreDefaults	protected	MakeDelimiters	protected

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public

IsDBGridLink method

Determines whether a report link is used to print the TdxDBGrid component.

```
function IsDBGridLink : Boolean; override;
```

Description

Returns **False**.

See Also

TdxDBGriReportLink.IsDBTreeListLink

IsDBTreeListLink method

Determines whether a report link is used to print a TdxDBTreeList component.

```
function IsDBTreeListLink : Boolean; override;
```

Description

Returns **True**.

See Also

TdxDBGriReportLink.IsDBGridLink

TdxDBTreeListReportLink Events

Derived from TCustomdxTreeListReportLink

OnCustomDrawBandCell	published	OnCustomDrawHeaderCell	published
OnCustomDrawCell	published	OnCustomDrawPreviewCell	published
OnCustomDrawFooterCell	published	OnCustomDrawRowFooterCell	published

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TCustomdxTreeViewReportLink Object

The **TCustomdxTreeViewReportLink** object represents the base class used to print the TTreeView, TdxTreeView and TdxDBTreeView components.

Unit

dxPSTVLnk

```
TCustomdxTreeViewReportLink = class(TBasedxReportLink)
```

Description

TCustomdxTreeViewReportLink is a common ancestor for the TdxTreeViewReportLink, TdxTreeViewExReportLink, and TdxDBTreeViewReportLink objects. It provides the functionality necessary to print the TTreeView, TdxTreeView, and TdxDBTreeView components.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
```

TCustomdxTreeViewReportLink Properties

In TCustomdxTreeViewReportLink

AutoNodesExpand	public / read / write	Options	public / read / write
AutoWidth	public / read / write	SupportedCustomDraw	public / read / write
ExpandLevel	public / read / write	TreeView	protected / read only
GridLineColor	public / read / write	Width	public / read / write
NodeAutoHeight	public / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	protected / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	public / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	protected / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	protected / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

AutoNodesExpand property

read / write

Specifies whether nodes are expanded when printing a tree view component.

property AutoNodesExpand: **Boolean**;

Description

Set the **AutoNodesExpand** property to **True** to force all nodes to expand when printing a report. If the **AutoNodesExpand** property is **False**, all tree view items are printed as is.

The default value for this property is **False**.

AutoWidth property

read / write

Specifies whether tree view items automatically size themselves to their text width.

property AutoWidth: **Boolean**;

Description

Set the **AutoWidth** property to **True** to display the entire contents of tree view items in a report. If tree view item width is larger than the longest width of item text, it does not change. If the **AutoWidth** property is set to **False**, tree view item width does not change.

The default value for this property is **True**.

ExpandLevel property**read / write**

Specifies the number of levels to print.

property ExpandLevel: **Integer**;

Description

Use the **ExpandLevel** property to specify the number of node levels to print. For instance, if the **ExpandLevel** property value is equal to 3, the report will contain only nodes for the first three levels. Set this property to -1 to print all levels.

The default value for this property is **-1**.

GridLineColor property**read / write**

Specifies the line color of a tree view component in a report.

property GridLineColor: **TColor**;

Description

Use the **GridLineColor** property to specify the color of tree view component lines in a report. This color may differ from the original line color.

The default value for this property is **clBlack**.

Options property**read / write**

Determines which elements of a tree view component are included in a report.

type

```
TdxTreeViewPaintOption = (tvpoBorder, tvpoGrid, tvpoStateImages,
tvpoImages);
```

```
TdxTreeViewPaintOptions = set of TdxTreeViewPaintOption;
```

property Options: TdxTreeViewPaintOptions;

Description

Use the **Options** property to determine which elements of a tree view component are included in a report:

Value	Description
Copyright © 2001 Developer Express Inc. www.devexpress.com	

tvpoBorder	If active, borderlines are printed.
tvpoGrid	If active, horizontal and vertical grid lines are printed.
tvpoStateImages	If active, state images are printed.
tvpoImages	If active, node images are printed.

The default value for this property is **[tvpoStateImages, tvpoImages]**.

NodeAutoHeight property

[read / write](#)

Specifies whether tree view nodes automatically resize their height to accommodate the entire text.

property NodeAutoHeight: **Boolean**;

Description

Use the **NodeAutoHeight** property to automatically adjust the height of a tree view node to fully display its contents. The **NodeAutoHeight** property is in effect only when the AutoWidth property of the tree view report link is set to **False**. In this instance, the horizontal size of the control within a report is determined by the Width property of the tree view control (not by the Width property of the tree view report link).

The default value for this property is **False**.

SupportedCustomDraw property

[read / write](#)

Specifies whether a custom painting procedure is enabled.

property SupportedCustomDraw: **Boolean**;

Description

If the **SupportedCustomDraw** property is **False**, the default painting process is used to paint a component in a report. Set this property to **True** to use your own custom painting procedure.

The default value for this property is **False**.

TreeView property

[read / write](#)

Determines the tree view object whose items are printed within a report.

property TreeView: TTreeView;

Description

This property returns a TTreeView object printed by a printing component.

Width property

[read / write](#)

Specifies the horizontal size of a tree view in pixels.

property Width: **Integer**;

Description

Use the **Width** property to specify the width of a tree view component in a report.

TCustomdxTreeViewReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TCustomdxTreeViewReportLink Events

In TCustomdxTreeViewReportLink

OnCustomDrawNode **protected**

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

OnCustomDrawNode event

Occurs when drawing a specific node within a tree view control.

type

```
TdxTextAlignX = (taLeft, taCenterX, taRight);
TdxTextAlignY = (taTop, taCenterY, taBottom);

TdxTVCustomDrawNodeEvent = procedure(Sender: TBasedxReportLink; ANode:
TTreeNode; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect; var AText:
string; AFont: TFont; var AColor: TColor; var ATextAlignX: TdxTextAlignX;
var ATextAlignY: TdxTextAlignY; var ADone: Boolean) of object;
```

property OnCustomDrawNode: TdxTVCustomDrawNodeEvent;

Description

Write an **OnCustomDrawNode** event handler to draw a specific node when printing a report. Draw a cell using the TCanvas method.

Parameter	Meaning
ANode	Specifies a specific node of a tree view component.
ACanvas	Determines canvas for drawing.
ABoundsRect	Specifies rectangle including borders for drawing.
AClientRect	Specifies rectangle excluding borders for drawing.
AText	Determines node text. You can change it if necessary.
AFont	Specifies font for drawing node text. You can change it, if necessary.
AColor	Specifies the background color of a node. You can change it, if necessary.
ATextAlignX	Determines horizontal text alignment of a node. You can change it, if necessary.
ATextAlignY	Determines vertical text alignment of a node. You can change it, if necessary.
ADone	Determines whether the OnCustomDrawNode event handler entirely draws a node. If ADone is True, the default drawing procedure is not called.

Available values for *ATextAlignX* include:

taLeft	Text is left justified.
---------------	-------------------------

taCenterX	Text is centered within a node cell.
taRight	Text is right justified.

Available values for *ATextAlignY* include:

taTop	Text is aligned to the top edge of a node cell.
taCenterY	Text is vertically centered within a node cell.
taBottom	Text is aligned to the bottom edge of a node cell.

In order to specify the color, font, text or alignment, used for drawing a specific node, set proper values for the *AColor*, *AFont*, *AText*, *ATextAlignX* or *ATextAlignY* parameters and set *ADone* to **False** within the **OnCustomDrawNode** event handler.

TdxTreeViewReportLink Object

TdxTreeViewReportLink is a report link used to print a TTreeView component.

Unit

dxPSTVLnk

TdxTreeViewReportLink= **class**(TCustomdxTreeViewReportLink)

Description

The **TdxTreeViewReportLink** object allows you to print a TTreeView component. The **TdxTreeViewReportLink** object uses a designer to customize pages with data from the TTreeView component.

Hierarchy

- TObject
 - TPersistent
 - TComponent
 - TBasedxReportLink
 - TCustomdxTreeViewReportLink

TdxTreeViewReportLink Properties

Derived from TCustomdxTreeViewReportLink

AutoNodesExpand	published / read / write	Options	published / read / write
AutoWidth	published / read / write	SupportedCustomDraw	published / read / write
ExpandLevel	published / read / write	TreeView	public / read only
GridLineColor	published / read / write	Width	published / read / write
NodeAutoHeight	public / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

TdxTreeViewReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TdxTreeViewReportLink Events

Derived from TCustomdxTreeViewReportLink

OnCustomDrawNode	published
------------------	-----------

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxTreeViewExReportLink Object

TdxTreeViewExReportLink is a report link used to print a TdxTreeView component.

Unit

dxPSdxDBTVLnk

```
TdxTreeViewExReportLink = class(TCustomdxTreeViewReportLink)
```

Description

Use the TdxTreeViewExReportLink object to print a TdxTreeView component. In order to customize data layout of this component, the TdxTreeViewExReportLink object uses a designer of type **TdxTVReportLinkDesignWindow**.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
        CustomdxTreeViewReportLink
```

TdxTreeViewExReportLink Properties

In TdxTreeViewExReportLink

dxTreeView **public / read only**

Derived from TCustomdxTreeViewReportLink

AutoNodesExpand	published / read / write	Options	published / read / write
AutoWidth	published / read / write	SupportedCustomDraw	published / read / write
ExpandLevel	published / read / write	TreeView	published / read / write
GridLineColor	published / read / write	Width	published / read / write
NodeAutoHeight	published / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	public / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExist	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

dxTreeView property

read only

Specifies a TdxTreeView control.

```
property dxTreeView: TdxTreeView;
```

Description

Use the dxTreeView property to get access to the printed object of type TdxTreeView.

TdxTreeViewExReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TdxTreeViewExReportLink Events

Derived from TCustomdxTreeViewReportLink

OnCustomDrawNode	published
------------------	-----------

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxDBTreeViewReportLink Object

TdxDBTreeViewReportLink is a report link used to print a TdxDBTreeView component.

Unit

dxPSdxDBTVLnk

TdxDBTreeViewReportLink = **class**(TdxTreeViewExReportLink)

Description

Use the TdxDBTreeViewReportLink object to print a TdxDBTreeView component. In order to customize data layout of this component, the TdxDBTreeViewReportLink object uses a designer of type **TdxTVReportLinkDesignWindow**.

Hierarchy

- TObject
 - TPersistent
 - TComponent
 - TBasedxReportLink
 - TCustomdxTreeViewReportLink
 - TdxTreeViewExReportLink

TdxDBTreeViewReportLink Properties

In TdxDBTreeViewReportLink

DBTreeView **protected / read only**

Derived from TdxTreeViewExReportLink

dxTreeView **protected / read only**

Derived from TCustomdxTreeViewReportLink

AutoNodesExpand	published / read / write	Options	published / read / write
AutoWidth	published / read / write	SupportedCustomDraw	published / read / write
ExpandLevel	published / read / write	TreeView	protected / read only
GridLineColor	published / read / write	Width	published / read / write
NodeAutoHeight	public / read / write		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	public / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

DBTreeView property

read only

Specifies a TdxDBTreeView control.

property DBTreeView: TdxDBTreeView;

Description

Use the DBTreeView property to get access to the printed object of type TCustomdxDBTreeListControl.

TdxDBTreeViewReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TdxDBTreeViewReportLink Events

Derived from TCustomdxTreeViewReportLink

OnCustomDrawNode publised / read / write

Derived from TBasedxReportLink

OnChangeComponent	publised / read / write	OnDestroy	publised / read / write
OnCustomDrawPageFooter	publised / read / write	OnFilterStyle	publised / read / write
OnCustomDrawPageHeader	publised / read / write	OnMeasureReportLinkTitle	publised / read / write
OnCustomDrawReportLinkTitle	publised / read / write		

TdxFCReportLinkDesignWindow

Unit

dxPSdxFCLnk

```
TdxFCReportLinkDesignWindow = class(TAbstractdxReportLinkDesignWindow);
```

Description

The **TdxFCReportLinkDesignWindow** object is used as a designer for the TdxFlowChartReportLink object. The **TdxFCReportLinkDesignWindow** object appears as a window that provides customization of reports created via the TdxFlowChartReportLink object.

Hierarchy

```

TObject
  TPersistent
    TComponent
      TControl
        TWinControl
          TScrollingWinControl
            TCustomForm
              TForm
                TAbstractdxReportLinkDesigner
```

TdxFlowChartReportLink Object

TdxFlowChartReportLink represents a report link used to print the TdxFlowChart (ExpressFlowChart) component.

Unit

dxPSdxFCLnk

```
TdxFlowChartReportLink = class(TBasedxReportLink);
```

Description

The **TdxFlowChartReportLink** object allows you to print the TdxFlowChart component. It uses the TdxFCReportLinkDesignWindow object to customize report page layout.

Hierarchy

```
Object
  Persistent
    Component
      BasedxReportLink
```

TdxFlowChartReportLink Properties

TdxFlowChartBoxReportLink

BorderColor	published / read / write	TransparentColor	published / read / write
DrawBorder	published / read / write	UseMetafile	published / read / write
FlowChart	public / read only		

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	protected / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	public / read / write
EmptyPagesCanExists	public / read only	ShowPageFooter	published / read / write
Font	protected / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

BorderColor property

read / write

Specifies border line color in a report.

```
property BorderColor : TColor;
```

Description

Use the **BorderColor** property to specify the color of the border drawn around the ExpressFlowChart in a report. This color may differ from the TdxFlowChart object's line color. By default, the **BorderColor** property value is **clBlack**.

DrawBorder property

read / write

Determines whether to print a border around the ExpressFlowChart.

```
property DrawBorder: Boolean;
```

Description

Use the **DrawBorder** property to include or exclude borders from a report. The default value for this property is **False** and a border is not printed in a report.

FlowChart property**read only**

Determines the TdxFlowChart (ExpressFlowChart) component to be printed by a printing component.

property FlowChart : TdxFlowChart;

Description

This property returns the TdxFlowChart (ExpressFlowChart) object for which a report is created.

TransparentColor property**read / write**

Specifies the transparent color applied to the TdxFlowChart component.

property TransparentColor: TColor;

Description

Use this property to specify the color of a component that is transparent within a report. The **TransparentColor** property is in effect only when the **UseMetafile** property is set to **False**.

The default value for this property is **cWindow**.

UseMetafile property**read / write**

Specifies whether to store a printed chart object as a metafile graphic.

property UseMetafile: **Boolean**;

Description

Set the **UseMetafile** property to **True** to draw chart object contents as a metafile graphics when printing a report. Unlike a bitmap, a metafile guarantees device independence and higher quality (especially when scaling a report). Note, however, that metafiles are generally drawn slower than bitmaps. If the **UseMetafile** property is **False**, chart object contents are drawn as a bitmap.

The default value for this property is **True**.

Note: The **TransparentColor** property is in effect only when the **UseMetafile** property is set to **False**.

TdxFlowChartReportLink Methods

TdxFlowChartReportLink

ConstructReport	protected	MakeDelimiters	protected
InternalRestoreDefaults	protected		

Derived from TBasedxReportLink

BuildPageSetupMenu	public	IsEmptyReport	public
CheckToDesign	public	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	PageReady	protected
DesignerExists	public	PageSetup	public
DesignReport	public	PageSetupEx	public
Destroy	public	Preview	public
DestroyReport	public	Print	public
DoChangeComponent	protected	PrintEx	public
DoProgress	protected	PrintPages	public
DrawCheckBox	public	PrintPagesEx	public
DrawEdge	public	RebuildReport	public
DrawGraphic	public	RestoreDefaults	public
DrawPageFooter	public	RestoreFromOriginal	public
DrawPageHeader	public	SaveToRegistry	public
DrawSortMark	public	SetActive	protected
DrawText	public	ShowDateTimeFormatsDlg	public
GetFilteredStyles	public	ShowPageNumberFormatsDlg	public
GetPageColRowCount	public	ShowTitlePropertiesDlg	public
GetSupportedComponentList	public	UsingShrinkToPageWidthMode	public
InternalRestoreFromOriginal	protected		

ConstructReport method

Builds a report.

```
procedure ConstructReport(AReportCells : TdxReportCells); override;
```

Description

The **ConstructReport** method creates the contents of a report based on specific properties of a flow chart component.

InternalRestoreDefaults method

Restores default report settings.

```
procedure InternalRestoreDefaults; override;
```

Description

The **InternalRestoreDefaults** method is used internally to restore default report settings specific to the flow chart report link: The **BorderColor** property is set to **clBlack**; The **DrawBorder** property is set to **False**.

MakeDelimiters method

Creates delimiters for report pages.

```
procedure MakeDelimiters(AReportCells : TdxReportCells; AHorzDelimiters,  
AVertDelimiters : TList); override;
```

Description

The **MakeDelimiters** method creates bounds that limit report pages. The *AHorzDelimiters* and *AVertDelimiters* parameters specify horizontal and vertical delimiters. When splitting report pages, cells are not split.

TdxFlowChartReportLink Events

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

TdxMasterViewReportLink Object

TdxMasterViewReportLink is a report link used to print a TdxMasterView component.

Unit

dxPSdxMVLnk

TdxMasterViewReportLink = **class**(TBasedxReportLink)

Description

The TdxMasterViewReportLink object allows you to print a TdxMasterView component. In order to customize the pages created from the TdxMasterView component, the TdxMasterViewReportLink object uses a designer of type **TdxMVReportLinkDesignWindow**.

Hierarchy

- TObject
 - TPersistent
 - TComponent
 - TBasedxReportLink

TdxMasterViewReportLink Properties

In TdxMasterViewReportLink

AutoNodesExpand	published / read / write	GroupNodeColor	published / read / write
CaptionColor	published / read / write	HeaderColor	published / read / write
CaptionNodeFont	published / read / write	HeaderFont	published / read / write
DrawMode	published / read / write	MasterView	public / read only
EvenColor	published / read / write	OddColor	published / read / write
EvenFont	published / read / write	OddFont	published / read / write
ExtendedSelect	published / read / write	OnlySelected	published / read / write
FixedTransparent	published / read / write	Options	published / read / write
FooterColor	published / read / write	PreviewColor	published / read / write
FooterFont	published / read / write	PreviewFont	published / read / write
GridLineColor	published / read / write	PreviewLineCount	published / read / write
GroupNodeFont	published / read / write	SupportedCustomDraw	published / read / write

Derived from TBasedxReportLink

Active	published / read / write	PrinterPage	published / read / write
AssignedFormatValues	published / read / write	RealPrinterPage	public / read / write
Color	published / read / write	RealScaleFactor	public / read only
Component	published / read / write	RebuildNeeded	public / read only
ComponentPrinter	public / read / write	ReportHeight	public / read only
CurrentPage	public / read / write	ReportTitle	published / read / write
CurrentPrintStyle	public / read only	ReportTitleMode	published / read / write
Data	public / read / write	ReportTitleText	published / read / write
DateFormat	published / read / write	ReportWidth	public / read only
DateTime	published / read / write	ScaleFonts	published / read / write
DesignerCaption	published / read / write	ShowDesigner	published / read / write
DesignerHelpContext	published / read / write	ShowEmptyPages	published / read / write
EmptyPagesCanExist	public / read only	ShowPageFooter	published / read / write
Font	published / read / write	ShowPageHeader	published / read / write
FootersOnEveryPage	protected / read / write	ShrinkToPageWidth	published / read / write
HeadersOnEveryPage	protected / read / write	StartPageIndex	published / read / write
Index	published / read / write	StyleManager	published / read / write
IsCurrentLink	published / read / write	TimeFormat	published / read / write
PageCount	public / read only	Transparent	published / read / write
PageNumberFormat	published / read / write	VisiblePageCount	public / read only

MasterView property


read only

Specifies an **ExpressMasterView** control.

```
property MasterView: TdxMasterView;
```

Description

Use the MasterView property to get access to the printed object of type TdxMasterView.



AutoNodesExpand property


read / write


Specifies whether all nodes are expanded.

property AutoNodesExpand: **Boolean**;

Description

If the AutoNodesExpandproperty is set to **False**, all collapsed nodes remain collapsed. If the AutoNodesExpand property is set to **True**, all nodes are expanded.





The default value for this property is **False**.

See Also

TdxMasterViewReportLink.ExtendedSelect; TdxMasterViewReportLink.OnlySelected

CaptionColor property


[read / write](#)

Specifies level caption color.

property CaptionColor: TColor;

Description

Use the CaptionColor property to change level caption color. Uncheck the Fixed Transparent check box in the Colors tab designer and choose the desired color from the Level Caption Color combobox.



The default value for this property is **clSilver**.

See Also

TdxMasterViewReportLink.CaptionNodeFont

CaptionNodeFont property


[read / write](#)

Specifies the font of a level node caption.

property CaptionNodeFont: TFont;

Description

The CaptionNodeFont property is used to specify the node caption font.



See Also

TdxMasterViewReportLink.CaptionColor

DrawMode property

[read / write](#)

Specifies the drawing mode of your report.

type

`TdxMasterViewDrawMode = (mvdMStrict, mvdMOddEven, mvdMBorrowSource);`


property DrawMode: TdxMasterViewDrawMode;

Description

Specifies the drawing mode of your report. It can take one of three values. Please refer to the table below for more information.

Value	Description
MvdMStrict	Used when all colors should look exactly as they are specified in the designer despite any manipulations applied to an application.
MvdMOddEven	Used to differentiate even and odd row colors in a report. These colors are specified in the EvenColor (for even rows) and OddColor (for odd rows) properties.
MvdMBorrowSource	Used when report color scheme should look exactly as in an application despite any changes made in the designer.

When the DrawMode property is set to **mvdmborrowSource**, the color set in the designer will be ignored and application colors will be used during printing.



The default value for this property is **mvdmStrict**.

See Also

TdxMasterViewReportLink.EvenColor; TdxMasterViewReportLink.OddColor

EvenColor property


[read / write](#)

Specifies the color of even report rows.

property EvenColor: TColor;

Description

The EvenColor property is used to specify the color of even report rows. The default value for this property is **clWhite**.



Note: This property is only available in Odd/Even Rows mode.

See Also

`TdxMasterViewReportLink.EvenFont`; `TdxMasterViewReportLink.OddColor`;
`TdxMasterViewReportLink.OddFont`

EvenFont property


[read / write](#)

Specifies the font name of even report rows.

property EvenFont: TFont;

Description

The EvenFont property is used to specify the font name of even report rows.



Note: This property is only available in **Odd/Even Rows** mode.

See Also

`TdxMasterViewReportLink.EvenColor`; `TdxMasterViewReportLink.EvenFont`;
`TdxMasterViewReportLink.OddColor`; `TdxMasterViewReportLink.OddFont`

ExtendedSelect property

read / write

Specifies the manner in which selected nodes are printed.

property ExtendedSelect: **Boolean**;

Description

If the ExtendedSelect property is set to **True**, all selected nodes will be printed along with their parents as they are displayed on screen. If a selected node is not expanded, its children are not printed. If ExtendedSelect is **False**, both the parent and child nodes of a selected node are printed.

The default value for this property is **True**.

Note: This property is valid if the **OnlySelected** property is **True**.

See Also

TdxMasterViewReportLink.OnlySelected

FixedTransparent property

read / write

property FixedTransparent: **Boolean**;

Description

The FixedTransparent property is a Boolean property. When set to **True**, it indicates that the level caption, header, footer, and group node colors are drawn transparently.

The default value for this property is **False**.

See Also

*TdxMasterViewReportLink.CaptionColor; TdxMasterViewReportLink.EvenColor;
TdxMasterViewReportLink.FooterColor; TdxMasterViewReportLink.GridLineColor;
TdxMasterViewReportLink.GroupNodeColor; TdxMasterViewReportLink.HeaderColor;
TdxMasterViewReportLink.OddColor; TdxMasterViewReportLink.PreviewColor;*

FooterColor property

read / write

Specifies footer color.

property FooterColor: **TColor**;

Description

The FooterColor property is used to set footer color.

The default value for this property is **clSilver**.

See Also

*TdxMasterViewReportLink.FooterFont; TdxMasterViewReportLink.HeaderColor;
TdxMasterViewReportLink.HeaderFont*

FooterFont property**read / write**

Specifies footer font.

property FooterFont: TFont;

Description

The FooterFont property is used to specify footer font.

See Also

*TdxMasterViewReportLink.FooterColor; TdxMasterViewReportLink.HeaderColor;
TdxMasterViewReportLink.HeaderFont*


GridLineColor property**read / write**

Specifies grid line color.

property GridLineColor: TColor;

Description

The GridLineColor property is used to specify grid line color.



The default value for this property is **clBlack**.

See Also

*TdxMasterViewReportLink.CaptionColor; TdxMasterViewReportLink.CaptionNodeFont;
TdxMasterViewReportLink.EvenColor; TdxMasterViewReportLink.ExtendedSelect;
TdxMasterViewReportLink.FixedTransparent; TdxMasterViewReportLink.FooterColor;
TdxMasterViewReportLink.GroupNodeColor; TdxMasterViewReportLink.HeaderColor;
TdxMasterViewReportLink.OddColor; TdxMasterViewReportLink.PreviewColor;*

GroupNodeFont property

[read / write](#)

Specifies group node font.

property GroupNodeFont: TFont;

Description

Use the GroupNodeFont property to specify group node font.

See Also

TdxMasterViewReportLink.GroupNodeColor

GroupNodeColor property


[read / write](#)

Specifies group node color.

property GroupNodeColor: TColor;

Description

The GroupNodeColor is used to specify group node color.



The default value for this property is **clSilver**.

See Also

TdxMasterViewReportLink.GroupNodeFont

HeaderColor property

[read / write](#)

Specifies header color.

property HeaderColor: TColor;

Description

Use the HeaderColor property to specify header color.

The default value for this property is **clSilver**.

See Also

TdxMasterViewReportLink.FooterColor; *TdxMasterViewReportLink.FooterFont*;
TdxMasterViewReportLink.HeaderFont

HeaderFont property

[read / write](#)

Specifies header font.

property HeaderFont: TFont;

Description

Use the HeaderFont property to specify header font.

See Also

*TdxMasterViewReportLink.FooterColor; TdxMasterViewReportLink.FooterFont;
TdxMasterViewReportLink.HeaderColor*

OddColor property


[read / write](#)

Specifies odd row color.

property OddColor: TColor;

Description

Use the OddColor property to specify the color of odd rows.



The default value for this property is **clWhite**.

See Also

TdxMasterViewReportLink.OddFont

OddFont property


[read / write](#)

Specifies odd row font.

property OddFont: TFont;

Description

Use the OddFont property to specify the font of odd rows.

**See Also**

TdxMasterViewReportLink.OddColor

OnlySelected property

[read / write](#)

Specifies whether the selected range or the entire report is printed out.

property OnlySelected: Boolean;

Description

The **OnlySelected** property is used to specify whether the selected range or the entire report is printed out. Range should be determined beforehand.

The default value for this property is **False**.

See Also

TdxMasterViewReportLink.ExtendedSelect; TdxMasterViewReportLink.OnlySelected

Options property

[read / write](#)

Indicates specific properties for a component.

type

```
TdxMasterViewPaintOption = (mvpoHeaders, mvpoFooters, mvpoPreview,
mvpoGrid, mvpoPreviewGrid, mvpoGroupFooterGrid, mvpoFlatCheckMarks,
mvpoTransparentColumnGraphic, mvpoGraphicAsText, mvpo3DEffects,
mvpoSoft3D);
```

```
TdxMasterViewPaintOptions = set of TdxMasterViewPaintOption;
```

property Options: TdxMasterViewPaintOptions;

Description

The options below are used to set specific properties for a report for easier navigation and analysis.

Value	Description	Default
mvpoHeaders	Specifies whether a header is visible.	True
mvpoFooters	Specifies whether a footer is visible.	True
mvpoPreview	Specifies whether preview is visible.	True
mvpoGrid	Specifies whether grid lines are visible.	True
mvpoPreviewGrid	Specifies whether a preview grid is visible.	True
mvpoGroupFooterGrid	Specifies whether a group footer is visible.	True
mvpoFlatCheckMarks	Specifies check box look & feel (flat or 3D).	True
mvpoTransparentColumnGraphic	Specifies whether column graphics are transparent.	False
mvpoGraphicAsText	Specifies the manner in which graphics are displayed. If enabled, text is displayed instead of a picture. If disabled, graphics are displayed as is.	False
mvpo3DEffects	Specifies whether 3D effects are enabled. If enabled, all borders will be displayed with a 3D look; Otherwise, the entire report will be displayed plain.	True
mvpoSoft3D	Specifies whether the Soft3D property is set to True. If disabled, all 3D graphics are flattened.	True

See Also

TdxMasterViewReportLink.CaptionColor;
TdxMasterViewReportLink.EvenColor;
TdxMasterViewReportLink.FixedTransparent;
TdxMasterViewReportLink.FooterFont;

TdxMasterViewReportLink.CaptionNodeFont;
TdxMasterViewReportLink.EvenFont;
TdxMasterViewReportLink.FooterColor;
TdxMasterViewReportLink.GridLineColor;

TdxMasterViewReportLink.GroupNodeColor;
TdxMasterViewReportLink.HeaderColor;
TdxMasterViewReportLink.OddColor; TdxMasterViewReportLink.OddFont

TdxMasterViewReportLink.GroupNodeFont;
TdxMasterViewReportLink.HeaderFont;
TdxMasterViewReportLink.OddFont

PreviewColor property

read / write

Specifies preview color.

property PreviewColor: TColor;

Description

The PreviewColor property is used to specify the color of a preview band.

The default value for this property is **clWhite**.

See Also

TdxMasterViewReportLink.PreviewFont

PreviewFont property

read / write

Specifies preview font.

property PreviewFont: TFont;

Description

The PreviewFont property is used to specify text font for a preview band.

See Also

TdxMasterViewReportLink.PreviewColor; TdxMasterViewReportLink.PreviewFont

PreviewLineCount property

read / write

Determines preview band width.

property PreviewLineCount: **Integer**;

Description

The PreviewLineCount property is used to determine the width of a preview band. If set to 0, no preview band appears.

The default value for this property is **-1**.

Note: To auto calculate the preview lines count set the PreviewLineCount property to -1.

See Also

TdxMasterViewReportLink.PreviewColor;
TdxMasterViewReportLink.PreviewLineCount

TdxMasterViewReportLink.PreviewFont;

SupportedCustomDraw property

read / write

Specifies whether custom drawing events are enabled.

property SupportedCustomDraw: **Boolean**;

Description

Use this property to allow a user to perform custom drawing of a component.

The default value for this property is **False**.

See Also

TdxMasterViewReportLink.OnCustomDrawCell;
TdxMasterViewReportLink.OnCustomDrawFooterCell;
TdxMasterViewReportLink.OnCustomDrawHeaderCell;
TdxMasterViewReportLink.OnCustomDrawPreviewCell

TdxMasterViewReportLink Methods

Derived from TBasedxReportLink

BuildPageSetupMenu	public	InternalRestoreFromOriginal	protected
CheckToDesign	public	IsEmptyReport	public
ConstructReport	protected	IsSupportedCompClass	public
Create	public	LinkClass	public
DefaultDateFormat	public	LinkModified	protected
DefaultPageNumberFormat	public	LoadFromRegistry	public
DefaultTimeFormat	public	MakeDelimiters	protected
DesignerExists	public	PageReady	protected
DesignReport	public	PageSetup	public
Destroy	public	PageSetupEx	public
DestroyReport	public	Preview	public
DoChangeComponent	protected	Print	public
DoProgress	protected	PrintEx	public
DrawCheckBox	public	PrintPages	public
DrawEdge	public	PrintPagesEx	public
DrawGraphic	public	RebuildReport	public
DrawPageFooter	public	RestoreDefaults	public
DrawPageHeader	public	RestoreFromOriginal	public
DrawSortMark	public	SaveToRegistry	public
DrawText	public	SetActive	protected
GetFilteredStyles	public	ShowDateTimeFormatsDlg	public
GetPageColRowCount	public	ShowPageNumberFormatsDlg	public
GetSupportedComponentList	public	ShowTitlePropertiesDlg	public
InternalRestoreDefaults	protected	UsingShrinkToPageWidthMode	public

TdxMasterViewReportLink Events

In TdxMasterViewReportLink

OnCustomDrawCell	published	OnCustomDrawHeaderCell	published
OnCustomDrawFooterCell	published	OnCustomDrawPreviewCell	published

Derived from TBasedxReportLink

OnChangeComponent	published	OnDestroy	published
OnCustomDrawPageFooter	published	OnFilterStyle	published
OnCustomDrawPageHeader	published	OnMeasureReportLinkTitle	published
OnCustomDrawReportLinkTitle	published		

OnCustomDrawCell event

Occurs when drawing a cell.

type

```
TdxTextAlignX = (taLeft, taCenterX, taRight);
TdxTextAlignY = (taTop, taCenterY, taBottom);
TdxMVReportLinkCustomDrawCellEvent = procedure(Sender: TBasedxReportLink;
ACanvas: TCanvas; ABoundsRect, AClientRect: TRect; ANode:
TdxMasterViewNode; AColumn: TdxMasterViewColumn; var AText: string; var
AColor: TColor; AFont: TFont; var ATextAlignX: TdxTextAlignX; var
ATextAlignY: TdxTextAlignY; var ADone: Boolean) of object;
```

property OnCustomDrawCell: TdxMVReportLinkCustomDrawCellEvent;

Description

Write an OnCustomDrawCell event handler to draw a cell.

Value	Description
ACanvas	Specifies the drawing surface.
ABoundsRect	Rectangular cell area including borders.
AClientRect	Rectangular cell area excluding borders.
ANode	Node of a cell.
AColumn	Column of a cell.
AText	Context of a cell. It can be changed, if necessary.
AColor	Specifies text color. It can be changed, if necessary.
AFont	Font of a cell. It can be changed, if necessary.
ATextAlignX	Horizontal text alignment within a cell. It can be changed, if necessary.
ATextAlignY	Vertical text alignment within a cell. It can be changed, if necessary.
ADone	Determines whether the OnCustomDrawCell event handler entirely draws a cell. If ADone is True , the default drawing procedure is not called.

Note: This property is only accessible if the SupportedCustomDraw property is set to **True**.

See Also

TdxMasterViewReportLink.OnCustomDrawCell;
TdxMasterViewReportLink.OnCustomDrawFooterCell;
TdxMasterViewReportLink.OnCustomDrawHeaderCell;
TdxMasterViewReportLink.OnCustomDrawPreviewCell

OnCustomDrawFooterCell event

Occurs when drawing a footer cell.

type

```

    TdxTextAlignX = (taLeft, taCenterX, taRight);
    TdxTextAlignY = (taTop, taCenterY, taBottom);
    TdxMVReportLinkCustomDrawFooterCellEvent = procedure(Sender:
    TBasedxReportLink; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect;
    ANode: TdxMasterViewNode; AColumn: TdxMasterViewColumn; var AText: string;
var AColor: TColor; AFont: TFont; var ATextAlignX: TdxTextAlignX; var
    ATextAlignY: TdxTextAlignY; var ADone: Boolean) of object;

```

property OnCustomDrawFooterCell: TdxMVReportLinkCustomDrawFooterCellEvent;

Description

Write an OnCustomDrawFooterCell event handler to draw a footer cell.

Value	Description
ACanvas	Specifies the drawing surface.
ABoundsRect	Rectangular cell area including borders.
AClientRect	Rectangular cell area excluding borders.
ANode	Node of a cell.
AColumn	Column of a cell.
AText	Context of a cell. It can be changed, if necessary.
AColor	Specifies text color. It can be changed, if necessary.
AFont	Font of a cell. It can be changed, if necessary.
ATextAlignX	Horizontal text alignment within a cell. It can be changed, if necessary.
ATextAlignY	Vertical text alignment within a cell. It can be changed, if necessary.
ADone	Determines whether the OnCustomDrawCell event handler entirely draws a cell. If ADone is True , the default drawing procedure is not called.

Note: This property is only accessible if the *SupportedCustomDraw* property is set to **True**.

See Also

TdxMasterViewReportLink.OnCustomDrawCell;
TdxMasterViewReportLink.OnCustomDrawFooterCell;
TdxMasterViewReportLink.OnCustomDrawHeaderCell;
TdxMasterViewReportLink.OnCustomDrawPreviewCell

OnCustomDrawHeaderCell event

Occurs when drawing a header cell.

type

```
TdxTextAlignX = (taLeft, taCenterX, taRight);
TdxTextAlignY = (taTop, taCenterY, taBottom);
TdxCellSortOrder = (csoNone, csoUp, csoDown);
TdxMVReportLinkCustomDrawHeaderCellEvent = procedure(Sender:
TBasedxReportLink; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect;
AColumn: TdxMasterViewColumn; var AText: string; var AColor: TColor; AFont:
TFont; var ATextAlignX: TdxTextAlignX; var ATextAlignY: TdxTextAlignY; var
ASorted: TdxCellSortOrder; var ADone: Boolean) of object;
```

property OnCustomDrawHeaderCell: TdxMVReportLinkCustomDrawHeaderCellEvent;

Description

Write an OnCustomDrawHeaderCell event handler to draw a header cell.

Value	Description
ACanvas	Specifies the drawing surface.
ABoundsRect	Rectangular cell area including borders.
AClientRect	Rectangular cell area excluding borders.
AColumn	Column of a cell.
AText	Context of a cell. It can be changed, if necessary.
AColor	Specifies text color. It can be changed, if necessary.
AFont	Font of a cell. It can be changed, if necessary.
ATextAlignX	Horizontal text alignment within a cell. It can be changed, if necessary.
ATextAlignY	Vertical text alignment within a cell. It can be changed, if necessary.
ASorted	Specifies the order cells are sorted (ascending order, descending order, unsorted).
ADone	Determines whether the OnCustomDrawCell event handler entirely draws a cell. If ADone is True, the default drawing procedure is not called.

Note: This property is only accessible if the SupportedCustomDraw property is set to **True**.

See Also

TdxMasterViewReportLink.OnCustomDrawCell;
TdxMasterViewReportLink.OnCustomDrawFooterCell;
TdxMasterViewReportLink.OnCustomDrawHeaderCell;
TdxMasterViewReportLink.OnCustomDrawPreviewCell

OnCustomDrawPreviewCell event

Occurs when drawing a preview cell.

type

```
TdxMVReportLinkCustomDrawPreviewCellEvent = procedure(Sender:
TBasedxReportLink; ACanvas: TCanvas; ABoundsRect, AClientRect: TRect;
ANode: TdxMasterViewNode; var AText: string; var AColor: TColor; AFont:
TFont; var ADone: Boolean) of object;
```

```
property OnCustomDrawPreviewCell:
TdxMVReportLinkCustomDrawPreviewCellEvent;
```

Description

Write an OnCustomDrawPreviewCell event handler to draw a preview cell.

Value	Description
ACanvas	Specifies the drawing surface.
ABoundsRect	Rectangular cell area including borders.
AClientRect	Rectangular cell area excluding borders.
ANode	Node of a cell.
AText	Context of a cell. It can be changed, if necessary.
AColor	Specifies text color. It can be changed, if necessary.
AFont	Font of a cell. It can be changed, if necessary.
ADone	Determines whether the OnCustomDrawCell event handler entirely draws a cell. If ADone is True , the default drawing procedure is not called.

Note: This property is accessible only if the SupportedCustomDraw property is set to **True**.

See Also

```
TdxMasterViewReportLink.OnCustomDrawCell;
TdxMasterViewReportLink.OnCustomDrawFooterCell;
TdxMasterViewReportLink.OnCustomDrawHeaderCell;
TdxMasterViewReportLink.OnCustomDrawPreviewCell
```

Index

A

Active.....	11
AssignedFormatValues	11
AutoNodesExpand	118, 162, 203, 228
AutoWidth	88, 119, 120, 203

B

BandColor	163
BandFont.....	163
BandsOnEveryPage.....	163
BorderColor	138, 221
BuildPageSetupMenu.....	24

C

CaptionColor.....	229
CaptionNodeFont	230
Chart	151
CheckListBox	95
CheckToDesign.....	26
Color	12
Component.....	12
ComponentPrinter	12
ConstructReport	27, 141, 152, 173, 223
Create.....	27
CurrentPage.....	12
CurrentPrintStyle	13
CustomGrid.....	66
CustomListBox	87
CustomTreeList.....	164

D

Data.....	13
DateFormat	13
DateTime	14
DBChart.....	158
DBGrid	192
DBInspector	134
DBOrgChart	148
DBTreeList	198
DBTreeListControl	187
DBTreeView	217
DefaultDateFormat.....	27
DefaultDrawing.....	81
DefaultPageNumberFormat.....	28
DefaultTimeFormat.....	28
DesignerCaption.....	14
DesignerExists	29
DesignerHelpContext	14
DesignReport	29
Destroy.....	29
DestroyReport	30
DoChangeComponent	30
DoProgress.....	30
DrawBorder.....	138, 221
DrawCheckBox.....	30
DrawEdge	31
DrawGraphic.....	31
DrawGrid	82
DrawMode	50, 164, 230
DrawPageFooter.....	32
DrawPageHeader	32
DrawSortMark	33
DrawText	34
dxTreeView.....	214

E

Effects3D	51
-----------------	----

EmptyPagesCanExist	14
EndEllipsis	52
EvenColor	52, 164, 231
EvenFont	53, 165, 232
ExpandLevel	165, 204
ExtendedColorManage	165
ExtendedSelect	165, 233

F

FixedColor	54, 121
FixedFont	55, 121
FixedTransparent.....	55, 120, 167, 233
FlowChart.....	222
Font	15
FooterColor	233
FooterFont	167, 234
FootersOnEveryPage.....	15
FullExpand	139

G

GetFilteredStyles	34
GetPageColRowCount	34
GetSupportedComponentList	35
GraphicAsTextValue	167, 198
GridLineColor	56, 121, 167, 168, 204, 234
GroupColor	123
GroupFont	122
GroupNodeColor	168, 235
GroupNodeFont.....	168, 235

H

HeaderColor	168, 236
HeaderFont	168, 169, 237
HeadersOnEveryPage.....	15
HorzDelimitByBands	169

I

IncludeFixed.....	57
Index	15
Inspector.....	131
InternalRestoreDefaults.....	35, 77, 83, 97, 105, 141, 173, 223
InternalRestoreFromOriginal.....	35, 84, 98, 174
IsCurrentLink	16
IsDBGridLink	174, 193, 199
IsDBTreeListLink	174, 194, 200
IsEmptyReport	36
IsSupportedCompClass	36
IsTreeListLink.....	174, 188, 194

L

LinkClass	36
LinkModified	37
ListBox.....	103
LoadFromRegistry.....	37

M

MakeDelimiters	37, 175, 224
MasterView	227
Multiline.....	60

N

NodeAutoHeight	205
----------------------	-----

O

OddColor.....	60, 123, 169, 237
---------------	-------------------

OddFont	61, 124, 169, 238
OnChangeComponent	45
OnCustomDrawBandCell	176
OnCustomDrawCaption	128, 129
OnCustomDrawCell	78, 85, 177
OnCustomDrawFooterCell	177, 244
OnCustomDrawHeaderCell	178, 245
OnCustomDrawItem	91
OnCustomDrawNode	208
OnCustomDrawPageFooter	45
OnCustomDrawPageHeader	46
OnCustomDrawPreviewCell	179, 245
OnCustomDrawReportLinkTitle	46
OnCustomDrawRowFooterCell	179
OnCustomDrawValue	129
OnDestroy	47
OnFilterStyle	48
OnlySelected	61, 108, 170, 238
OnMeasureReportLinkTitle	48
Options	67, 96, 103, 125, 170, 171, 204, 239
OrgChart	139

P

PageCount	16
PageNumberFormat	16
PageReady	37
PageSetup	37
PageSetupEx	38
PaintItemsGraphics	103
PrepareConstruct	142
Preview	38
PreviewColor	171, 240
PreviewFont	171, 240
PreviewLineCount	171, 240
Print	39
PrintEx	39
PrintPages	40
PrintPagesEx	40

R

RealPrinterPage	16
RealScaleFactor	17
RebuildNeeded	19
RebuildReport	40
REHandle	108
ReportHeight	19
ReportTitle	20
ReportTitleMode	20
ReportTitleText	21
ReportWidth	21
RestoreDefaults	41
RestoreFromOriginal	41
RichEdit	112
RichEditVersion	109
RowAutoHeight	62
RowFooterColor	171
RowFooterFont	172
rxRichEdit	115

S

SaveToRegistry	41
ScaleFonts	17
SetActive	42
ShowDateTimeFormatsDlg	42
ShowDesigner	21
ShowEmptyPages	17
ShowPageFooter	22
ShowPageHeader	17
ShowPageNumberFormatsDlg	42
ShowTitlePropertiesDlg	43
ShrinkToPageWidth	22
Soft3D	62
StartPageIndex	18
StringGrid	74

StyleManager	18
SupportedCustomDraw	63, 126, 172, 205, 241

T

TAbstractdxGridReportLink	49
DrawMode	50
Effects3D	51
EndEllipsis	52
EvenColor	52
EvenFont	53
FixedColor	54
FixedFont	55
FixedTransparent	55
GridLineColor	56
IncludeFixed	57
Multiline	60
OddColor	60
OddFont	61
OnlySelected	61
RowAutoHeight	62
Soft3D	62
SupportedCustomDraw	63
TAbstractdxReportLinkDesigner	8
TAbstractdxReportLinkDesignWindow	9
TAbstractdxRichEditReportLink	107
OnlySelected	108
REHandle	108
RichEditVersion	109
TBasedxReportLink	40
PrintPagesEx	40
TBasedxReportLink	10
Active	11
AssignedFormatValues	11
BuildPageSetupMenu	24
CheckToDesign	26
Color	12
Component	12
ComponentPrinter	12
ConstructReport	27
Create	27
CurrentPage	12
CurrentPrintStyle	13
Data	13
DateFormat	13
DateTime	14
DefaultDateFormat	27
DefaultPageNumberFormat	28
DefaultTimeFormat	28
DesignerCaption	14
DesignerExists	29
DesignerHelpContext	14
DesignReport	29
Destroy	29
DestroyReport	29
DoChangeComponent	30
DoProgress	30
DrawCheckBox	30
DrawEdge	31
DrawGraphic	31
DrawPageFooter	32
DrawPageHeader	32
DrawSortMark	33
DrawText	34
EmptyPagesCanExist	14
Font	15
FootersOnEveryPage	15
GetFilteredStyles	34
GetPageColRowCount	34
GetSupportedComponentList	35
HeadersOnEveryPage	15
Index	15
InternalRestoreDefaults	35
InternalRestoreFromOriginal	35
IsCurrentLink	16
IsEmptyReport	36

IsSupportedCompClass	36	UnPrepareConstruct	142
LinkClass	36	UseMetafile	139
LinkModified	37	TCustomdxTeeChartReportLink	150
LoadFromRegistry	37	Chart	151
MakeDelimiters	37	ConstructReport	152
OnChangeComponent	45	TCustomdxTreeListReportLink	161
OnCustomDrawPageFooter	45	AutoNodesExpand	162
OnCustomDrawPageHeader	46	BandColor	163
OnCustomDrawReportLinkTitle	46	BandFont	163
OnDestroy	47	BandsOnEveryPage	163
OnFilterStyle	48	ConstructReport	173
OnMeasureReportLinkTitle	48	CustomTreeList	164
PageCount	16	DrawMode	164
PageNumberFormat	16	EvenColor	164
PageReady	37	EvenFont	165
PageSetup	37	ExpandLevel	165
PageSetupEx	38	ExtendedColorManage	165
Preview	38	ExtendedSelect	165
Print	39	FixedTransparent	167
PrintEx	39	FooterFont	167
PrintPages	40	GraphicAsTextValue	167
RealPrinterPage	16	GridLineColor	167
RealScaleFactor	17	GroupNodeColor	168
RebuildNeeded	19	GroupNodeFont	168
RebuildReport	40	HeaderColor	168
ReportHeight	19	HeaderFont	168, 169
ReportTitle	20	InternalRestoreDefaults	173
ReportTitleMode	20	InternalRestoreFromOriginal	174
ReportTitleText	21	IsDBGridLink	174
ReportWidth	21	IsDBTreeListLink	174
RestoreDefaults	41	IsTreeListLink	174
RestoreFromOriginal	41	MakeDelimiters	175
SaveToRegistry	41	OddColor	169
ScaleFonts	17	OddFont	169
SetActive	42	OnCustomDrawBandCell	176
ShowDateTimeFormatsDlg	42	OnCustomDrawCell	177
ShowDesigner	21	OnCustomDrawFooterCell	177
ShowEmptyPages	17	OnCustomDrawHeaderCell	178
ShowPageFooter	22	OnCustomDrawPreviewCell	179
ShowPageHeader	17	OnCustomDrawRowFooterCell	179
ShowPageNumberFormatsDlg	42	OnlySelected	170
ShowTitlePropertiesDlg	43	Options	170
ShrinkToPageWidth	22	PreviewColor	171
StartPageIndex	18	PreviewFont	171
StyleManager	18	PreviewLineCount	171
TimeFormat	18	RowFooterColor	171, 172
Transparent	23	RowFooterFont	172
UsingShrinkToPageWidthMode	44	SupportedCustomDraw	172
VisiblePageCount	19	UseColumnFont	172
TCustomdxGridReportLink	65	TCustomdxTreeViewReportLink	202
CustomGrid	66	AutoNodesExpand	203
Options	67	AutoWidth	203
TCustomdxInspectorReportLink	117	ExpandLevel	204
AutoNodesExpand	118	GridLineColor	204
AutoWidth	119	NodeAutoHeight	205
FixedColor	121	OnCustomDrawNode	208
FixedFont	121	Options	204
FixedTransparent	120	SupportedCustomDraw	205
GridLineColor	121	TreeView	205
GroupColor	123	Width	205
GroupFont	122	TdxCheckBoxReportLink	94
OddColor	123	CheckBox	95
OddFont	124	InternalRestoreDefaults	97
OnCustomDrawCaption	128	InternalRestoreFromOriginal	98
OnCustomDrawValue	129	Options	96
Options	125	TdxCustomListBoxReportLink	86
SupportedCustomDraw	126	AutoWidth	88
TCustomdxOrgChartReportLink	137	CustomListBox	87
BorderColor	138	OnCustomDrawItem	91
ConstructReport	141	TextAlignX	88
DrawBorder	138	TextAlignY	88
FullExpand	139	Width	89
InternalRestoreDefaults	141	TdxDBGridReportLink	190
OrgChart	139	DBGrid	192, 198
PrepareConstruct	142	DBTreeList	198
TransparentColor	139	GraphicAsTextValue	198

IsDBGGridLink	193, 199
IsDBTreeListLink	194, 200
IsTreeListLink	194
TdxDBInspectorReportLink	133
DBInspector	134
TdxDBOrgChartReportLink	147
DBOrgChart	148
TdxDBTeeChartReportLink	157
DBChart	158
TdxDBTreeListControlReportLink	185
DBTreeListControl	187
IsTreeListLink	188
TdxDBTreeListReportLink	196
TdxDBTreeViewReportLink	216
DBTreeView	217
TdxDGrReportLinkDesignWindow	79
TdxDrawGridReportLink	
InternalRestoreDefaults	83
TdxDrawGridReportLink	80
DefaultDrawing	81
DrawGrid	82
InternalRestoreFromOriginal	84
OnCustomDrawCell	85
TdxFCReportLinkDesignWindow	219
TdxFlowChartReportLink	220
BorderColor	221
ConstructReport	223
DrawBorder	221
FlowChart	222
InternalRestoreDefaults	223
MakeDelimiters	224
TransparentColor	222
UseMetafile	222
TdxInspectorReportLink	130
Inspector	131
TdxLBxReportLinkDesignWindow	100
TdxListBoxReportLink	101
InternalRestoreDefaults	105
ListBox	103
Options	103
PaintItemsGraphics	103, 104
TransparentGraphics	104
TdxMasterViewReportLink	226
AutoNodesExpand	228
CaptionColor	229
CaptionNodeFont	230
DrawMode	230
EvenColor	231
EvenFont	232
ExtendedSelect	233
FixedTransparent	233
FooterColor	233
FooterFont	234
GridLineColor	234
GroupNodeColor	236
GroupNodeFont	235
HeaderColor	233

HeaderFont	237
MasterView	227
OddColor	237
OddFont	238
OnCustomDrawFooterCell	244
OnCustomDrawHeaderCell	245
OnCustomDrawPreviewCell	245
OnlySelected	238
Options	239
PreviewColor	240
PreviewFont	240
PreviewLineCount	240
SupportedCustomDraw	241
TdxOCReportLinkDesignWindow	136
TdxOrgChartReportLink	144
TdxRichEditReportLink	111
RichEdit	112
TdxSGrReportLinkDesignWindow	72
TdxStringGridReportLink	
InternalRestoreDefaults	77
OnCustomDrawCell	78
TextAlignX	75
TextAlignY	75
TdxStringGridReportLink	73
StringGrid	74
TdxTLReportLinkDesignWindow	160
TdxTreeListReportLink	181
TreeList	183
TdxTreeViewExReportLink	213
dxTreeView	214
TdxTreeViewReportLink	210
TextAlignX	75, 88
TextAlignY	75, 88
TimeFormat	18
Transparent	23
TransparentColor	139, 222
TransparentGraphics	104
TreeList	183
TreeView	205
TrxRichEditReportLink	114
rxRichEdit	115
TStdxdxGridReportLink	6

U

UnPrepareConstruct	142
UseColumnFont	172
UseMetafile	139, 222
UsingShrinkToPageWidthMode.....	44

V

VisiblePageCount.....19

W

Width..... 89, 205