
Assembly Language Macros

- An assembly language **macro** is a template whose format represents a pattern of 0 or more assembly language statements that might be common to multiple programs.
- For this purpose, a *macro language* is used to provide a syntax for defining macros.
- Where a sequence of assembly language statements can be represented by a macro, a *macro call* is inserted into the assembly program source code where the assembly code would otherwise go.
- A *macro facility* is used to interpret macro definitions and expand each macro call as it occurs with the requisite pattern of assembly language statements, providing *expanded source code* ready for the assembler.


Hence, the macro facility is a *preprocessor*, which interprets all macro calls into assembly code prior to passing the *expanded code* on to the assembler. A macro facility is an add-on piece of system software, a convenience for the programmer, to facilitate production of multiple lines of commonly occurring code via single macro calls embedded in the programmer's assembly program. The macro preprocessor included with C compilers (with calls such as #include) uses the same idea, albeit assembly language macro facilities predate the similar compiler preprocessors.

Macro Definition

- Assembly language macro definitions can be predefined and placed in a macro library, or can be included "in-line" with the assembly language program.
- The handling sequence for the program becomes:



Macro Definition Format



Note that the macro prototype statement differs from that of the course text book to permit inclusion of a label.

A First Example: PUTC


Consider the following simple definition of a macro for the output of a character:

	MACRO	
&INIT	PUTC	&CHAR, &DEV
&INIT	STA	PUTCSAVE
	LDCH	&CHAR
	J	PUTCLOOP
PUTCSAVE	RESW	1
PUTCLOOP	TD	&DEV
	JEQ	PUTCLOOP
	WD	&DEV
	LDA	PUTCSAVE
	MEND	

If our assembler comes with a macro facility for handling this format, then PUTC can be used in a program in the same manner as an instruction. In particular, if the definition of PUTC is in the macro library or included "in-line" in the assembly code, then the preprocessor will be able to expand any statement whose op code is PUTC.

Macro Expansion of of PUTC (first version)

Suppose that you have a code fragment utilizing PUTC as follows:



Then the macro facility will apply the PUTC definition to produce the expanded code:

. . .

	JEQ	NEXT
.DUMPX	PUTC	(LINE,X), =X'04'
DUMPX	STA	PUTCSAVE
	LDCH	LINE,X
	J	PUTCLOOP
PUTCSAVE	RESW	1
PUTCLOOP	TD	=X'04'
	JEQ	PUTCLOOP
	WD	=X'04'
	LDA	PUTCSAVE
NEXT	STA	LAST

. . .

Note that the parentheses around LINE, X are stripped (parentheses are used to group comma separated items).

Problems with the First Version of PUTC

The PUTC macro definition given as a first example has a severe flaw in that it can only be used once in any given assembly language program. If it was used a second time, the labels PUTCSAVE and PUTCLOOP would get generated again in the expansion of PUTC in its second location, which in turn would cause a "duplicate label" error when the expanded code is passed on to the assembler.

System Variables

To correct for this problem, two additional types of macro "*system variables*" are provided to go with the & prefixed variable names of the prototype statement:

- 1. **Set Variables** & prefixed variables that can be "set" by the SET directive (with limited arithmetic capability); e.g. &GCNT.
- 2. **System Qualifiers** \$ prefixed symbols with a value that is automatically adjusted to a new value each time a macro expansion (not necessarily the same macro) occurs; e.g., \$LOOP. \$ is expanded to \$AA for the 1st macro expansion, \$AB for the 2nd and so forth.

Concatenation of Symbols

Macro text elements *can be concatenated together*; for example, if the prototype statement has the label &INIT and appears in the macro definition in the construction

```
ONE&INIT
```

then if the value of &INIT is DUMPX, the macro facility will expand the construction as

```
ONEDUMPX
```

Note that this can be interpreted successfully because the & and trailing blank allow &INIT to be identified. If the order was reversed (&INITONE) this would not be possible. For this case, the symbol \rightarrow (or \sim) is used to provide a right delimiter; i.e.,

```
&INIT-ONE
```

Hence a construction such as

X&PARM→Y

generates

X12Y

if &PARM has the value 12.

Revised PUTC using SET Variables

If we revisit the PUTC macro taking advantage of set variables, an "improved" construction might be:

&GCNT	SET	0	(global SET)
	MACRO		
&INIT	PUTC	&CHAR, &DEV	
&GCNT	SET	&GCNT + 1	
&INIT	STA	SAVE&GCNT	
	LDCH	&CHAR	
	J	LOOP&GCNT	
SAVE&GCNT	RESW	1	
LOOP&GCNT	TD	&DEV	
	JEQ	LOOP&GCNT	
	WD	&DEV	
	LDA	SAVE&GCNT	
	MEND		

The global SET takes place as the macro definitions are read, initializing the set variable to 0. It is subsequently incremented by the internal SET statement each time the PUTC macro is expanded.

Macro Expansion of Second Version of PUTC

Using the same code fragment as for the first version of PUTC,

. . .

DUMPX NEXT	JEQ PUTC STA	NEXT (LINE,X), LAST	=X'04'

. . .

for the sake of illustration assume that 4 prior macro calls for PUTC have occurred before the macro facility encounters this code fragment, so the value of the global set variable &GCNT has incremented to 4. Then the expansion in this case will be

. . .

	JEQ	NEXT
.DUMPX	PUTC	(LINE,X), =X'04'
DUMPX	STA	SAVE5
	LDCH	LINE,X
	J	LOOP <mark>5</mark>
SAVE5	RESW	1
LOOP5	TD	=X'04'
	JEQ	LOOP5
	WD	=X'04'
	LDA	SAVE <mark>5</mark>
NEXT	STA	LAST

. . .

Note that the in expanding the call, the macro facility incremented the value of &GCNT from 4 to 5.

Problems with the Second Version of PUTC

There is still a potential problem with the approach of using set variables, because a name such as SAVE3 is one a programmer might use (and so inadvertently set up code for which the macro facility produces a duplicated symbol).

System Qualifiers

For this reason, *special system qualifiers* are provided. In this case the convention is that under macro expansion, the "\$" symbol is replaced by

\$AA	within the 1 st macro expansion
\$AB	within the 2 nd macro expansion
\$AZ \$A0	within the 26 th macro expansion within the 27 th macro expansion
\$A9 \$BA	etc.
 \$Z9	

The \$ system qualifier is advanced for each macro expansion, whether or not the expansion makes use of it.

A Final Version of PUTC using System Qualifiers

Revisiting the PUTC macro using system qualifiers, an "even better" construction might be:

	MACRO		
&INIT	PUTC	&CHAR, &DI	ΞV
&INIT	STA	\$SAVE	
	LDCH	&CHAR	
	J	\$L00P	
\$SAVE	RESW	1	
\$L00P	TD	&DEV	
	JEQ	\$L00P	
	WD	&DEV	
	LDA	\$SAVE	
	MEND		

This time, if 4 prior macro expansions have occurred, *not* necessarily to PUTC and not necessarily using the \$ system qualifier, the \$ system qualifier has been advanced through \$AA, \$AB, \$AC, and \$AD, so for this expansion the code will be

. . .

	JEQ	NEXT
.DUMPX	PUTC	(LINE,X), =X'04'
DUMPX	STA	\$AESAVE
	LDCH	LINE,X
	J	\$AELOOP
\$AESAVE	RESW	1
\$AELOOP	TD	=X'04'
	JEQ	\$AELOOP
	WD	=X'04'
	LDA	\$AESAVE
NEXT	STA	LAST

Each macro expansion gets its own \$ system qualifier, whether or not it uses the \$ system qualifier.

Macro Calls Within a Macro

There is no reason that the macro facility cannot successfully process a macro call within a macro. For example,

	MACRO	
&TOP	PUTMSG	&MSG, &DEV, &LEN
&TOP	STA	\$SAVA
	STX	\$SAVX
	CLEAR	X
\$LOOP	PUTC	((&MSG,X)), &DEV
	TIX	&LEN
	JLT	\$L00P
	LDA	\$SAVA
	LDX	\$SAVX
	J	\$NEXT
\$SAVA	RESW	1
\$SAVX	RESW	1
\$NEXT	RESW	0
	MEND	

Observations

- The PUTMSG macro (and the PUTC macro for that matter) generate code that first *saves the system state* (by saving the registers it works with), then restores the system state upon exit. Strictly speaking, this is not necessary (the programmer could do it), but it is advisable since the whole idea of using macros is to save the programmer work.
- The value of the \$ system qualifier for a PUTMSG macro expansion is resumed after the PUTC expansion contained within it is completed (although PUTC gets its own \$ system qualifier value). This means that if PUTMSG is used twice in succession by a programmer, then if for the first expansion the \$ system qualifier has value \$AC, on the 2nd call the \$ system qualifier for PUTMSG will have the value \$AE since there was an intervening expansion of PUTC (which gets the \$ system qualifier value of \$AD).

Example Macro Expansion of PUTMSG

For the code fragment,

. . .

JEQ NEXT

DUMPM PUTMSG =C'COP 3601', =X'04', MSGLEN

NEXT STA LAST

. . .

assuming that 4 prior macro expansions have occurred before the macro facility encounters this code fragment (so the \$ system qualifier is at \$AE), then the expansion will be

Note: the macro facility has to be "smart enough" to not expand \$ a 2^{nd} time NEXT JEO =C'COP 3601', =X'04', MSGLEN . DUMPM **PUTMSG** DUMPM STA \$AESAVA STX \$AESAVX CLEAR Χ (=C'COP 3601',X), =X'04'.\$AELOOP **PUTC** \$AELOOP STA \$AFSAVE LDCH =C'COP 3601',X J \$AFLOOP \$AFSAVE RESW 1 \$AFLOOP TD= X' 04**PUTC** expansion: JEQ \$AFLOOP (\$ system qualifier =X'04 WD*has the value* \$AF) \$AFSAVE LDA TIX MSGLEN JLT\$AELOOP LDA \$AESAVA \$AESAVX LDXJ \$AENEXT PUTMSG expansion: \$AESAVA RESW 1 (\$ system qualifier 1 \$AESAVX RESW *has the value* \$AE) \$AENEXT RESW 0 NEXT LAST STA

. . .

Conditional Assembly

Conditional Assembly in a macro facility refers to mechanisms for providing program control over the code generation process. These require the addition of macro facility commands such as

- IF-ELSE-ENDIF
- WHILE-ENDW
- GOTO

along with branch point labels (e.g., !EXIT) and representational forms for comparison; e.g.,

EQ	for =	NE	for ≠
LT	for <	LTE	for <=
GT	for >	GTE	for >=

and logical operators AND, OR, NOT with the usual parenthesis grouping.

Additionally, since the macro facility is essentially a text processor, it is necessary to provide at least rudimentary string processing capabilities, including *system functions* for

- working with comma separated lists (%NITEMS)
- length of input parameters (%LENGTH)
- substrings (%SUBSTR)
- indexing into a string (e.g., &MSG[0], or &INIT[2])

%NITEMS() is the number of parameters given by the programmer; if a parameter &L is a comma separated list, then **%NITEMS(&L)** gives the number of items in the list.

```
%LENGTH(&L) gives the length of &L as a text string.
```

%SUBSTR(&L, 3, 4) gives the (up to) length 4 substring of &L starting from index 3.

&L[2] gives the character at index 2 of &L. &L[2,4] gives the string consisting of the characters at indices 2 and 4 of &L.

For example, given the macro definition

	&LABL		&TWO, &ONE
	&LABL	ELSE ST→&ONE RMO LD→&TWO	\$TEMP &TWO, &ONE \$TEMP
	\$TEMP SNEXT	J RESW RESW ENDIF MEND	\$NEXT 1 0
			NITEMS() = 3
the	en the call		
un	on the can	SWAPR <	S, T, SWAPAREA
ha	s the expansion		
	•	SWAPR	S, T, SWAPAREA
		STA	SWAPAREA
		RMO	S,T
		LDT	SWAPAREA
an	d the call (first mad	cro call, so \$	
ha	s the expansion	SWAPR	S, T
Ha	s the expansion		
	•	SWAPR	S, T
		STA	\$AATEMP
		RMO	S,T
		LDT	\$AATEMP
		J	\$AANEXT
	\$AATEMP	RESW	1
	\$AANEXT	RESW	0

Keyword and Positional Parameters

The prototype statement's parameter list as given to this point uses what are known as *positional parameters*. The position of the parameter in the comma separated list determines which entry it represents (note two successive commas in the list represents an omitted parameter).

A *keyword parameter* is one specified in the comma separated list by the form &<name>=<value> or &<name>= . In the first form, <value> is the default used in the macro's expansion if the programmer does not supply the parameter. In the second form, the programmer must supply the value (by name). For example, if we revise the prototype statement for the final version of PUTC to be

&INIT PUTC &CHAR=, &DEV==X'04'

then for the call

PUTC CHAR=MSG

then the expansion (first macro call, so $\$ \rightarrow \AA) is

•	PUTC	CHAR=MSG
	STA	\$AASAVE
	LDCH	MSG
	J	\$AALOOP
\$AASAVE	RESW	1
\$AALOOP	TD	=X'04'
	JEQ	\$AALOOP
	WD	=X'04'
LDA	\$AASAVE	

If the next call is

then the expansion is

.LOOP	PUTC	CHAR=MSG, DEV==X'05'
	STA	\$ABSAVE
	LDCH	MSG
	J	\$ABLOOP
\$ABSAVE	RESW	1
\$ABLOOP	TD	=X'05'
	JEQ	\$ABLOOP
	WD	=X'05'
LDA	\$ABSAVE	

The same expansion would have resulted if the call had been

In other words, because the parameters are "named" by the keywords, the order in which they are given does not matter. Key word parameters are sometimes used in combination with positional parameters to provide a default. For example, if the PUTC prototype statement was

then the &CHAR parameter is specified by position and the &DEV parameter is a keyword parameter with a default. In this case the following calls are all equivalent:

It may be argued that using keyword parameter lists burdens the programmer with having to remember names, but it can be very convenient for providing default values, and is particularly useful if there are multiple parameters needed in the macro.


For a simple example taking advantage of both conditional assembly and keyword parameters, suppose that you want a macro that decides whether to use TIX or TIXR; i.e., you want a call such as

MYTIX TLOC

to expand as

•	MYTIX	TLOC
	TIX	TLOC
and a call s	 MYTIX	REG=A
	MYTIX	REG=A
	TIXR	A

The form the macro definition might take is



It is also perfectly OK is a macro doesn't even generate any code; for example, consider the macro to lay in code for incrementing register X via the TIXR operation.

&INIT &CNT &CNT	MACRO INCRX SET WHILE TIXR SET ENDW MEND	&AMT &AMT (&CNT GT 0) X &CNT - 1
Then the call has the expansion	INCRX	4
	INCRX	4
	TIXR	X
and the call has the expansion	INCRX	0
	INCRX	0