

OpenText™ Identity Manager

Email Notification Guide

Version : 25.4

PDF Generated on : April 21, 2026

Table of Contents

1. Email Notification Guide	1
1.1. Overview	2
1.1.1. System Email Notifications	3
1.1.2. Custom Email Notifications	4
1.1.3. Default Notification Collection	5
1.2. Designating an Email Server	6
1.2.1. Designating an Email Server in Designer	7
1.2.2. Designating an Email Server in OpenText Identity Console	9
1.3. Editing Predefined Templates	11
1.3.1. List of Predefined Templates	12
1.3.2. Editing a Template in Designer	16
1.3.3. Editing a Template in OpenText Identity Console	19
1.4. Creating Templates	21
1.4.1. Creating a Template in Designer	22
1.4.2. Creating a Template in OpenText Identity Console	24
1.5. Importing Templates Into Designer	26
1.5.1. Importing a Template from the Identity Vault	27
1.5.2. Importing a Template from another Designer Project	28
1.6. Using Templates	29
1.7. Tokens and Replacement Tags	30

1. Email Notification Guide

This guide explains how to configure your OpenText Identity Manager system to send email notifications to administrators and users when certain events occur.

This book is intended for OpenText Identity Manager administrators, partners, and consultants.

1.1. Overview

OpenText Identity Manager sends email notifications to designated recipients whenever certain actions occur. The following sections provide the conceptual information needed to understand and complete the tasks associated with using email notifications.

- [System Email Notifications](#)
- [Custom Email Notifications](#)
- [Default Notification Collection](#)

1.1.1. System Email Notifications

OpenText Identity Manager includes functionality, such as password management, jobs, and workflow provisioning, that can utilize email messages to notify administrators or users of actions or results that have taken place. For example, email messages can be sent to:

- Notify a user who has reset his or her password that the action failed.
- Provide a password to a user who has used the Forgotten Password feature to request the password.
- Notify you, or another administrator, of the results of a job that has just run.
- Inform a manager, or another approver, that a provisioning request awaits his or her approval.

OpenText Identity Manager provides a set of predefined email notification templates to send customized and action-specific information in the message. For example, there is an email template for forgotten passwords and one for when a manager needs to approve a user's request for access to a resource.

In most cases, the system functionality (password management, jobs, and so forth) must be configured to use email notifications, and the text in the email templates must be modified to fit your environment and needs. For mor information, see [Editing Predefined Templates](#).

1.1.2. Custom Email Notifications

You can send email notifications through actions you define in policies. For example, if you use the Active Directory driver to create Microsoft Exchange mailboxes for Active Directory users, you can include an action in the Active Directory driver policy to send emails to users.

Policies include two email notification actions:

- **Send Email:** Includes the email information in the action.
- **Send Email from Template:** References a custom email notification template you create. For information about creating templates, see [Creating Templates](#).

1.1.3. Default Notification Collection

The Default Notification Collection is an Identity Vault object containing a set of email notification templates and an SMTP server used while sending emails generated from the templates.

The predefined email notification templates are included in the Default Notification Collection. Any custom templates that you create are also added to the collection. You must define the SMTP server that you want associated with the collection. For more information, see [Designating an Email Server](#).

1.2. Designating an Email Server

Before using any email notification templates included in the Default Notification Collection, you must associate an SMTP server with the collection. Whenever an email is generated from one of the collection's templates, the SMTP server is used to send the email.

- [Designating an Email Server in Designer](#)
- [Designating an Email Server in OpenText Identity Console](#)

1.2.1. Designating an Email Server in Designer

1. Open your project.
2. In the Outline view, locate the **Default Notification Collection** under the Identity Vault.
3. Right-click the collection, then select **Properties** to display the email Notification Server page.

Properties for Default Notification Collection

E-Mail Notification Server

Enter the settings for your E-Mail notification server:

Host Name:

From: (for example: admin@novell.com)

Time Out Value(Seconds):

☐ Do you want to enable SSL ?

☐ Authenticate to the server by using credentials

User Name:

Password:

Retype Password:

OK Cancel

4. Fill in the following fields to define the SMTP email server.

Host Name: The hostname/IP address of your SMTP email server. You can also specify a port along with the hostname/IP address using the following syntax:

`<server_url>:<port>`

From: When a user opens the email, the text you enter in the **From** edit box is displayed in the **From** field of the user's email heading. Depending on your mail server settings, the text in this field might need to match a valid sender in the

system (for example, `helpdesk@company.com`) instead of descriptive text such as The Password Administrator. Such a match allows the mail server to do reverse lookups or authentication.

Time Out Value: Specify the value in seconds.

Do you want to enable SSL: Use this option to enable SSL.

Authenticate to the server by using credentials: Use this option for a secured SMTP server.

If your server requires authentication before sending email, specify the username and password here.

Although the authentication information is specified here, you might also need to specify it separately for the application sending the notification emails.

For example, Forgotten Password email notifications can be sent by using the authentication information you specify here. However, notification emails for OpenText Identity Manager Password Synchronization require the authentication information to be provided in the driver policy used to send notification emails.

5. Click **OK**.

1.2.2. Designating an Email Server in OpenText Identity Console

1. On the home page, click **Email Server Configuration**.
2. On the Email Server Options page, specify the values for your email notification server.

- **Host Name:** Specify the hostname or IP address of your SMTP server along with the port number. Use a colon (:) to separate the hostname or IP address and port.

For example, `smtp.example.com:587`

- **From:** Specify the sender's email address. The email server performs reverse lookups or authentication using this value.
- **Time Out Value:** The timeout option allows you to set the time limit (in seconds) to send notification emails.
- **Enable SSL:** Select to enable SSL, if required.

3. (Conditional) If your server requires basic authentication before sending emails, select **Authentication Required** as `Basic Authentication` and provide your username and password.

Although the authentication information is specified here, you might also need to specify it separately for the application sending the notification emails.

For example, Forgotten Password email notifications can be sent by using the authentication information you specify here. However, notification emails for OpenText Identity Manager Password Synchronization require the authentication information to be provided in the driver policy used to send notification emails.

4. (Conditional) If your server requires modern authentication before sending email, select **Authentication Required** as `Modern Authentication` and provide values for the following parameters:



Note

Register the OpenText Identity Console application with Azure AD to get the values for these parameters. For more information about registering your application, see "Register an application in Microsoft Entra ID" in the Microsoft documentation.

- **User Id:** Specifies the account required for server authentication.
- **Tenant Id:** Specifies the Global Unique Identifier (GUID) for your registered account on Azure Active Directory. Also referred to as the Tenant (Directory) ID.
- **Client Id:** Specifies the unique ID assigned by Azure Active Directory to your OpenText Identity Manager. Also referred to as the Application (client) ID.
- **Client Secret** Specifies a secret string that OpenText Identity Manager uses to prove its identity when requesting an access token. This encrypted value is unique for your application.
- **Scope:** Specify the scope of the server.
- **Request Url:** Specifies the request URI of your email server, to which OpenText Identity Manager sends authentication requests containing the client secret, scope, grant type, and auth mechanism in the payload.

For example,

`https://login.microsoftonline.com/<tenantID>/oauth2/v2.0/token`

- **Grant type:** Used by OpenText Identity Console to obtain an access token to access their own resources, not on behalf of a user. The Grant Type parameter is set to `client_credentials` by default and cannot be modified.
- **Auth mechanism:** Specifies the format used by the application to encode and transmit the access token to the authentication server. The access token authenticates a user's Outlook account. By default, Auth Mechanism is set to `XOAUTH2` and cannot be modified.

5. Click **Save**.

1.3. Editing Predefined Templates

OpenText Identity Manager includes predefined templates that are used with the password management, jobs, and workflow provisioning functionality. In most cases, you need to change the templates to reflect your environment. For example, several of the templates include example contact information that you should correct for your organization.

The following sections provide information about editing the predefined templates:

- [List of Predefined Templates](#)
- [Editing a Template in Designer](#)
- [Editing a Template in OpenText Identity Console](#)

1.3.1. List of Predefined Templates

The predefined templates are listed according to the OpenText Identity Manager functionality with which they are used:

- [Forgotten Password](#)
- [Password Synchronization](#)
- [Workflow Provisioning](#)
- [Jobs](#)

Forgotten Password

The following templates are used with the Forgotten Password functionality in the User Application.

Forgotten Password Templates

Template Name	Description
Forgot Hint	Provides a hint to a user who has forgotten a password.
Forgot Password	Provides a password to a user who has forgotten their password.

Password Synchronization

The following templates are used with the Password Synchronization functionality available for the OpenText Identity Manager drivers. For more information, see [Configuring Password Flow](#).

Password Synchronization Templates

Template Name	Description
Password Reset Fail	A notification that the reset password did not meet password policy requirements and was not accepted.
Password Set Fail	A notification that a password cannot be set in a connected system.
Password Sync Fail	A notification that a password failed to synchronize.

Workflow Provisioning

The following templates are used with the Workflow Provisioning functionality in the User Application. For more information, see [Managing Provisioning Workflows](#).

Workflow Provisioning Templates

Template Name	Description
Attestation Completed Notification	A notification that the workflow process for an attestation request is completed.
Attestation Notification	A notification that a new compliance activity has been submitted that requires attention.
Availability	A notification that an availability setting has been created or modified.
Delegate	A notification that a delegate assignment has been created or modified
Provisioning Approval Completed Notification	A notification that a workflow is completed. Indicates the overall workflow and provisioning decision.
Provisioning Notification	A notification to a user or manager for approval. Indicates that action is required from the user or manager.
Provisioning Notification Activity	A notification to a user or manager about the activity of the provisioning notification.

Template Name	Description
Provisioning Reminder	A notification to a user that an activity timeout is about to occur. Reminds the user or manager to act.
Proxy	A notification that a proxy assignment has been created or modified.
Role Request Approval Completed Notification	A notification that the approval process is completed.
Role Request Notification	A notification that a new role request requires approval.

Jobs

The following template is used with the engine's Jobs functionality. For more information, see [Adding a Predefined Job](#).

Jobs Template

Template Name	Description
Default Job Notification	Report results of the job as configured in the template. Contains the name of a job and any status information from the job.

1.3.2. Editing a Template in Designer

1. Open your project.
2. In the Outline view, locate and expand the **Default Notification Collection** to display the default templates.
3. (Conditional) If no templates are displayed under the **Default Notification Collection**, right-click **Default Notification Collection** and click **Add Default Templates**.
4. Double-click the template you want to edit.

The screenshot shows the 'E-Mail Template Editor' window. At the top, the title bar says 'E-Mail Template Editor'. Below it, the breadcrumb path is 'Forgot Hint.Default Notification Collection.Identity Vault'. The main area is titled 'E-Mail Content'. It has two tabs: 'Send As' (HTML) and 'Text'. The 'Subject' field contains 'Your password hint request'. To the right, there is a 'Tokens' list with '\$UserFullName\$' and '\$Hint\$', and buttons for 'New...', 'Remove', and 'Insert'. Below the subject field is the 'Message' field, which contains HTML code for the email body. The code includes a title, a style for the font-family (Trebuchet MS), and a body with a white background color. The body text reads: 'Dear \$UserFullName\$', 'You have requested that your password hint be emailed to you. The password hint is given below:', 'Hint: \$Hint\$', and 'If you did not request that your hint be emailed to you, please contact the...'. A toolbar with various formatting icons is visible above the message field.


5. In the **Send As** field, select whether to send the email in HTML or text format.
6. In the **Subject** field, type the text you want users to see in the email's Subject line.

You can use tokens in the Subject field. To do so, click where you want to insert the token, select the token from the **Tokens** list, then click **Insert**. For information about adding new tokens, see [Tokens and Replacement Tags](#).

7. In the **Message** box, type the message you want.
 - To format text, use the toolbar.



- To insert HTML tags, place your cursor in the Message box at the location where you want to insert a tag, then press Ctrl+Spacebar or type `<` to display a list of HTML tags to choose from.



- To insert a token, place your cursor in the Message box at the location where you want to insert the token, select the token in the Tokens list, then click **Insert**. For information about adding new tokens, see [Tokens and Replacement Tags](#).
 - To preview the message, click the **Preview** icon .
8. To attach an image to an email, ensure that you place the image files in the correct directory depending on your platform:
- **UNIX/Linux:** Place the images in the `/opt/novell/eDirectory/lib/dirxml/rules/manualtask/mt_files` directory.
 - **Windows:** Place the images in the `<eDirectory installation folder>\NDS\mt_files` directory.
1. In your email template, use the following syntax to attach images:

```
<p> <img ALT="your image" SRC="cid:orchid.gif"
height="29
width="80/> </p>
```

where orchid is the name of the image.

Because the file name is case sensitive, the name of the file (image) must exactly match the file name in the directory.

2. Restart the system after placing the image files in the correct directory for your platform.

For example, if an email has already been sent, you need to restart ndsd/eDirectory for it to use the new image.

- **UNIX/Linux:** Restart ndsd.
- **Windows:** Restart OpenText eDirectory.

9. Right-click the template and click **Save As**.

10. To deploy the template into your live system, right-click the template, click **Live > Deploy**.

1.3.3. Editing a Template in OpenText Identity Console

1. On the home page, click **Email Notification Templates**.
2. Click the email template you want to edit.
3. Customize the template with your own text.
 - **Template Name:** Displays the name of the template.
 - **Subject:** The text a user views in an email's Subject headline. You can change the text of the subject line. The actual name of the template remains the same.
 - **Send As:** The format the SMTP server uses to send the email: Text or HTML.
 - **Tokens or Replacement Tags:** The replacement tags help you personalize the message for the user. You can copy replacement tags from the available tags to the message. You can also type the tag in the message text. For information about adding new tokens, see [Tokens and Replacement Tags](#).

Each template includes default tokens or replacement tags, which are variables needed to personalize the email for the user. For example, the Forgot Password email template for sending a password to the user includes the default token or replacement tag named 'CurrentPassword.'

- **Add:** You can define other tokens or replacement tags for use in the body of the message.

To add a token or replacement tag, perform the following steps:

1. Click **+ Add Tag**.
2. Specify the **Name** and **Description** in the Add Replacement Tag window.
3. Click **OK**.

The new token or replacement tag is listed in the Replacement Tags column.

- **Copy Tag:** Click the **Copy Tag** icon to copy the selected tag to the system buffer, then copy and utilize it in the subject line or body of the message.
 - **Delete:** Select a token or replacement tag in the list and click **the Delete Tag** icon to delete it from the list. Ensure you do not remove tags needed for the body of the message.
 - **Message Body:** The text of the email message.
4. To attach an image to an email, follow [Step 8](#) in [Editing a Template in Designer](#).



Important

OpenText Identity Console enforces some restrictions on adding or editing some attributes in HTML tags, such as `src`. You must use Designer to edit these attributes.

5. Click **Update** after specifying all the email notification template modifications.

1.4. Creating Templates


You can create email notification templates to support custom functionality you implement in OpenText Identity Manager. For example, if you use the Active Directory driver to create Microsoft Exchange mailboxes in Active Directory, you can include an action in the Active Directory driver policy that sends emails to the users when their mailbox has been created. To support this email, you can create a template that includes the message required to inform the user about the new mailbox

The following sections provide information about creating new templates:

- [Creating a Template in Designer](#)
- [Creating a Template in OpenText Identity Console](#)

1.4.1. Creating a Template in Designer

1. Open your project.
2. In the Outline view, right-click **Default Notification Collection** > click **New Template** to display the Add Notification Template dialog box.
3. In the **Name** field, type a name for the template.
4. Make sure the **Open the editor after creating a template** option is selected, click **OK** to create the template, and display the template editor.




5. In the **Send As** field, select whether to send the email in HTML format or in text format.
6. In the **Subject** field, type the text you want users to see in the email's Subject line.

You can use tokens in the Subject field. To do so, click where you want to insert the token, select the token from the **Tokens** list, then click **Insert**. For information about adding new tokens, see [Tokens and Replacement Tags](#).
7. In the **Message** box, type the message you want.
 - To format text, use the toolbar.



- To insert HTML tags, place your cursor in the Message box at the location where you want to insert a tag, then press Ctrl+Spacebar or type `<` to display a list of HTML tags to choose from.



- To insert a token, place your cursor in the Message box at the location where you want to insert the token, select the token in the Tokens list, then click **Insert**. For information about adding new tokens, see [Tokens and Replacement Tags](#).
- To preview the message, click the **Preview** icon .

8. Click **OK** to save the template.

9. To deploy the template into your live system, right-click the template, click **Live** > **Deploy**.

1.4.2. Creating a Template in OpenText Identity Console

1. On the home page, click **Email Notification Templates**.
2. Click **+ Create a new template**.
3. Specify a name for the new template (for example, Approval) and click **OK**.

If you have disabled pop-ups, return to the Edit Email Notification Template pop-up. The new template name appears in the Name column, but [No Subject] appears in the Subject headline column. In this case, click [No Subject] to provide details in the new template.

4. The Edit Email Notification Template page enables you to modify the email template. You can customize the template with your own text.
 - **Template Name:** Displays the name of the template.
 - **Subject:** The text a user views in an email's Subject headline. You can change the text of the subject line. The actual name of the template remains the same.
 - **Send As:** The format the SMTP server uses to send the email: Text or HTML.
 - **Tokens or Replacement Tags:** The replacement tags help you personalize the message for the user. You can copy replacement tags from the list of available tags and paste them into the message. You can also type the tag in the message text. For information about adding new tokens, see [Tokens and Replacement Tags](#).

Each template includes default tokens or replacement tags, which are variables needed to personalize the email for the user. For example, the Forgot Password email template for sending a password to the user includes the default token or replacement tag named 'CurrentPassword.'

- **Add:** You can define other tokens or replacement tags for use in the body of the message.

To add a token or replacement tag, perform the following steps:

1. Click **+ Add Tag**.

2. Specify the **Name** and **Description** in the Add Replacement Tag window.

3. Click **Ok**.

The new token or replacement tag is listed in the Replacement Tags column.

- **Copy Tag:** Click the **Copy Tag** icon to copy the selected tag to the system buffer, and then you can click the mouse to paste it and utilize it in the subject line or body of the message.
- **Delete:** Select a token or replacement tag in the list and click the **Delete Tag** icon to delete it from the list. Ensure you do not remove tags that are needed for the body of the message.

- **Message Body:** The text of the email message.

5. Click **Update** after specifying all the email notification template modifications.

1.5. Importing Templates Into Designer

To work on an email notification template located in the Identity Vault but not in your Designer project, you must import the template into the Designer project. Likewise, to copy a template from one Designer project to another, you must save it from the first project and import it into the second project.

The following sections explain how to accomplish each of these tasks:

- [Importing a Template from the Identity Vault](#)
- [Importing a Template from another Designer Project](#)

1.5.1. Importing a Template from the Identity Vault

The following situations can result in templates being located in your Identity Vault but not in your Designer project:

- OpenText Identity Console is used to modify a predefined template or create a new template.
- A template is created or modified in one Designer project and deployed to the Identity Vault. You now need it in another Designer project.

To import a template from the Identity Vault into a Designer project:

1. In Designer, open the project into which you want to import the template.
2. In the Outline view, right-click **Default Notification Collection**, then click **Live > Import** to display the **Import from Identity Vault** dialog box.
3. Click **Browse**, select the template to import, then click **OK** to add the template to the list of objects to import in the **Import from Identity Vault** dialog box.
4. Click **Continue** to display the Import Summary dialog box.
5. Click **Import**, then click **OK** when the import results are displayed.

1.5.2. Importing a Template from another Designer Project

If you create or edit a template in one Designer project, you can import it to another Designer project.

1. In Designer, open the source project. This is the project with the template you want to copy.
2. Save the template to a file:
 1. In the Outline view, locate and expand the **Default Notification Collection**, right-click the template, then click **Save As** to display the **Save As** dialog box.
 2. Select the folder where you want to save the template file, then click **Save**.
3. Import the template file into the target project:
 1. Open the target project.
 2. In the Outline view, right-click the **Default Notification Collection**, then click **Import Template from File**.
 3. Select the template file, then click **Open** to add it to the project.

If a template with the same name already exists, you are prompted to overwrite it.

Another way to copy the template is to deploy it from the source project into the Identity Vault and then import it into the target project (as explained in [Importing a Template from the Identity Vault](#)).

1.6. Using Templates

The predefined templates (see [List of Predefined Templates](#)) are associated with existing OpenText Identity Manager functionality. Refer to the following guides for information about using these templates:

- **Forgotten Password/Hint Templates:** See Password Management Configuration in the [Administrator's Guide to the Identity Applications](#).
- **Password Synchronization Templates:** See [Configuring Password Flow](#) in the [Password Management Guide](#).
- **Workflow Provisioning Templates:** See [Managing Provisioning Workflows](#) in the [Administrator's Guide to the Identity Applications](#).
- **Jobs Template:** See [Adding a Predefined Job](#) in the [Jobs Guide](#).

For information about using templates with policies, see [Send Email from Template](#) in the [Using Designer to Create Policies](#) guide. For an example of implementing templates in a policy, see [Configuring Email Notification](#) in the [Password Management Guide](#).

1.7. Tokens and Replacement Tags

Tokens or replacement tags are variables used in the message body and subject of email notification templates.

Each predefined template includes default tokens. For example, the Forgot Password email template (for sending a password to a user) includes a default token named `$CurrentPassword$`. When the email is sent, the `$CurrentPassword$` token is replaced with the user's current password.

For a token to work in an email template, it must be defined in the application or the policy that initiates the email notification. This enables the application or policy to provide the correct token information to the email template.

Tokens Defined in Applications

The Workflow engine and Jobs engine provide the provisioning workflow and jobs functionality. To add tokens to the predefined email templates used with these applications, define the tokens in the applications. This is true of any application you create to use with OpenText Identity Manager.

Tokens Defined in Policies

You mostly implement driver policies with rules that trigger email notifications, rather than developing or altering applications to send emails.

>For example, when using the Active Directory driver to create Microsoft Exchange mailboxes, you might include an action in the Active Directory driver policy to send an email notification to the user after their mailbox creation.

When you create policies that initiate email notifications, the tokens used in the notification templates must be defined in the policy rules.

For example, the tokens used with the predefined password synchronization email templates are defined in the password synchronization policies used by the drivers. To add tokens to the password synchronization templates requires that the new tokens be defined in the policies.

You can use the password synchronization policies as an example for defining the tokens you want to use in an email template. See [Configuring email Notification](#) in the [Password Management Guide](#).



© Copyright 2026 Open Text

For more info, visit <https://docs.microfocus.com>
