

OpenText™ Identity Manager

Certificate Management Guide

Version : 25.4

PDF Generated on : April 21, 2026

Table of Contents

[1. Certificate Management Guide](#)

1

1. Certificate Management Guide

This document provides information on renewing and importing updated certificates into OpenText Identity Manager.

All the certificates have a default lifetime period, after which certificates expire. When the certificate expires, the applications' becomes inaccessible. You can either extend the existing certificate's validity or renew the certificate to restore access to application.

Renewing Expired Certificates

The following sections describe how to renew an expired certificate.

- [Renewing Expired Certificates on Distributed Servers](#)
- [Renewing Expired Certificates on a Single Server](#)

Renewing Expired Certificates on Distributed Servers

When the OpenText Identity Manager components are installed on different servers, follow the steps below to renew expired certificates:

- [Renewing Certificates for Identity Application](#)
- [Renewing Certificates for OSP Keystore](#)

Renewing Certificates for Identity Application

- [idm Keystore](#)
- [Tomcat Keystore](#)

idm Keystore

To renew the expired certificate entry for Identity Applications in the OpenText Identity Manager keystore (`idm.jks`), perform the following steps:

1. On the server where Identity Applications is installed, navigate to the `/opt/netiq/idm/apps/tomcat/conf/` directory.
2. Take a backup of the `idm.jks` file.
3. Delete the expired SSL Certificate DNS from OpenText Identity Console.
4. Log in to the server where Identity Vault is installed and run the following command:

```
ndsconfig add -m SAS
```



Note

This command creates new SSL Certificate DNS. It will also create a certificate entry in the `cacerts` of Identity Manager Engine.

5. Restart OpenText eDirectory.

6. On the server where Identity Applications is installed, perform the following steps to update the trustedCertEntry (server certificate) entry in the `idm.jks` keystore.

1. Navigate to the `/opt/netiq/idm/apps/configupdate` directory.
2. Launch the configuration update utility by running the following command and click OK.

```
./configupdate.sh
```

This updates the `idm.jks` with the new SSL Certificate DNS.

7. Restart the Tomcat service.

8. On the server where SSPR is installed, perform the following steps:

1. Navigate to the `/opt/netiq/idm/apps/sspr/sspr_data/` directory.
2. Set the **configsEditable** value to true in `SSPRConfiguration.xml` file.
3. Save the file.

9. To import the Identity Vault root certificate into SSPR, perform the following steps:

1. Log in to the SSPR portal in private mode.

```
https://<server-dns>:<port>/sspr/private/login?sso=false
```

2. Select the **Configuration Editor**.
3. Specify the configuration password and click **Sign In**.
4. Navigate to **LDAP > LDAP Directories > Default > Connection**.
5. Clear the **LDAP Certificates** and click **Import From Server**, and then click **Save**.

10. Log in to the Identity Manager Dashboard.

Tomcat Keystore

To renew the expired certificates in Identity Applications Tomcat keystore (tomcat.ks), perform the following steps:

1. Stop the Tomcat service.
2. Navigate to the /opt/netiq/idm/apps/tomcat/conf/ directory.
3. Take a backup of the tomcat.ks file.
4. Delete the existing tomcat.ks file.
5. Create a new tomcat.ks (Identity Application Tomcat keystore) file.

```
keytool -genkey -alias <alias_name> -storetype PKCS12 -
keyalg RSA -keystore tomcat.ks -validity <no_of_days> -
keysize <key_size> -dname "CN=<fqdn>" -keypass <password> -
storepass <password>
```

For example,

```
keytool -genkey -alias userapp -storetype PKCS12 -keyalg RSA
-keystore tomcat.ks -validity 2555 -keysize 1024 -dname
"CN=rhel8-3388.novell.com" -keypass novell -storepass novell
```

6. Ensure that the trustedcert (server certificate) entry is present in the Identity Applications Tomcat keystore.

```
keytool -import -trustcacerts -alias
<alias_of_trustedcert_root> -keystore tomcat.ks -file <root-
certificate-file> -storepass <password> -noprompt
```

For example,

```
keytool -import -trustcacerts -alias root -keystore
/opt/netiq/idm/apps/tomcat/conf/tomcat.ks -file
/opt/certs/cert.der -storepass novell -noprompt
```

7. Import the new user certificate to the Identity Applications Tomcat keystore.
8. Start the Tomcat service.



Note

You must have a certificate with CN as Identity Applications in the keystore (`idm.jks`) of the Identity Applications server. As part of enhanced Java security, now Identity Applications requires trusted certificate to communicate with OSP.

```
/opt/netiq/common/jre/bin/keytool -importkeystore -srckeystore
/opt/netiq/idm/apps/tomcat/conf/tomcat.ks -destkeystore
/opt/netiq/idm/apps/tomcat/conf/idm.jks
```

Renewing Certificates for OSP Keystore

To renew the certificates in the OSP keystore (`osp.jks`), perform the following steps:

1. Stop the Tomcat service.
2. Navigate to the `/opt/netiq/idm/apps/osp/` directory.
3. Take a backup of the `osp.jks` file.
4. Delete the existing `osp` alias in `osp.jks`.

```
keytool -delete -noprompt -alias <alias_name> -keystore
<osp.jks> -storepass <password>
```

For example,

```
keytool -delete -noprompt -alias osp -keystore
/opt/netiq/idm/apps/osp/osp.jks -storepass novell
```

5. Run the below command to extend the validity of `osp.jks`

```
keytool -genkey -keyalg RSA -keysize <key_size> -keystore
/opt/netiq/idm/apps/osp/osp.jks -storepass <password> -
keypass <password> -alias osp -validity <no_of_days> -dname
"<fqdn>"
```

For example,

```
keytool -genkey -keyalg RSA -keysize 2048 -keystore
/opt/netiq/idm/apps/osp/osp.jks -storepass novell -keypass
novell -alias osp -validity 1460 -dname "CN=rhel8-
3387.novell.com"
```

6. Start the Tomcat service.



Note

If you see any errors while accessing the SSPR page, perform the following steps:

1. Log in to the SSPR portal.

`https://<IP address>:<port>/sspr`

2. On the upper-right corner, click on the logged-in user and then click **Configuration Editor**.

3. Specify the configuration password and click **Sign In**.

4. Navigate to **Settings > Single Sign On (SSO) Client > OAuth**.

5. Clear and import the OAuth Server Certificate.

6. Click the Save icon at the upper-right corner to save the certificate.

Renewing Expired Certificates on a Single Server

When the OpenText Identity Manager components are installed on a single server, follow the below steps to renew expired certificates:

- [Renewing Certificates for Identity Applications](#)
- [Renewing Certificates for OSP Keystore](#)

Renewing Certificates for Identity Applications

- [idm Keystore](#)
- [Tomcat Keystore](#)

idm Keystore

To renew the expired certificates for IDM keystore, perform the following steps:

1. Take a backup of `idm.jks` file.
2. Log in to OpenText Identity Console and delete the expired SSL Certificate DNS.
3. Run the below command:

```
ndsconfig add -m SAS
```



Note

This command creates new SSL Certificate DNS. It will also create a certificate entry in the `cacerts` of Identity Manager Engine.

4. Restart the Identity Vault instance.

```
ndsmanage stopall
```

```
ndsmanage startall
```

5. Launch the `configupdate.sh` and click **OK**.
6. Navigate to the `/opt/netiq/idm/apps/sspr/sspr_data/` directory, set the **configsEditable** value to true in `SSPRConfiguration.xml` file, and then save the file.
7. To import the certificates into SSPR, perform the following steps:

1. Log in to the SSPR portal in private mode.

```
https://<server-dns>:<port>/sspr/private/login?sso=false
```

2. Select the **Configuration Editor**.
3. Specify the configuration password and click **Sign In**.
4. Navigate to **LDAP > LDAP Directories > Default > Connection**.
5. Clear the **LDAP Certificates** and click **Import From Server**, and then click **Save**.



Note

SSL Certificate DNS change mandates to update the `tomcat.ks` with new server certificate. If OpenText eDirectory is the certificate issuing authority, you should also change user certificates.

Tomcat Keystore

To renew the expired certificates for Tomcat keystore, perform the following steps:

1. Stop the Tomcat service.
2. Navigate to the `/opt/netiq/idm/apps/tomcat/conf/` directory.
3. Take a backup of the `tomcat.ks` file.
4. Delete the existing `tomcat.ks` file.
5. Create a new `tomcat.ks` (Identity Application Tomcat keystore) file.

```
keytool -genkey -alias <alias_name> -storetype PKCS12 -
keyalg RSA -keystore tomcat.ks -validity <no_of_days> -
keysize <key_size> -dname "CN=<fqdn>" -keypass <password> -
storepass <password>
```

For example,

```
keytool -genkey -alias userapp -storetype PKCS12 -keyalg RSA
-keystore tomcat.ks -validity 2555 -keysize 1024 -dname
"CN=rhel8-3388.novell.com" -keypass novell -storepass novell
```

6. Ensure that the trustedcert (server certificate) entry is present in the Identity Applications Tomcat keystore.

```
keytool -import -trustcacerts -alias
<alias_of_trustedcert_root> -keystore tomcat.ks -file <root-
certificate-file> -storepass <password> -noprompt
```

For example,

```
keytool -import -trustcacerts -alias root -keystore
/opt/netiq/idm/apps/tomcat/conf/tomcat.ks -file
/opt/certs/cert.der -storepass novell -noprompt
```

7. Import the new user certificate to the Identity Applications Tomcat keystore.
8. Restart the Tomcat service.

9. Use the command to import the new generated keystore(s) from tomcat.ks to idm.jks

```
/opt/netiq/common/jre/bin/keytool -importkeystore -
srckeystore /opt/netiq/idm/apps/tomcat/conf/tomcat.ks -
destkeystore /opt/netiq/idm/apps/tomcat/conf/idm.jks
```

10. To import the OAuth certificate into SSPR, perform the following steps.
 1. Log in to SSPR portal.
 2. Select the **Configuration Editor**.
 3. Navigate to **Settings > Single Sign On (SSO) Client > OAuth**.
 4. Clear the OAuth Server Certificate and Import from the Server, and then click **Save**.
11. Restart the Tomcat service.

Renewing Certificates for OSP Keystore

To renew the expired certificate for OSP keystore, perform the following steps:

This sections explains the steps to renew the OSP keystore (osp.jks). For more information, see [Renewing Certificates for OSP Keystore](#).



© Copyright 2026 Open Text

For more info, visit <https://docs.microfocus.com>
