Machine Problem 2 - Virtual Memory, Swapping and Page Replacement

CSIE3310 - Operating Systems National Taiwan University

Total Points:	100
Release Date:	March 19
Due Date:	April 1, 23:59:00

TA e-mail: ntuos@googlegroups.com

TA hours: Mon. 11:00-12:00, Wed. 14:00-15:00, CSIE Building B04 (Please knock the door)

Contents

1	Summary		
2	Launching Docker		
3	Launching xv6 with the Docker Image for MP2		
4	Scoring and Submission 4.1 Run the Preliminary Judge 4.2 Submission	3 3 3	
5	Assignment 5.1 Print a Page Table (Public 6%+Private 4%) 5.2 Swapping (Public 24%+Private 16%) 5.2.1 Handle Page Faults 5.2.2 Swapping / Pinning Pages 5.2.3 madvise MADV_NORMAL Option 5.2.4 Swap In Pages 5.2.5 Pin/Unpin Pages 5.3 Page Replacement (Public 30%+Private 20%)	44 45 5 5 7 7 7 7 7 7 7 7 7 7 7 7 7 7 7	
6	Appendix 6.1 Macros and Builtin Types 6.1.1 Headers 6.1.2 Naming Conventions 6.1.3 Page Alignment 6.1.4 Page table entry (PTE) Constants and Macros 6.2 Functions Used in The Homework 6.3 Functions to be Modified in the Homework 6.4 Generate your own test cases 6.5 Notes on Device I/O 6.6 Troubleshooting	88 88 99 100 111 122 13	
7	References	13	

1 Summary

The virtual memory system provides each process with an isolated and abstracted memory space. Through per-process page tables, only a portion of virtual memory pages are actively mapped to physical memory. This sophisticated memory management enables the operating system to manage processes that have large virtual memory spaces while utilizing a relatively small amount of physical memory.

To further enhance memory efficiency, modern operating systems implement page replacement algorithms. Page replacement is a technique used to select which memory pages to swap out to disk when physical memory is full. This homework introduces two classic page replacement strategies: First In, First Out (FIFO) and Least Recently Used (LRU). FIFO evicts the oldest page in memory, while LRU removes the page that has been unused for the longest time. These algorithms aim to optimize the use of available memory and the performance of the system by keeping the most relevant pages in physical memory and swapping out the less frequently used ones.

2 Launching Docker

It follows the same procedure in MP0. If you're using Windows, it strongly suggested to install WSL2 and run Docker in WSL2.

3 Launching xv6 with the Docker Image for MP2

1. Download the MP2.zip from NTUCOOL, unzip it, and enter it.

```
$ unzip MP2.zip
$ cd mp2
```

2. Pull Docker image from Docker Hub

```
$ docker pull ntuos/mp2
```

3. In the mp2 directory, run docker run to enter to the shell in the container.

```
$ docker run -it -v $PWD:/root ntuos/mp2
```

4. Enter home directory

```
$ cd
```

5. Run Individual Tests

You can refer the correct output in mp2_output directory for each public test cases.

(a) For mp2_1,...,3, run make qemu before mp2_N command, where $N=1,\ldots,3$

```
$ make clean
$ make qemu
...
$ mp2_1
```

(b) For mp2_ 4, run make fifo before mp2_4 command

```
$ make clean
$ make fifo
...
$ mp2_4
```

(c) For mp2_5, run make lru before mp2_5 command

```
$ make clean
$ make lru
...
$ mp2_5
```

In the case that the test program hangs, start a new shell and run:

```
killall qemu-system-riscv64
```

4 Scoring and Submission

The judge program for public tests is shipped with MP2.zip. The private test is disclosed after the deadline.

- Public program tests (60%)
- Private program tests (40%)

No partial points will be given!!

4.1 Run the Preliminary Judge

You can get 60 points (100 points in total) if you pass all public test cases. You can judge the code by running the following command in the docker container (not in xv6; this should run in the same place as make qemu).

```
$ make grade
```

If you successfully pass all the public test cases, the output should be similar to the one below.

```
== Test mp2_1 (6%) ==
mp2_1: OK (3.4s)
== Test mp2_2 (12%) ==
mp2_2: OK (1.1s)
== Test mp2_3 (12%) ==
mp2_3: OK (1.0s)
== Test mp2_4 (12%) ==
mp2_4: OK (4.6s)
== Test mp2_5: OK (4.5s)
Score: 60/60
```

4.2 Submission

Run this command to pack your code into a zip named in your lowercase student ID, for example, d10922013.zip. Submit this file to *Machine Problem 2* section on NTUCOOL.

```
make STUDENT_ID=d10922013 zip # set your ID here
```

4.3 Grading Policy

- It is allowed to re-submit your code and report. The renaming due to resubmission will not result in point deduction. Only the latest submission is judged, even it's over the deadline.
- Compilation error leads to 0 points.
- Erroneous folder structure incurs 10 point penalty. Using uppercase in <student_id> is also treated as wrong folder structure.
- Late submission will incur immediate 20 points penalty. The score is deduced by 20 points per 24 hours later on. For example, 25-hour late submission leads to 40 points deduction.

5 Assignment

It is recommended to read materials in Section 6 before writing your code. It will save your time. Also, do your homework early. :)

5.1 Print a Page Table (Public 6%+Private 4%)

Most of the operating systems implement a separate page table for each process. If a process occupies its page table with the size analogous to the size of its virtual memory, the amount of memory occupied by the page tables can be huge, and is unacceptable as main memory is a scarce resource.

Hence, modern operating systems incorporate with *multilevel* page tables. It has a higher level page table, where each entry points to a lower level page table. Page tables of each level are structured similarly except that the lowest page tables point to actual pages. Lower level page tables are allocated only when needed. The RISC-V xv6 page table has 3 levels.

In this section, we are going to implement the vmprint() function in kernel/vm.c to dump the page table tree. It takes a page table of type pagetable_t and print that page table in the format below.

```
$ mp2_1
page table 0x000000087f49000
+-- 0: pte=0x0000000087f49000 va=0x000000000000000000 pa=0x0000000087f45000 V
| +-- 0: pte=0x0000000087f45000 va=0x000000000000000000 pa=0x0000000087f44000 V
| +-- 0: pte=0x0000000087f44000 va=0x00000000000000 pa=0x0000000087f46000 V R W X U
| +-- 1: pte=0x0000000087f44008 va=0x0000000000000000000087f43000 V R W X
| +-- 2: pte=0x0000000087f44010 va=0x000000000000000000087f42000 V R W X U
+-- 255: pte=0x0000000087f497f8 va=0x0000003fc000000 pa=0x000000087f48000 V
+-- 511: pte=0x0000000087f48ff8 va=0x0000003fffe00000 pa=0x0000000087f47000 V
+-- 510: pte=0x0000000087f47ff0 va=0x0000003fffff0000 pa=0x0000000087f65000 V R W D
+-- 511: pte=0x0000000087f47ff8 va=0x0000003ffffff000 pa=0x0000000087f65000 V R X
```

In the example above, the top-level page table has mappings in entries at indexes 0 and 255. The next level down for entry 0 has only index 0 mapped, and the bottom-level for that index 0 has entries 0, 1, and 2 mapped.

The printed tree structure satisfies the rules.

- 1. The first line shows the address passed to vmprint.
- 2. Print the page table entries (PTEs) since the second line. One line per entry.
- 3. The entries are indented to show the tree structure of the page table, four spaces per level. Use the +-- prefix to indicate an entry.

Each page table entry (PTE) contains the following items.

- 1. It has an index in its page-table page for that entry. e.g. +-- 255: is the 255th entry in that tree level.
- 2. pte= writes the physical address of the entry.
- 3. va= writes the virtual memory address recorded on the entry.
- 4. pa= writes the physical memory address recorded on the entry.
- 5. It has flag bits V, R, W, X, U, D for the entry. Note that PTEs without PTE_V bit are not printed.
- 6. Each entry ends with a line break ('\n') and has no trailing spaces.

Hints:

- 1. Your code might emit different physical addresses than those shown above. The number of entries and the virtual addresses should be the same.
- 2. You may check the source files.
 - kernel/memlayout.h defines the memory layout.

- kernel/vm.c contains most virtual memory related code.
- 3. Use the macros at the end of the file kernel/riscv.h.
- 4. Use %p in printf calls to print out full 64-bit hex addresses.

5.2 Swapping (Public 24%+Private 16%)

Page replacement with swapping is a technique to manage memory pages in a secondary storage, typically a hard disk. This technique involves replacing pages in main memory with pages from secondary storage when the available physical memory is insufficient to accommodate all the required pages. This approach aims to optimize memory utilization and performance. In this section, we are going to implement the new madvise() syscall. It allows the users to hint that a sequence of pages, namely a memory region, should be swapped out to the disk or be swapped in to the physical memory.

5.2.1 Handle Page Faults

The page fault handler must be modified to find the virtual address triggering page fault in the process, and allocate a physical memory page for that offending virtual address. The page fault will be captured by usertrap() in kernel/trap.c. Change the function to handle page fault events. The modification goes as follows.

- Use r_scause() == 13 || r_scause() == 15 condition to catch page fault events in usertrap() in kernel/trap.c. Create a page fault handling function handle_page_fault() in /kernel/paging.c and call that function whenever a page fault occurs. Check Figure 1 for the exception codes of scause.
- Always mark PTE_U, PTE_R, PTE_W, PTE_X flags on newly allocated pages.
- In handle_page_fault(), call uint64 va = r_stval() to find the offending virtual address, and round the address to page boundary using PGROUNDDOWN().
- Make use of the functions below to allocate a physical page for the offending virtual address.
 - The walk() in kernel/vm.c traverses entries in a page table.
 - The mappages() in /kernel/vm.c is used to assign a physical to virual address mapping in the page table.
 - The memset() in /kernel/string.c zeros out a fraction of memory.

5.2.2 Swapping / Pinning Pages

The user passes a virtual memory address range to madvise() syscall to hint how a memory region is expected to use to the kernel. The memory region is the minimum set of pages covering the address range from user. The kernel can choose an appropriate paging policy and caching techniques according to the user's advice. The function signature is defined as follows.

int madvise(void *addr, size t length, int advice);

The behavior of madvise() obeys the following rules.

- The addr and length specifies a range of memory address [addr, addr + length). The byte at addr + length is not included. The corresponding $memory \ region$ is the minimum set of pages covering the address range.
- If a portion of the memory region exceeds the process memory size (myproc()->sz), it returns -1. Otherwise, it performs appropriate actions and returns 0.
- The advice option describes how the region is expected to be used, which can be one of the three values.
 - MADV_NORMAL : No special treatment. Nothing to be done.
 - MADV_WILLNEED: Expect an access in the near future. It swaps in the pages on the disk to the memory, and allocates new physical memory pages for unallocated pages.

Figure 1: Supervisor cause register (scause) values after trap. Andrew Waterman, Krste Asanovic, The RISC-V Instruction Set Manual

Interrupt	Exception Code	Description
1	0	User software interrupt
1	1	Supervisor software interrupt
1	2–3	Reserved
1	4	User timer interrupt
1	5	Supervisor timer interrupt
1	6–7	Reserved
1	8	User external interrupt
1	9	Supervisor external interrupt
1	≥10	Reserved
0	0	Instruction address misaligned
0	1	Instruction access fault
0	2	Illegal instruction
0	3	Breakpoint
0	4	Reserved
0	5	Load access fault
0	6	AMO address misaligned
0	7	Store/AMO access fault
0	8	Environment call
0	9–11	Reserved
0	12	Instruction page fault
0	13	Load page fault
0	14	Reserved
0	15	Store/AMO page fault
0	≥16	Reserved

- MADV_DONTNEED: Do not expect any access in the near future. Any pages within the region that are still in the physical memory will be swapped out to the disk. This feature is provided by TAs, thus you can reference the implementation to implement the feature of MADV_WILLNEED, MADV_PIN, and MADV_UNPIN. Note that you need to extend the vmprint() function to show the PTE_S bit if a page is swapped. Show block numbers for swapped page entries.
Sampled output:

- MADV_PIN: Make pages within the region that cannot be page out. Note that you need to extend the vmprint() function to show the PTE_P bit if a page is pinned. Sampled output:

MADV_UNPIN: Make pages within the region that can be page out if necessary.

It leverages balloc_page() and write_page_to_disk() to allocate a page on the storage device. More utility functions can be found at Section 6.

5.2.3 madvise MADV NORMAL Option

Handle the MADV_NORMAL option in madvise() syscall. It does nothing and just return. This option is combined into the test case of swapping in, swapping out, please read 5.2.4.

5.2.4 Swap In Pages

Handle the MADV_WILLNEED option in madvise() syscall. It ensures the pages within the memory region to be physically allocated. The PTE_V bit is set on those affected page table entries.

The testing program may goes through the following steps:

- 1. Call vmprint() to check current page table.
- 2. Increase the process memory by malloc(x * PGSIZE) where x >= 16.
- 3. Call madvise() with MADV_NORMAL option to the correspond pages, and call vmprint() to check current page table.
- 4. Call madvise() with MADV_DONTNEED option to swap the correspond pages to the disk, and call vmprint() to check current page table.
- 5. Call madvise() with MADV_WILLNEED option to place the correspond the physical memory from the disk back to physical memory and allocate pages for those not allocated yet. Then, Call vmprint() to check the page table.

5.2.5 Pin/Unpin Pages

The concept of "pinning" a page table entry (PTE) is related to memory management strategies, particularly in scenarios where certain pages of memory need to be prevented from being moved or swapped out by the operating system. Handle the MADV_PIN option in madvise() syscall. It ensures the pages within the memory region to be pined or unpined. The PTE_P bit is set on those affected page table entries.

The testing program may goes through the following steps:

- 1. Increase the process memory by malloc(x * PGSIZE) where x>=16.
- 2. Call vmprint() to check current page table.
- 3. Call madvise() with MADV_PIN option to pin the correspond pages, and call vmprint() to check current page table.
- 4. Call madvise() with MADV_UNPIN option to unpin the correspond pages. Then, Call vmprint() to check the page table.

5.3 Page Replacement (Public 30%+Private 20%)

Implement your algorithms in fifo.c and lru.c file. We have provided a template of data structure which to implement FIFO(fifo.c) and LRU(lru.c) algorithms. You can use the template (encouraged) or change it if you do not want to use it. Note that the fields inside the structure must be primitive type and array type.

• This preprocessor directives are used to differentiate FIFO or LRU page replacement algorithm. You will see multiple preprocessor directives like this and you should implement your page replacement algorithm in corresponding block.

```
#ifdef (PG_REPLACEMENT_USE_LRU)
     \\ LRU behavior
#elif defined(PG_REPLACEMENT_USE_FIFO)
     \\ FIFO behavior
#endif
```

- How to select page replacement algorithm when booting xv6?
 - FIFO

\$make fifo

```
$make lru
```

• You should implement pgprint() in kernel/vm.c to show final page replacement buffer for grading public test cases mp2_{4, 5}. Note that the next most likely victim should output first. Sampled output:

```
Page replacement buffers
-----Start-----
pte: 0x0000000087f44040
pte: 0x0000000087f44048
pte: 0x0000000087f44050
pte: 0x0000000087f44058
pte: 0x0000000087f44060
pte: 0x0000000087f44068
pte: 0x0000000087f44078
pte: 0x0000000087f44080
------End-------
```

Hints:

- Pinned pages should not be replaced
- Swapped out pages should be removed from page replacement buffer
- The page replacement buffer size will be 8 for grading
- You have to ignore the first three PTEs
- The page replacement occurs in your page replacement buffer, do not try to modify the process's pagetable_t directly

6 Appendix

6.1 Macros and Builtin Types

6.1.1 Headers

To use the macros and builtin types on XV6 kernel code, the following headers must be included.

```
#include "types.h"
#include "param.h"
#include "riscv.h"
```

6.1.2 Naming Conventions

- PA Physical address
- VA Virtual address
- PG Page
- PTE Page table entry
- BLOCKNO Block number on a device or a disk
- PGTBL Page table

6.1.3 Page Alignment

The following macros convert a memory address to a page aligned value.

• PGSIZE

The page size, which is 4096.

• PGSHIFT

The number of offset bits in memory address, which is 12.

• PGROUNDUP(sz)

Round the memory address to multiple of 4096 greater than or equal to sz.

• PGROUNDDOWN(sz)

Round the memory address to multiple of 4096 less than or equal to sz.

6.1.4 Page table entry (PTE) Constants and Macros

A page table entry is a 64-bit integer, consisting of 10 low flag bits and remaining high address bits. The flag bits includes PTE_V, PTE_R, PTE_W, PTE_X, PTE_U, PTE_S, PTE_D, PTE_P.

• PTE_V

If set, the high bits represent a valid memory address.

• PTE_R

If set, the page at the address can be read.

PTE_W

If set, the page at the address can be written.

• PTE_X

If set, the code on the page at the address can be executed.

• PTE_U

If set, the page at the address is visible to userspace.

• PTE S

If set, the high bits represent the block number of a swapped page.

• PTE_D

If set, the page at the address is written.

PTE_P

If set, the page at the address is pined.

They can be used to check, set or unset flag bits on a page table entry.

```
pte_t *pte = walk(pagetable, va, 0);

/* Check if PTE_V bit is set */
if (*pte & PTE_V) { /* omit */ }

/* Set the PTE_V bit */
*pte |= PTE_V;

/* Unset the PTE_V bit */
*pte &= ~PTE_V;
```

The high bits must be a valid address if PTE_V bit is set. The following macros are used to convert a physical address to the high bits of PTE, and vice versa.

```
pte_t *pte = walk(pagetable, va, 0);

if (*pte & PTE_V) {
    /* Get the PA from a PTE */
    uint64 pa = PTE2PA(*pte);

    /* Create a PTE from a PA and flag bits */
    *pte = PA2PTE(pa) | PTE_FLAGS(*pte);
}
```

If a PTE points to a swapped page, the PTE_S bit is set but PTE_V should be eliminated. The high bits represents the block number on ROOTDEV device.

```
pte_t *pte = walk(pagetable, va, 0);

if (*pte & PTE_S) {
    /* Get the BLOCKNO from a PTE */
    uint64 blockno = PTE2BLOCKNO(*pte);

char *pa = kalloc();    /* Assume pa != 0 */
    read_page_from_disk(ROOTDEV, pa, blockno);

/* Create a PTE from a BLOCKNO and flag bits */
    *pte = BLOCKNO2PTE(pa) | PTE_FLAGS(*pte);
}
```

6.2 Functions Used in The Homework

The following functions can de/allocate pages on a storage device.

- uint balloc_page(uint dev)
 - Allocate a 4096-byte page on device dev.
 - Return the block number of the page.
- uint bfree_page(uint dev, uint blockno)
 - Deallocate the 4096-byte page at block number blockno on device dev.
 - The blockno must be returned from balloc_page().

The following functions are used to load/save a memory page from/to a page on a storage device.

- void write_page_to_disk(uint dev, char *page, uint blk)
 - Write 4096 bytes from page to the page at block number blk on device dev.
 - The address page must be 4096-aligned and is returned from kalloc().
 - The blk must be returned from balloc_page()
- void read_page_from_disk(uint dev, char *page, uint blk)
 - Read 4096 bytes from the page at block number blk on device dev to page.
 - The address page must be 4096-aligned and is returned from kalloc().
 - The blk must be returned from balloc_page()

The following functions are related to the page table.

• pte_t *walk(pagetable_t pagetable, uint64 va, int alloc)

- Look up the virtual address va in pagetable.
- Return the pointer to the PTE if the entry exists, otherwise return zero.
- If alloc is nonzero, it allocates page tables for each level for the given virtual address.
- Note that it can return a non-null PTE pointer but without PTE_V bit set on the entry.
- int mappages(pagetable_t pagetable, uint64 va, uint64 size, uint64 pa, int perm)
 - Map a virtual memory range of size bytes starting at virtual address va to the physical address pa on pagetable.
 - Return 0 if successful, otherwise nonzero.
 - The corresponding PTEs for the given virtual memory range must not set PTE_V flag.

6.3 Functions to be Modified in the Homework

The following functions are potential candidates to be modified in this homework. You are free to roll out your own implementation.

- kernel/vm.c - vmprint() - madvise() - pgprint() • kernel/paging.c - handle_pgfault() • kernel/trap.c - usertrap() • kernel/fifo.c - q_init() - q_push()

 - q_pop_idx()
 - q_empty()
 - q_full()
 - q_clear()
 - q_find()
- kernel/lru.c
 - lru_init()
 - lru_push()
 - lru_pop()
 - lru_empty()
 - lru_full()
 - lru_clear()
 - lru_find()

Note that for fifo/lru.[ch] file, if you want to rename the function, you must need to change the header file accordingly. For example, if you change the function in fifo.c, then you also need to change the fifo.h.

6.4 Generate your own test cases

You may want to write own test cases, you may use malloc(), but just ignore free()

- user/umalloc.c
 - malloc(), the vmprint() is your implementation in 5.1.1. Your test case must store in user/directory. Then, open Makefile and search UPROGS variable, add your file to the last entry of this variable. For example, if your file called mytest.c, add U/ mytest to the last entry:

```
UPROGS=\
        $U/_cat\
        $U/_echo\
        $U/_forktest\
        $U/_grep\
        $U/_init\
        $U/_kill\
        U/_ln\
        U/_ls
        $U/_mkdir\
        U/_rm\
        U/_{sh}
        $U/_stressfs\
        $U/_usertests\
        $U/_grind\
        $U/_wc\
        $U/_zombie\
        $U/_mp2_1\
        $U/_mp2_2\
        $U/_mp2_3\
        $U/_mp2_4\
        $U/_mp2_5\
        $U/_mytest
```

Sample test case:

```
#include "kernel/types.h"
#include "kernel/stat.h"
#include "user/user.h"
#include "kernel/vm.h"

#define PG_SIZE 4096
#define NR_PG 18

int main(int argc, char *argv[]) {
   char *ptr = malloc(NR_PG * PG_SIZE);
   vmprint();
   exit(0);
}
```

6.5 Notes on Device I/O

When working calling device I/O functions, such as balloc_page() and bfree_page(), it must be encapsulated with begin_op() and end_op() to work properly.

```
begin_op();
read_page_from_disk(ROOTDEV, pa, blockno);
bfree_page(ROOTDEV, blockno);
end_op();
```

6.6 Troubleshooting

panic: invalid file system when starting xv6 Download the fresh zip source code from NTUCOOL. Copy the fs.img from the zip and overwrite the fs.img in your homework directory. Make sure your write_page_to_disk() writes to a valid blockno, and balloc_page()/bfree_page() are used in the right way.

The page fault is triggered on kerneltrap() It occurs when your kernel code accidentally reads or writes to to an address which page is not in page table(not allocted or swapped out).

remap panic in mappages() mappages() expects the received virtual address does not have PTE_V on the corresponding page table entry. It is usually caused by setting PTE_V on the entry before calling mappages().

If you free swapped pages in uvmunmap(), the process will panic when exits. The fix is not trivial. You can choose to ignore swapped pages in this case.

7 References

[1] POSIX — IEEE Standard Portable Operating System Interface for Computer Environments https://ieeexplore.ieee.org/document/8684566](https://ieeexplore.ieee.org/document/8684566/

[2] Inverted Page Table — Computer Architecture: A Quantitative Approach https://ict.iitk.ac.in/wp-content/uploads/CS422-Computer-Architecture-patterson-5th-edition.pdf

[3] xv6 — A simple, Unix-like teaching operating system by MIT https://pdos.csail.mit.edu/6.828/2020/xv6/book-riscv-rev1.pdf/

[4] Linux Kernel - The Process Address Space — sathya's Blog https://sites.google.com/site/knsathyawiki/example-page/chapter-15-the-process-address-space/

[5] Advanced Programming in the UNIX® Environment https://www.oreilly.com/library/view/advanced-programming-in/9780321638014/

[6] RISC-V privileged manual (table 4.2) https://riscv.org/wp-content/uploads/2017/05/riscv-privileged-v1.10.pdf