

Purpose of this lab

- Set up a client to pull configuration from a *Config Server* with a git backend.
- Use @ConfigurationProperties to create type-safe configuration.
- Use @RefreshScope to live-reload configuration.
- Notify horizontally-scaled applications to refresh configuration with *Cloud Bus*.

Set up the app-config repository

1. Create a local directory and initialize a git repo.

```
mkdir ~/workspace/app-config
cd ~/workspace/app-config
git init
```

2. Create a repository named app-config in your GitHub account. Copy the ssh URL and add a remote to your local repo.

```
git remote add origin https://github.com/<YOUR-USERNAME>/app-confi
g.git
```

Set up your Config Server

1. Clone the spring cloud services repo and change to the Config Server folder.

```
git clone https://github.com/platform-acceleration-lab/apps-spring
-cloud-services-code.git
cd apps-spring-cloud-services-code/config-server
```

2. Note that in the pom.xml, the spring-cloud-config-server has been added to the classpath. This enables this application to embed a config-server.

```
<dependency>
    <groupId>org.springframework.cloud</groupId>
    <artifactId>spring-cloud-config-server</artifactId>
</dependency>
```

- 3. Review the following file. Pay special attention to the <code>@EnableConfigServer</code> annotation.
 - ➡ Hide ConfigServerApplication.java config-server/src/main/java/io/pivotal/ConfigServerApplication.java (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/config-

server/src/main/java/io/pivotal/ConfigServerApplication.java)

view on **GitHub ?** (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/config-server/src/main/java/io/pivotal/ConfigServerApplication.java)

```
package io.pivotal;
import org.springframework.boot.SpringApplication;
import org.springframework.boot.autoconfigure.SpringBootApplicatio
n;
import org.springframework.cloud.config.server.EnableConfigServer;

@SpringBootApplication
@EnableConfigServer
public class ConfigServerApplication {
    public static void main(String[] args) {
        SpringApplication.run(ConfigServerApplication.class, args)
;
    }
}
```

4. Configure the config-server application to get configuration from your apps-config repository. Edit your application.yml to point to your repository.

Hide application.yml

config-server/src/main/resources/application.yml (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/config-server/src/main/resources/application.yml)

view on **GitHub ()** (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/config-server/src/main/resources/application.yml)

```
server:
  port: 8888

spring:
  cloud:
    config:
     server:
       git:
       uri: https://github.com/<github-username>/app-config.git
```

5. Start the config-server and leave it running.

```
./mvnw clean spring-boot:run
```

6. To add some configuration, create a file called hello-world.yml in your app-config repo. Add the content below to the file and push the changes back to GitHub. Be sure to substitute your name for <Your name>.

```
name: <Your Name>
```

7. Confirm the config-server is up and configured with a backing git repository by navigating to http://localhost:8888/hello-world/default (http://localhost:8888/hello-world/default).

The config-server exposes several endpoints (http://projects.spring.io/spring-cloud/docs/1.0.3/spring-cloud.html#_quick_start) to fetch configuration.

In this case, we are manually calling one of those endpoints (/{application}/{profile} [/{label}]) to fetch configuration. We substituted our example client application helloworld as the {application} and the default profile as the {profile}. We did not specify the label to use so master is assumed.

In the returned document, we see the configuration file hello-world.yml listed as a propertySource with the associated key/value pair.

Set up greeting-config

1. In a new terminal window, go to the Greeting Config app

```
cd ~/workspace/apps-spring-cloud-services-code/greeting-config
```

This application will consume configuration from the config-server.

Review the pom.xml in the greeting-config app. Note the addition of spring-cloud-services-starter-config-client to the classpath.

```
<dependency>
     <groupId>io.pivotal.spring.cloud</groupId>
        <artifactId>spring-cloud-services-starter-config-client</artifactId>
    </dependency>
```

- 2. Review the following file/
 - ➡ Hide bootstrap.yml

greeting-config/src/main/resources/bootstrap.yml (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/src/main/resources/bootstrap.yml)

view on **GitHub** (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/src/main/resources/bootstrap.yml)

```
spring:
   application:
    name: greeting-config
```

The application name is defined by spring application name. This name will be used to locate config files for the greeting-config application.

Absent from the bootstrap.yml is the spring.cloud.config.uri, which defines how greeting-config reaches the config-server. Since there is no spring.cloud.config.uri defined in this file, the default value of http://localhost:8888 is used. Notice that this is the same host and port of the config-server application.

3. Start the greeting-config application.

```
./mvnw clean spring-boot:run
```

4. Confirm the greeting-config app is up by browsing to http://localhost:8080 (http://localhost:8080). You will be prompted to authenticate because spring-cloud-services-starter-config-client has a dependency on Spring Security (http://projects.spring.io/spring-security/).

By default, this causes all endpoints to be protected by HTTP Basic Authentication.

5. For these labs we do not need Spring Security's default behavior of securing every endpoint, so we will turn it off. Add a <code>greeting-config.yml</code> to your <code>app-config</code> repo with the following content:

```
security:
  basic:
    enabled: false

management:
  security:
  enabled: false
```

Push the changes to GitHub and restart the greeting config application.

6. Navigate to localhost:8080 (http://localhost:8080).

At this point, you connected the <code>greeting-config</code> application with the <code>config-server</code>. This can be confirmed by reviewing the logs of the <code>greeting-config</code> application.

We will next add additional configuration parameters/values and see the effects in out client application greeting-config.

Changing Logging Levels

Next you will change the logging level of the greeting-config application.

- 1. View the getGreeting() method of the GreetingController class.
 - Hide GreetingController.java

greeting-config/src/main/java/io/pivotal/greeting/GreetingController.java (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/src/main/java/io/pivotal/greeting/GreetingController.java)

view on **GitHub** (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/src/main/java/io/pivotal/greeting/GreetingController.java)

```
package io.pivotal.greeting;
import io.pivotal.fortune.FortuneService;
```

```
import org.slf4j.Logger;
import org.slf4j.LoggerFactory;
import org.springframework.beans.factory.annotation.Autowired;
import org.springframework.boot.context.properties.EnableConfigura
tionProperties;
import org.springframework.stereotype.Controller;
import org.springframework.ui.Model;
import org.springframework.web.bind.annotation.RequestMapping;
@Controller
@EnableConfigurationProperties(GreetingProperties.class)
public class GreetingController {
    private Logger logger = LoggerFactory.getLogger(getClass());
    private GreetingProperties greetingProperties;
    private FortuneService fortuneService;
    @Autowired
    public GreetingController(GreetingProperties greetingPropertie)
s, FortuneService fortuneService) {
        this.greetingProperties = greetingProperties;
        this.fortuneService = fortuneService;
    }
    @RequestMapping("/")
    public String getGreeting(Model model) {
        logger.debug("Adding greeting");
        model.addAttribute("msg", "Greetings!!!");
        if (greetingProperties.isDisplayFortune()) {
            logger.debug("Adding fortune");
            model.addAttribute("fortune", fortuneService.getFortun
e());
        }
        //resolves to the greeting.vm velocity template
        return "greeting";
    }
}
```

We want to see these debug messages, but DEBUG logs are not shown by default. Next we will change the log level to DEBUG using configuration.

All log output will be directed to System.out & System.error by default, so logs will be output to the terminal window(s).

2. In your app-config repo, add the following content to the greeting-config.yml file:

```
security:
  basic:
    enabled: false

management:
  security:
    enabled: false

logging:
  level:
    io:
      pivotal: DEBUG

greeting:
  displayFortune: false

quoteServiceURL: http://quote-service-dev.cfapps.io/quote
```

Push the changes back to GitHub.

We have added several configuration parameters that will be used throughout this lab. For this exercise, we have set the log level for classes in the <code>io.pivotal</code> package to <code>DEBUG</code>.

- 3. While watching the <code>greeting-config</code> terminal, refresh the http://localhost:8080 (http://localhost:8080/) url. Notice there are no <code>DEBUG</code> logs yet.
- 4. Does the config-server see the change in your git repo? Check what the config-server is serving by browsing to http://localhost:8888/greeting-config/default (http://localhost:8888/greeting-config/default)

The propertySources value has changed! The config-server has picked up the changes to the git repo. (If you do not see the change, verify that you have pushed your app-config repo to GitHub.)

5. Review the following file:

➡ Hide pom.xml

greeting-config/pom.xml (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/pom.xml)

view on **GitHub** (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/pom.xml)

```
description>
        <parent>
                <groupId>org.springframework.boot
                <artifactId>spring-boot-starter-parent</artifactId</pre>
>
                <version>1.4.2.RELEASE
                <relativePath /> <!-- lookup parent from repositor</pre>
        </parent>
        properties>
                project.build.sourceEncoding>UTF-8/project.build
.sourceEncoding>
                oproject.reporting.outputEncoding>UTF-8/project.r
eporting.outputEncoding>
                <java.version>1.8</java.version>
        </properties>
        <dependencies>
                <dependency>
                        <groupId>io.pivotal.spring.cloud
                        <artifactId>spring-cloud-services-starter-
config-client</artifactId>
                </dependency>
                <dependency>
                        <groupId>org.springframework.cloud
d>
                        <artifactId>spring-cloud-starter-config</a</pre>
rtifactId>
                </dependency>
                <dependency>
                        <groupId>org.springframework.boot/groupId
>
                        <artifactId>spring-boot-starter-actuator/
artifactId>
                </dependency>
                <dependency>
                        <groupId>org.springframework.boot/groupId
```

```
>
                        <artifactId>spring-boot-starter-web</artif</pre>
actId>
                </dependency>
                <dependency>
                        <groupId>org.springframework.boot/groupId
>
                        <artifactId>spring-boot-starter-velocity/
artifactId>
                </dependency>
                <dependency>
                        <groupId>org.springframework.boot/groupId
>
                        <artifactId>spring-boot-starter-test</arti</pre>
factId>
                        <scope>test</scope>
                </dependency>
                <dependency>
                        <groupId>org.springframework.boot/groupId
                        <artifactId>spring-boot-configuration-proc
essor</artifactId>
                        <optional>true</optional>
                </dependency>
        </dependencies>
        <dependencyManagement>
                <dependencies>
                        <dependency>
                                 <groupId>org.springframework.cloud
</groupId>
                                <artifactId>spring-cloud-dependenc
ies</artifactId>
                                 <version>Camden.SR3</version>
                                 <type>pom</type>
                                 <scope>import</scope>
                        </dependency>
                        <dependency>
                                 <groupId>io.pivotal.spring.cloud
groupId>
                                 <artifactId>spring-cloud-services-
dependencies</artifactId>
                                 <version>1.3.1.RELEASE
```

<type>pom</type>

Note the inclusion of the actuator dependency. The actuator adds several additional endpoints to the application for operational visibility and tasks that need to be carried out. In this case, we have added the actuator so that we can use the /refresh endpoint, which allows us to refresh the application config on demand.

6. For the <code>greeting-config</code> application to pick up new configuration changes, it must be told to do so. Notify <code>greeting-config</code> app to pick up the new config by sending a POST request to the <code>greeting-config</code> /refresh endpoint. Run the following command:

```
curl -X POST http://localhost:8080/refresh
```

7. Refresh the greeting-config localhost:8080 (http://localhost:8080/) url while viewing the greeting-config terminal. You should now see the debug log message Adding greeting.

Turning on a Feature with @ConfigurationProperties

Use of @ConfigurationProperties is a common way to provide type-safe configuration in Spring applications. Beans annotated with @ConfigurationProperties are automatically reloaded when the application config is refreshed.

1. Review the following file:

Hide GreetingProperties.java

greeting-config/src/main/java/io/pivotal/greeting/GreetingProperties.java (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/src/main/java/io/pivotal/greeting/GreetingProperties.java)

view on **GitHub** (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/src/main/java/io/pivotal/greeting/GreetingProperties.java)

```
package io.pivotal.greeting;
import org.springframework.boot.context.properties.ConfigurationPr
operties;

@ConfigurationProperties(prefix = "greeting")
public class GreetingProperties {
    private boolean displayFortune;
    public boolean isDisplayFortune() {
        return displayFortune;
    }

    public void setDisplayFortune(boolean displayFortune) {
        this.displayFortune = displayFortune;
    }
}
```

Use of the <code>@ConfigurationProperties</code> annotation allows for reading of configuration values. Configuration keys are a combination of the <code>prefix</code> and the field names. In this case, there is one field (<code>displayFortune</code>). Therefore <code>greeting.displayFortune</code> is used to turn the display of fortunes on/off.

- 2. Review the greeting controller.
 - Hide GreetingController.java

greeting-config/src/main/java/io/pivotal/greeting/GreetingController.java (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/src/main/java/io/pivotal/greeting/GreetingController.java)

view on **GitHub** (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/src/main/java/io/pivotal/greeting/GreetingController.java)

```
package io.pivotal.greeting;
import io.pivotal.fortune.FortuneService;
```

```
import org.slf4j.Logger;
import org.slf4j.LoggerFactory;
import org.springframework.beans.factory.annotation.Autowired;
import org.springframework.boot.context.properties.EnableConfigura
tionProperties;
import org.springframework.stereotype.Controller;
import org.springframework.ui.Model;
import org.springframework.web.bind.annotation.RequestMapping;
@Controller
@EnableConfigurationProperties(GreetingProperties.class)
public class GreetingController {
    private Logger logger = LoggerFactory.getLogger(getClass());
    private GreetingProperties greetingProperties;
    private FortuneService fortuneService;
    @Autowired
    public GreetingController(GreetingProperties greetingPropertie
s, FortuneService fortuneService) {
        this.greetingProperties = greetingProperties;
        this.fortuneService = fortuneService;
    }
    @RequestMapping("/")
    public String getGreeting(Model model) {
        logger.debug("Adding greeting");
        model.addAttribute("msg", "Greetings!!!");
        if (greetingProperties.isDisplayFortune()) {
            logger.debug("Adding fortune");
            model.addAttribute("fortune", fortuneService.getFortun
e());
        }
        //resolves to the greeting.vm velocity template
        return "greeting";
    }
}
```

Note how the <code>greetingProperties.isDisplayFortune()</code> is used to turn the display of fortunes on/off. There are times when you want to turn features on/off on demand. In this case, we want the fortune feature "on" with our greeting.

3. In your app-config repo change greeting displayFortune from false to true in the greeting-config.yml.

```
greeting:
displayFortune: true
```

Push the changes to GitHub.

4. Notify the greeting-config app to pick up the new config by POSTing to the /refresh endpoint.

```
curl -X POST http://localhost:8080/refresh
```

5. Refresh the localhost:8080 (http://localhost:8080/) url and see the fortune included.

Reinitializing Beans with @RefreshScope

Next we will use the config-server to obtain a service URI.

- 1. Review the QuoteService.
 - Hide QuoteService.java

greeting-config/src/main/java/io/pivotal/quote/QuoteService.java (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/src/main/java/io/pivotal/quote/QuoteService.java)

view on **GitHub** (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/src/main/java/io/pivotal/quote/QuoteService.java)

```
package io.pivotal.quote;
import org.slf4j.Logger;
import org.slf4j.LoggerFactory;
import org.springframework.beans.factory.annotation.Autowired;
import org.springframework.beans.factory.annotation.Value;
import org.springframework.cloud.context.config.annotation.Refresh
Scope;
import org.springframework.stereotype.Service;
import org.springframework.web.client.RestTemplate;
@Service
@RefreshScope
public class QuoteService {
    private Logger logger = LoggerFactory.getLogger(getClass());
    private String quoteServiceURL;
    private RestTemplate restTemplate;
    @Autowired
    public QuoteService(@Value("${quoteServiceURL:}") String quote
ServiceURL) {
        this.quoteServiceURL = quoteServiceURL;
        this.restTemplate = new RestTemplate();
    }
    public String getQuoteServiceURL() {
        return quoteServiceURL;
    }
    public Quote getQuote() {
        logger.info("quoteServiceURL: {}", quoteServiceURL);
        return restTemplate.getForObject(quoteServiceURL, Quote.cl
ass);
}
```

Note that the QuoteService uses the @RefreshScope annotation. Beans with the @RefreshScope annotation will be recreated when configuration is refreshed. The @Value annotation allows for injecting the config value named quoteServiceURL.

In this case, we are using a third party service to get quotes. We want to keep our environments aligned with the third party, so we are going to override configuration values by profile (next section).

- 2. Review the QuoteController, which uses the QuoteService.
 - Hide QuoteController.java

greeting-config/src/main/java/io/pivotal/quote/QuoteController.java (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/src/main/java/io/pivotal/quote/QuoteController.java)

view on **GitHub** (https://github.com/platform-acceleration-lab/apps-spring-cloud-services-code/blob/master/greeting-config/src/main/java/io/pivotal/quote/QuoteController.java)

```
package io.pivotal.quote;
import org.springframework.beans.factory.annotation.Autowired;
import org.springframework.stereotype.Controller;
import org.springframework.ui.Model;
import org.springframework.web.bind.annotation.RequestMapping;
@Controller
public class QuoteController {
    private QuoteService quoteService;
    @Autowired
    public QuoteController(QuoteService quoteService) {
        this.quoteService = quoteService;
    }
    @RequestMapping("/random-quote")
    public String getView(Model model) {
        model.addAttribute("quote", quoteService.getQuote());
        model.addAttribute("uri", quoteService.getQuoteServiceURL(
));
        return "quote";
    }
}
```

3. Navigate to localhost:8080/random-quote (http://localhost:8080/random-quote). Note the uri that is serving the quotes: http://quote-service-dev.cfapps.io/quote

Override Configuration Values By Profile

- 1. Stop the greeting-config application.
- 2. Set the active profile to qa for the greeting-config application. In the example below, we use an environment variable to set the active profile.
 - MacOS:

```
SPRING_PROFILES_ACTIVE=qa ./mvnw clean spring-boot:run
```

Windows:

```
set SPRING_PROFILES_ACTIVE=qa
./mvnw clean spring-boot:run
```

3. Make sure the profile is set by browsing to the localhost:8080/env (http://localhost:8080/env) endpoint (provided by actuator). Under profiles qa should be listed.

```
← → C | ☐ localhost:8080/env
    ▼ "profiles": [
         "qa"
    "configService:https://github.com/d4v3r/app-config.git/greeting-config.yml": {
         "logging.level.io.pivotal": "DEBUG",
         "greeting.displayFortune": true,
         "quoteServiceURL": "http://quote-service-dev.cfapps.io/quote"
      "servletContextInitParams": {},
      "systemProperties": {
         "java.runtime.name": "Java(TM) SE Runtime Environment",
         "sun.boot.library.path": "/Library/Java/JavaVirtualMachines/jdk1.8.0_45.jdk/Contents/Home/jre/lib",
         "java.vm.version": "25.45-b02",
         "gopherProxySet": "false",
         "maven.multiModuleProjectDirectory": "/Users/droberts/repo/cloud-native-app-labs/greeting-config",
         "java.vm.vendor": "Oracle Corporation",
         "java.vendor.url": "http://java.oracle.com/",
         "guice.disable.misplaced.annotation.check": "true",
         "path.separator": ":",
```

4. In your fork of the <code>app-config</code> repository, create a new file: <code>greeting-config-qa.yml</code>. Fill it in with the following content:

```
quoteServiceURL: http://quote-service-qa.cfapps.io/quote
```

Make sure to commit and push to GitHub.

5. Browse to localhost:8080/random-quote (http://localhost:8080/random-quote). Quotes are still being served from http://quote-service-dev.cfapps.io/quote.

6. Refresh the application configuration values

```
curl -X POST http://localhost:8080/refresh
```

- 7. Refresh the localhost:8080/random-quote (http://localhost:8080/random-quote) url. Quotes are now being served from QA.
- 8. Stop both the config-server and greeting-config applications.

```
Configuration from greeting-config.yml was overridden by a configuration file that was more specific (greeting-config-qa.yml).
```

Deploy the greeting-config Application to PCF

1. Package the greeting-config application. Execute the following from the greeting-config directory:

```
./mvnw clean package
```

2. Deploy the greeting-config application to PCF, without starting the application:

```
cf push greeting-config -p target/greeting-config-0.0.1-SNAPSHOT.j
ar -m 512M --random-route --no-start
```

3. Create a Config Server Service Instance

Using the cf cli, do the following (for help review the docs (http://docs.pivotal.io/spring-cloud-services/config-server/creating-an-instance.html)):

Create a config server:

First, create a cfg-svr-config.json file in the greeting-config directory. The contents of the file look something like this:

```
{ "git": { "uri": "https://github.com/<username>/app-config.git" }
}
```

Then:

Feel free to name your service anything you like (it does not have to be named config-server). The Config Server instance will take a few moments to initialize and then be ready for use.

You can invoke either the cf services or cf service commands to view the status of the service you just created.

In addition, you can visit your Config Server's service dashboard in the Apps Manager to view its configuration and status:

In a browser, navigate to the apps manager and to your space. You should be able to find your config server service and its status there (it may be in a separate tab named services).

4. Bind the config-server service to the greeting-config app. This will enable the greeting-config app to read configuration values from the config-server.

```
cf bind-service greeting-config config-server
```

You can safely ignore the *TIP*: *Use 'cf restage' to ensure your env variable changes take effect* message from the CLI. Our app does not need to be restaged at this time because it is not currently running.

5. If you are using PWS or if your PCF instance is using self-signed SSL certificates, you should set the TRUST_CERTS environment variable to the API endpoint of your Elastic Runtime instance. You can quickly retrieve the API endpoint by running the command cf api.

```
cf set-env greeting-config TRUST_CERTS <your api endpoint>
```

Be sure to specify the api endpoint as a hostname and not a url, i.e. without the leading https:// scheme. You can safely ignore the *TIP*: *Use 'cf restage' to ensure your env variable changes take effect* message from the CLI. Our app does not need to be restaged at this time.

NOTE: All communication between Spring Cloud Services components are made through HTTPS. If you are on an environment that uses self-signed certs, the Java SSL trust store will not have those certificates. By adding the TRUST_CERTS environment variable a trusted domain is added to the Java trust store. For more information see the this portion (https://docs.pivotal.io/spring-cloud-services/config-server/writing-client-applications.html#self-signed-ssl-certificate) of the SCS documentation.

6. Start the greeting-config app.

```
cf start greeting-config
```

- 7. Browse to your greeting-config application. Are your configuration settings that were set when developing locally mirrored on PCF?
 - Is the log level for io.pivotal package set to DEBUG? Yes, this can be confirmed with cf logs command while refreshing the greeting-config / endpoint (http://<your-random-greeting-config-url/).
 - Is greeting-config app displaying the fortune? Yes, this can be confirmed by visiting the greeting-config / endpoint.
 - o Is the <code>greeting-config</code> app serving quotes from <code>http://quote-service-qa.cfapps.io/quote</code>? No, this can be confirmed by visiting the <code>greeting-config</code> <code>/random-quote</code> endpoint. Why not? When developing locally we used an environment variable to set the active profile, we need to do the same on PCF.

```
cf set-env greeting-config SPRING_PROFILES_ACTIVE qa
cf restart greeting-config
```

You can safely ignore the *TIP*: *Use 'cf restage' to ensure your env variable changes take effect* message from the CLI. Our app does not need to be restaged but just re-started.

Then confirm quotes are being served from http://quote-service-qa.cfapps.io/quote

Refreshing Application Configuration at Scale with Cloud Bus

Until now you have been notifying your application to pick up new configuration by POSTing to the /refresh endpoint.

When running several instances of your application, this poses several problems:

- Refreshing each individual instance is time consuming and too much overhead
- When running on Cloud Foundry you do not have control over which instances you hit when sending the POST request due to load balancing provided by the router

Cloud Bus addresses the issues listed above by providing a single endpoint to refresh all application instances via a pub/sub notification.

1. Create a RabbitMQ service instance *or* a CloudAMQP service instance and bind it to greeting—config

```
cf create-service p.rabbitmq standard cloud-bus
cf bind-service greeting-config cloud-bus
```

You can safely ignore the *TIP*: *Use 'cf restage' to ensure your env variable changes take effect* message from the CLI. Our app does not need to be restaged. We will push it again with new functionality in a moment.

2. Include the cloud bus dependency in the <code>greeting-config/pom.xml</code>. You will need to paste this in your file.

```
<dependency>
    <groupId>org.springframework.cloud</groupId>
    <artifactId>spring-cloud-starter-bus-amqp</artifactId>
</dependency>
```

3. Repackage the greeting-config application:

```
./mvnw clean package
```

4. Deploy the application and scale the number of instances.

```
cf push greeting-config -p target/greeting-config-0.0.1-SNAPSHOT.j ar -i 3
```

- 5. Observe the logs that are generated by refreshing the <code>greeting-config</code> / endpoint several times in your browser and tailing the logs. Allow this process to run through the next few steps.
 - MacOS

```
cf logs greeting-config | grep GreetingController
```

Windows

```
cf logs greeting-config
```

	All app instances are creating debug statements. Notice the <code>[App/X]</code> . It denotes which app instance is logging.
6.	Turn logging down. In your fork of the app-config repo edit the greeting-config.yml.
	Set the log level to INFO and push to Github.
	logging:
	level:
	io:
	pivotal: INFO
7.	Notify applications to pickup the change. Open a new terminal window. Send a POST to the greeting-config /bus/refresh endpoint. Use your greeting-config URL not the literal below.
	<pre>curl -X POST http://greeting-config-hypodermal-subcortex.cfapps.io /bus/refresh</pre>
8.	Refresh the greeting-config / endpoint several times in your browser. No more logs!
	(https://pivotal.io)
	course version: 1.5.3