

Status

Status provides updates about the trading session, such as halts, pauses, short-selling restrictions, auction start, and other matching engine statuses. The granularity and frequency of these updates vary by publisher and dataset.

Databento groups this under [L0](#).

Fields (`status`)

Field	Type	Description
<code>ts_recv</code>	uint64_t	The capture-server-received timestamp expressed as the number of nanoseconds since the UNIX epoch. See ts_recv .
<code>ts_event</code>	uint64_t	The matching-engine-received timestamp expressed as the number of nanoseconds since the UNIX epoch. See ts_event .
<code>rtype</code>	uint8_t	A sentinel value indicating the record type. Always 18 in the status schema. See Rtype .
<code>publisher_id</code>	uint16_t	The publisher ID assigned by Databento, which denotes the dataset and venue. See Publishers .
<code>instrument_id</code>	uint32_t	The numeric instrument ID. See Instrument identifiers .
<code>action</code>	uint16_t	The type of status change. See Status actions table below.
<code>reason</code>	uint16_t	Additional details about the cause of the status change. See Status reasons table below.
<code>trading_event</code>	uint16_t	Further information about the status change (if provided). See Trading events table below.
<code>is_trading</code>	char	The best-efforts state of trading in the instrument, either <code>Y</code> , <code>N</code> , or <code>~</code> .
<code>is_quoting</code>	char	The best-efforts state of quoting in the instrument, either <code>Y</code> , <code>N</code> , or <code>~</code> .
<code>is_short_sell_restricted</code>	char	The best-efforts state of short sell restrictions for the instrument (if applicable), either <code>Y</code> , <code>N</code> , or <code>~</code> .

Status action variants

Variant	<code>action</code>	Description
None	<code>0</code>	No change.
Pre-open	<code>1</code>	The instrument is in a pre-open period.
Pre-cross	<code>2</code>	The instrument is in a pre-cross period.
Quoting	<code>3</code>	The instrument is quoting but not trading.
Cross	<code>4</code>	The instrument is in a cross/auction.
Rotation	<code>5</code>	The instrument is being opened through a trading rotation.
New price indication	<code>6</code>	A new price indication is available for the instrument.
Trading	<code>7</code>	The instrument is trading.
Halt	<code>8</code>	Trading in the instrument has been halted.
Pause	<code>9</code>	Trading in the instrument has been paused.
Suspend	<code>10</code>	Trading in the instrument has been suspended.
Pre-close	<code>11</code>	The instrument is in a pre-close period.
Close	<code>12</code>	Trading in the instrument has closed.
Post-close	<code>13</code>	The instrument is in a post-close period.
Short sell restriction (SSR) change	<code>14</code>	A change in short-selling restrictions.
Not available for trading	<code>15</code>	The instrument is not available for trading, either trading has closed or been halted.