Floating point numbers model a tiny finite subset of reals

- almost all real values have no exact representation, e.g. 1/3
- numbers close to zero have higher precision (more accurate)

C has two floating point types

- float ... typically 32-bit (lower precision, narrower range)
- double ... typically 64-bit (higher precision, wider range)
- long double ... typically 128-bits (but maybe only 80 bits used)

Literal floating point values: 3.14159, 1.0/3, 1.0e-9

```
printf("%10.4lf", (double)2.718281828459);
// displays 2.7183
printf("%20.20lf", (double)4.0/7);
//displays 0.57142857142857139685
```

IEEE 754 standard ...

- C floats almost always IEEE 754 single precision (binary32)
- C double almost always IEEE 754 double precision (binary64)
- C long double might be IEEE 754 (binary128)
- scientific notation with fraction F and exponent E
- numbers have form $F \times 2^E$, where both F and E can be -ve
- INFINITY = representation for ∞ and $-\infty$ (e.g. 1.0/0)
- NAN = representation for invalid value (e.g. sqrt(-1.0))

Fraction part is *normalised* (i.e. 1.2345×10^2 rather than 123.45) In binary, exponent is represented relative to a bias value B

• if the unsigned exponent value is e, the actual value is e - B


Example of normalising the fraction part in binary:

- 1010.1011 is normalized as 1.0101011×2^{011}
- 1010.1011 = 10 + 11/16 = 10.6875
- 1.0101011 \times 2⁰¹¹ = (1 + 43/128) * 2³ = 1.3359375 * 8 = 10.6875

The normalised fraction part always has 1 before the decimal point. Example of determining the exponent in binary:

- ullet assume an 8-bit exponent, then bias $B=2^{8-1}-1=127$
- valid bit patterns for exponent 00000001 .. 11111110
- exponent values -126 .. 127

Internal structure of floating point values



More complex representation than int because 1.ddddedd

```
$ ./explain_floating_point_representation -0.125
-0.125 is represented as IEEE-754 single-precision
sign | exponent | fraction
  sign bit = 1
sign = -
raw exponent = 01111100 binary
           = 124 decimal
actual exponent = 124 - exponent bias
           = 124 - 127
           = -3
= -1 \text{ decimal} * 2**-3
    = -1 * 0.125
    = -0.125
```

```
$ ./explain_floating_point_representation 150.75
150.75 is represented in IEEE-754 single-precision
sign | exponent | fraction
  sign bit = 0
sign = +
raw exponent = 10000110 binary
            = 134 decimal
actual exponent = 134 - exponent bias
             = 134 - 127
             = 7
number = +1.0010110110000000000000 binary * 2**7
     = 1.17773 decimal * 2**7
     = 1.17773 * 128
     = 150.75
```

```
$ ./explain_floating_point_representation inf
inf is represented as IEEE-754 single-precision
sign | exponent | fraction
  sign bit = 0
sign = +
raw exponent = 11111111 binary
           = 255 decimal
number = +inf
```

```
$ ./explain_floating_point_representation NaN
NaN is represented as IEEE-754 single-precision
sign | exponent | fraction
  sign bit = 0
sign = +
raw exponent = 11111111 binary
           = 255 decimal
number = NaN
```

Exercise: Floating point → **Decimal**

Convert the following floating point numbers to decimal. Assume that they are in IEEE 754 single-precision format.

```
0 10000000 11000000000000000000000
```