#### Contents

- 1. Introduction
- 2. System Structures
- 3. Process Concept
- 4. Multithreaded Programming
- 5. Process Scheduling
- 6. Synchronization
- 7. Deadlocks
- 8. Memory-Management Strategies



- 9. Virtual-Memory Management
- 10. File System
- 11. Mass-Storage Structures
- 12. I/O Systems
- 13. Protection, Security, Distributed Systems 67

# **Chapter 9 Virtual-Memory Management**

#### Virtual Memory

- Virtual Memory
  - A technique that allows the execution of a process that may not be completely in memory.
- Motivation:
  - An entire program in execution may not all be needed at the same time!
    - e.g. error handling routines, a large array, certain program features, etc


### Virtual Memory

- Potential Benefits
  - Programs can be much larger than the amount of physical memory. Users can concentrate on their problem programming.
  - The level of multiprogramming increases because processes occupy less physical memory.
  - Each user program may run faster because less I/O is needed for loading or swapping user programs.
- Implementation: demand paging, demand segmentation (more difficult),etc.


## Demand Paging – Lazy Swapping

- Process image may reside on the backing store. Rather than swap in the entire process image into memory, Lazy Swapper only swaps in a page when it is needed!
  - Pure Demand Paging Pager vs Swapper
  - A Mechanism required to recover from the missing of non-resident referenced pages.
    - A page fault occurs when a process references a non-memory-resident page.

# Demand Paging – Lazy Swapping



# A Procedure to Handle a Page Fault



<sup>\*</sup> All rights reserved, Tei-Wei Kuo, National Taiwan University.

# A Procedure to Handle A Page Fault

- Pure Demand Paging:
  - Never bring in a page into the memory until it is required!
- Pre-Paging
  - Bring into the memory all of the pages that "will" be needed at one time!
  - Locality of reference

# Hardware Support for Demand Paging


- New Bits in the Page Table
  - To indicate that a page is now in memory or not.
- Secondary Storage
  - Swap space in the backing store
    - A continuous section of space in the secondary storage for better performance.

#### Crucial issues

- Example 1 Cost in restarting an instruction
  - Assembly Instruction: Add a, b, c
  - Only a short job!
    - Re-fetch the instruction, decode, fetch operands, execute, save, etc
  - Strategy:
    - Get all pages and restart the instruction from the beginning!


#### **Crucial Issues**

- Example 2 Block-Moving Assembly Instruction
  - MVC x, y, 256
    - IBM System 360/ 370
  - Characteristics
    - More expensive
    - "self-modifying" "operands"
  - Solutions:
    - Pre-load pages
    - Pre-save & recover before page-fault services



#### Crucial Issues

■ Example 3 – Addressing Mode



- Effective Access Time:
  - ma: memory access time for paging
  - p: probability of a page fault
  - pft: page fault time

$$(1 - p) * ma + p * pft$$

- Page fault time major components
  - Components 1&3 (about 10³ ns ~ 10⁵ ns)
    - Service the page-fault interrupt
    - Restart the process
  - Component 2 (about 8ms)
    - Read in the page (multiprogramming! However, let's get the taste!)
    - pft ≈ 8ms = 8,000,000 ns
- Effect Access Time (when ma = 100ns)
  - (1-p) \* 100ns + p \* 8,000,000 ns
  - 100ns + 7,999,900ns \* p

- Example (when ma = 100ns)
  - p = 1/1000
  - Effect Access Time ≈ 8,000 ns
    - → Slowed down by 80 times
  - How to only 10% slow-down?


```
110 > 100 * (1-p) + 8,000,000 * p
```

p < 0.0000125

p < 1 / 799,990


- How to keep the page fault rate low?
  - Effective Access Time ≈ 100ns + 7,999,900ns \* p
- Handling of Swap Space A Way to Reduce Page Fault Time (pft)
  - Disk I/O to swap space is generally faster than that to the file system.
    - Preload processes into the swap space before they start up.
    - Demand paging from file system but do page replacement to the swap space. (BSD UNIX)

### Copy-on-Write



Page Table 2

- Rapid Process Creation and Reducing of New Pages for the New Process
- fork(); execve()
  - Shared pages → copy-on-write pages
    - Only the pages that are modified are copied!



### Copy-on-Write

- zero-fill-on-demand
  - Zero-filled pages, e.g., those for the stack or bss.
- vfork() vs fork() with copy-on-write
  - vfork() lets the sharing of the page table and pages between the parent and child processes.
  - Where to keep the needs of copy-onwrite information for pages?


- Demand paging increases the multiprogramming level of a system by "potentially" over-allocating memory.
  - Total physical memory = 40 frames
  - Run six processes of size equal to 10 frames but with only five frames. => 10 spare frames
- Most of the time, the average memory usage is close to the physical memory size if we increase a system's multiprogramming level!

- Q: Should we run the 7th processes?
  - How if the six processes start to ask their shares?
- What to do if all memory is in use, and more memory is needed?
- Answers
  - Kill a user process!
    - But, paging should be transparent to users?
  - Swap out a process!
  - Do page replacement!

可能產生兩個 I/O,把 victim 搬出去,再把 page 搬進來

- A Page-Fault Service
  - Find the desired page on the disk!
  - Find a free frame
    - Select a victim and write the victim page out when there is no free frame!
  - Read the desired page into the selected frame.
  - Update the page and frame tables, and restart the user process.


#### Logical Memory Page Table




3	V
4	V
5	V
	i

P2	0	А
	1	В
	2	D
	3	Е

6	V
	i
2	V
7	V





Two page transfers per page fault if no frame is available!

#### Page Table

6	V	Ν				
4	V	N				
3	V	Υ				
7	V	Υ				
	<b>↑</b>					
id-Invalid Bit						

Modify Bit is set by the hardware automatically!

Modify (/Dirty) Bit! To

"eliminate" 'swap out"

=> Reduce I/O time by onehalf

- Two Major Pieces for Demand Paging
  - Frame Allocation Algorithms
    - How many frames are allocated to a process?
  - Page Replacement Algorithms
    - When page replacement is required, select the frame that is to be replaced!
  - Goal: A low page fault rate!
- Note that a bad replacement choice does not cause any incorrect execution!

#### Page Replacement Algorithms


- Evaluation of Algorithms
  - Calculate the number of page faults on strings of memory references, called reference strings, for a set of algorithms
- Sources of Reference Strings
  - Reference strings are generated artificially.
  - Reference strings are recorded as system traces:
    - How to reduce the number of data?

#### Page Replacement Algorithms

- Two Observations to Reduce the Number of Data:
  - Consider only the page numbers if the page size is fixed.
    - Reduce memory references into page references
  - If a page p is referenced, any immediately following references to page p will never cause a page fault.
    - Reduce consecutive page references of page p into one page reference.

#### Page Replacement Algorithms

Example



0100, 0432, 0101, 0612, 0103, 0104, 0101, 0611


①
01, 04, 01, 06, 01, 01, 06

①
①
01, 04, 01, 06, 01, 06

Does the number of page faults decrease when the number of page frames available increases?

### FIFO Algorithm

- A FIFO Implementation
  - 1. Each page is given a time stamp when it is brought into memory.
  - 2. Select the oldest page for replacement!



### FIFO Algorithm

- The Idea behind FIFO
  - The oldest page is unlikely to be used again.
  - ??Should we save the page which will be used in the near future??
- Belady's anomaly
  - For some page-replacement algorithms, the page fault rate may increase as the number of allocated frames increases.

## FIFO Algorithm


Run the FIFO algorithm on the following reference:

string:	1	2	3	4	1	2	5	1	2	3	4	5
2.6	1	1	1	2	3	4	1	1	1	2	5	5
3 frames		2	2	3	4	1	2	2	2	5	3	3
			3	4	1	2	5	5	5	3	4	4
	•			•			•		•			•
	1	1	1	1	1	1	2	3	4	5	1	2
4 frames		2	2	2	2	2	3	4	5	1	2	3
			3	3	3	3	4	5	1	2	3	4
				4	4	4	5	1	2	3	4	5

<sup>\*</sup> All rights reserved, Tei-Wei Kuo, National Taiwan University.

### **Optimal Algorithm (OPT)**

- Optimality
  - One with the lowest page fault rate.
- Replace the page that will not be used for the longest period of time. ←→ Future Prediction



## Least-Recently-Used Algorithm (LRU)


- The Idea:
  - OPT concerns when a page is to be used!
  - "Don't have knowledge about the future"?!

Use the history of page referencing in the past to predict the future!

S? SR (SR is the reverse of S!)


#### LRU Algorithm

#### Example



Remark: LRU is like OPT which "looks backward" in time.

### LRU Implementation - Counters




#### LRU Implementation - Counters

#### Overheads

- The logical clock is incremented for every memory reference.
- Update the "time-of-use" field for each page reference.
- Search the LRU page for replacement.
- Overflow prevention of the clock & the maintenance of the "time-of-use" field of each page table.

#### LRU Implementation – Stack



# A Stack Algorithm

```
memory-
resident
pages

n frames
available

memory-
resident
pages
(n +1) frames
available
```


- Need hardware support for efficient implementations.
- Note that LRU maintenance needs to be done for every memory reference.

## LRU Approximation Algorithms

- Motivation
  - No sufficient hardware support
  - Most systems provide only "reference bit" which only indicates whether a page is used or not, instead of their order.
- Additional-Reference-Bit Algorithm
- Second-Chance Algorithm
- Enhanced Second Chance Algorithm
- Counting-Based Page Replacement

#### Additional-Reference-Bits Algorithm

- Motivation
  - Keep a history of reference bits



reference bit

one byte per page in memory


#### Additional-Reference-Bits Algorithm

History Registers

```
(smaller value!)  \begin{array}{c} LRU \\ 000000001 \end{array}  Not used for 8 times  00000001   \begin{array}{c} 111111110 \\ 111111111 \end{array}  Used at least once every time
```

- But, how many bits per history register should be used?
  - Fast and cost-effective!
  - The more bits, the better the approximation is.

#### Second-Chance (Clock) Algorithm



- Motivation
  - Use the reference bit only
- Basic Data Structure:
  - Circular FIFO Queue
- Basic Mechanism
  - When a page is selected
    - Take it as a victim if its reference bit = 0
    - Otherwise, clear the bit and advance to the next page

207

# **Enhanced Second-Chance Algorithm**

- Motivation:
  - Consider the cost in swapping out pages.
  - 4 Classes (reference bit, modify bit)
    - (0,0) not recently used and not "dirty"
    - (0,1) not recently used but "dirty"
    - (1,0) recently used but not "dirty"
    - (1,1) recently used and "dirty"

low priority

high priority

# Enhanced Second-Chance Algorithm ST page fault 的 probability

- Use the second-chance algorithm to replace the first page encountered in the lowest nonempty class.
  - => May have to scan the circular queue several times before find the right page.
- Macintosh Virtual Memory Management

### **Counting-Based Algorithms**

- Motivation:
  - Count the # of references made to each page, instead of their referencing times.
- Least Frequently Used Algorithm (LFU)
  - LFU pages are less actively used pages!
  - Potential Hazard: Some heavily used pages may no longer be used!
  - A Solution Aging
    - Shift counters right by one bit at each regular interval.

#### **Counting-Based Algorithms**

- Most Frequently Used Algorithm (MFU)
  - Pages with the smallest number of references are probably just brought in and has yet to be used!
- LFU & MFU replacement schemes can be fairly expensive!
- They do not approximate OPT very well!

不是很好的方法

### Page Buffering

減少 page fault service time

- Basic Idea
  - a. Systems keep a pool of free frames
  - b. Desired pages are first "swapped in" some frames in the pool.
  - c. When the selected page (victim) is later written out, its frame is returned to the pool.
- Variation 1
  - a. Maintain a list of modified pages.
  - Whenever the paging device is idle, a modified page is written out and reset its "modify bit".

### Page Buffering

- Variation 2
  - a. Remember which page was in each frame of the pool.
  - b. When a page fault occurs, first check up whether the desired page is there already.
    - Pages which were in frames of the pool must be "clean".
    - "Swapping-in" time is saved!
- VAX/VMS with the FIFO replacement algorithm adopt it to improve the performance of the FIFO algorithm.

很大的垃殼桶,很本的腦袋 -> LRU

#### Frame Allocation – Single User

- Basic Strategy:
  - User process is allocated any free frame.
  - User process requests free frames from the free-frame list.
  - When the free-frame list is exhausted, page replacement takes place.
  - All allocated frames are released by the ending process.
- Variations
  - O.S. can share with users some free frames for special purposes.
  - Page Buffering Frames to save "swapping" time

- Fixed Allocation
  - a. Equal Allocation m frames, n processes → m/n frames per process
  - b. Proportional Allocation

```
S = \Sigma S_i, A_i \propto (S_i / S) \times m, where (sum <= m) & (A_i >= minimum \# of frames required)
```

- 2. Ratios of Frames ∞ Priority S<sub>i</sub> : relative importance
  - 3. Combinations, or others.

- Dynamic Allocation
  - a. Allocated frames ∞ the multiprogramming level
  - b. Allocated frames ∞ Others
- The minimum number of frames required for a process is determined by the instruction-set architecture.
  - ADD A,B,C → 4 frames needed
  - ADD (A), (B), (C) → 1+2+2+2 = 7 frames, where (A) is an indirect addressing.

    indirect pointer

16 bits

address

0 direct 1 indirect

- Minimum Number of Frames (Continued)
  - How many levels of indirect addressing should be supported?
    - It may touch every page in the logical address space of a process
      - => Virtual memory is collapsing!
  - A long instruction may cross a page boundary.

MVC X, Y, 256  $\rightarrow$  2 + 2 + 2 = 6 frames

The spanning of the instruction and the operands.

- Global Allocation 可以搶別人的 frame,類似 dynamic allocation
  - Processes can take frames from others. For example, high-priority processes can increase its frame allocation at the expense of the low-priority processes!
- Local Allocation
  - Processes can only select frames from their own allocated frames → Fixed Allocation
  - The set of pages in memory for a process is affected by the paging behavior of only that process.


- Remarks
  - a.Global replacement generally results in a better system throughput
  - b. Processes might not control their own page fault rates such that a process can affect each another easily under global replacement.

## **Non-Uniform Memory Access**

- Non-Uniform Memory Access (NUMA) Systems:
  - The access of some memory section might be faster than that of another.
    - It is due to how CPUs and memory are interconnected.
  - Potential Issues
    - Memory frame allocation versus CPU scheduling
      - Threading Considerations over Cores

## **Thrashing**


- Thrashing A High Paging Activity:
  - A process is thrashing if it is spending more time paging than executing.
- Why thrashing? 大家都在 page fault
  - Too few frames allocated to a process!



### **Thrashing**

- Solutions:
  - Decrease the multiprogramming level
     → Swap out processes!
  - Use local page-replacement algorithms
    - Only limit thrashing effects "locally"
    - Page fault services of other processes also slow down. 不見得有用,可能會用到 disk 仍會影響
  - Give processes as many frames as they need!
    - But, how do you know the right number of frames for a process?


## **Locality Model**



- A program is composed of several different (overlapped) localities.
  - Localities are defined by the program structures and data structures (e.g., an array, hash tables)
- How do we know that we allocate enough frames to a process to accommodate its current locality?

## Working-Set Model

#### Page references



The working set is an approximation of a program's locality.


可能 window 的設法不對,不一定 10,可能 20、30……

The minimum  $\Delta$   $\infty$  All touched pages may cover several localities.

## Working-Set Model

$$D = \sum working - set - size_i \leq M$$


where M is the total number of available frames.



# Working-Set Model

猜測 locality,才知道要給你多少 frame


- The maintenance of working sets is expensive!
  - Approximation by a timer and the reference bit



Accuracy v.s. Timeout Interval!

# Page-Fault Frequency


- Motivation
  - Control thrashing directly through the observation on the page-fault rate!





\*Processes are suspended and swapped out if the number of available frames is reduced to that under the minimum needs.227

#### Memory-Mapped Files

- File writes might not cause any disk write!
- Solaris 2 uses memory-mapped files for open(), read(), write(), etc.







### **Shared Memory – Windows API**

#### Producer


- hfile=CreateFile("temp,txt", ...);
- hmapfile=CreateFileMapping(hfile, ..., TEXT("Shared Object"));
- Ipmapaddr=MapViewOfFile(hm apfile, ...);
- sprintf(Ipmapaddr,"for consumer");
- UnmapViewOfFile(Ipmapaddr);
- CloseHandle(hfile);
- CloseHandle(hmapfile);

#### Consumer

- hmapfile=OpenFileMapping( ..., TEXT("Shared Object"));
- IpMapAddress=MapViewOfF ile(hmapfile, ...);
- printf("Read msg %s", lpMapAddress);
- UnmapViewOfFile(Ipmapador);
- CloseHandle(hmapfile);

\* Named shared-memory objects

### Memory-Mapped I/O




- Processor can have direct access!
- Intermediate storage for data in the registers of device controllers
- Memory-Mapped I/O (PC & Mac)
  - (1) Frequently used devices
  - (2) Devices must be fast, such as video controller, or special I/O instructions are used to move data between memory & device controller registers
- Programmed I/O polling
  - or interrupt-driven handling


request I/O

- Separation from user-mode memory allocation
  - The kernel might request memory of various sizes, that are often less than a page in size.
  - Certain hardware devices interact directly with physical memory, and the accesses memory must be in physically contiguous pages!

- The Buddy System
  - A fixed-size segment of physically contiguous pages
  - A power-of-2 allocator
  - Advantage: quick coalescing algorithms
  - Disadvantage: internal fragmentation 若 17, 就浪費



- Slab Allocation
  - Slab: one or more physically contiguous pages
  - Cache: one or more slabs



- Slab States
  - Full
  - Empty
  - Partial

- Slab Allocator
  - Look for a free object in a partial slab.
  - Otherwise, allocate a new slab and assign it to a cache.
- Benefits
  - No space wasted in fragmentation.
  - Memory requests are satisfied quickly.
- Implementations
  - Solaris 2.4 kernel, Linux version 2.2+

- Pre-Paging
  - Bring into memory at one time all the pages that will be needed!



Do pre-paging if the working set is known!


Issue

Pre-Paging Cost ←→ Cost of Page Fault Services

Not every page in the working set will be used!

Page Size

Better
Resolution
for Locality &
Internal
Fragmentation




Smaller Page Table Size & Better I/O Efficiency

- Trends Large Page Size
  - The CPU speed and the memory capacity grow much faster than the disk speed!

- TLB Reach
  - TLB-Entry-Number \* Page-Size
- Wish
  - The working set is stored in the TLB!
  - Solutions
    - Increase the page size
    - Have multiple page sizes UltraSparc II (8KB - 4MB) + Solaris 2 (8KB or 4MB)


- Inverted Page Table
  - The objective is to reduce the amount of physical memory for page tables, but they are needed when a page fault occurs!
  - More page faults for page tables will occur!!!

- **Program Structure** 
  - Motivation Improve the system performance by an awareness of the underlying demand paging.



- Program Structures:
  - Data Structures
    - Locality: stack, hash table, etc.
    - Search speed, # of memory references, # of pages touched, etc.
  - Programming Language
    - Lisp, PASCAL, etc.
  - Compiler & Loader
    - Separate code and data
    - Pack inter-related routines into the same page
    - Routine placement (across page boundary?)

#### I/O Interlock



- DMA gets the following information of the buffer:
  - Base Address in Memory
  - Chunk Size
- Could the buffer-residing pages be swapped out?

Physical Memory

#### I/O Interlock

- Solutions
  - I/O Device ←→ System Memory ←→ User Memory
    - Extra Data Copying!!
  - Lock pages into memory
    - The lock bit of a page-faulting page is set until the faulting process is dispatched!
    - Lock bits might never be turned off!
    - Multi-user systems usually take locks as "hints" only!

#### **Real-Time Processing**

Predictable  $\longleftrightarrow$  Behavior

Virtual memory introduces unexpected, long-term delays in the execution of a program.

#### Solution:

■ Go beyond locking hints → Allow privileged users to require pages being locked into memory!

#### OS Examples – Windows

- Virtual Memory Demand Paging with Clustering
  - Clustering brings in more pages surrounding the faulting page!
  - Working Set
    - A Min and Max bounds for a process
      - Local page replacement when the max number of frames are allocated.
    - Automatic working-set trimming reduces allocated frames of a process to its min when the system threshold on the available frames is reached.

# OS Examples – Solaris



- Process *pageout* first clears the reference bit of all pages to 0 and then later returns all pages with the reference bit = 0 to the system *(handspread)*.
  - 4HZ → 100HZ when desfree is reached!
    - Swapping starts when desfree fails for 30s.
  - pageout runs for every request to a new page when minfree is reached.

#### **Demand Segmentation**

- Motivation
  - Segmentation captures better the logical structure of a process!
  - Demand paging needs a significant amount of hardware!
- Mechanism
  - Like demand paging!
  - However, compaction may be needed!
    - Considerable overheads!