## Bee GFS Practical Server Client 198 2000 1900

Server - NAT: - 192.168.44.145 - Hostnare - bgts-scover Client - NAT: - 192.168.44.146 - Hostnare. - bgfs-client

## on both machine

# systemeth stop firewalld
# systemeth disable firewalld
# Vi /etc/selinup/config
L> SELINUP= disabled
# Vi/etc/hosts
L> 192.168.44.145 bgfs-server
192.168.44.146 bgfs-client

```
on server
 # ssh-keygen
 It ssh-copy-id root@ bgfs-client
# taish Iden sab
# mkts.ext4 /dev/6db1
# mount /dev/sdb1 /mnt/
# yum install wget
# wget --no-check-certificate -0 /etc/yum.repos.d/
   beegts repo https://www.beegts.io/release/beegts_
   7.2 / dists / bregts - whelt we shelt vepo
# yum Install by becats-utils beegts-client beegts-
    meta beegts-storage beegts-mgmtd
 # Mkdir -p/mnt/beegts/meta
# mkdir - p/mnt/beegts/storage
# Mrdir -p /mnt/ beegts / beegts_mgmtd
# /opt/beegts/sbin/beegts-setup-mgmtd-p/mnt/
   beegts/beegts_mgmtd
# vi /etc/beegts/beegfs-client.conf
   > 545 Mgmtd Host = 192.168.44.145
                      Server ip
```

# systemed start beggs-mgmtd # systemed enable beggs-mgmtd

# /opt/beegfs/sbin/beegfs-setup-meta -P/mnt/beegfs
/meta -s 1-m 192.168.44.145
server ip

# systematl stuot beegts - metal # systematl enable beegts - metal

# /opt/beegts/sbin/beegts-setup-storage -p/mnt/ beegts/storage -s 2 -i 1 -m 192.166.44.145 server ip

# systemed start breggs-storage # systemed enable breggs-storage

# beegfs - check - servers -> all servers are activeted

# beegts-ctl -- listnodes -- nodetype= storage -- nic details

-- nic details or server, ports details, interfaces.

## on dient

# yum install k-conel-devel beegts-ulls beegts-client
beegts-mgmtd

wget --no-check-ceotificate -0 /etc/yum.oepos.d/
beegts.oepo https://www.beegts.io/oelease/beegts\_

7.2/dists/beegfs-shelt-repo

#/opt/beegts/sbin/beegts-setup-client-m 198.168.44

.145

server ip

# systemat start beegts-dient

# systemed start beegts-dient. # systemed enable beegts-client