Chapter 3 - Arithmetic for Computers

- Chapter 3 Arithmetic for Computers
 - Integer
 - Overflow
 - Overflow conditions
 - How MIPS deals with overflow
 - Multiplication
 - Division
 - Floating Point
 - Scientific Notation
 - To convert from "human mode" to "machine mode":
 - Smallest and Largest in Single-precision
 - Smallest and Largest in Double-precision
 - Practice
 - Convert Base 10 Floating number to IEEE Binary
 - Convert IEEE Binary to Base 10 Floating number
 - Addition of Floating Point numbers in Base 10
 - Addition of Floating Point numbers in Base 2
 - Multiplication of Floating Point numbers in Base 10
 - Multiplication of Floating Point numbers in Base 2
 - Load/Store Floating Point Instructions in MIPS
 - Other Operational Floating Point Instructions
 - Other Notes
 - Excercise

1. Integer

1.1. Overflow

1.1.1. Overflow conditions

Add

- (+) add (-) -> No overflow
- (+) add (+) , result sign is 1 -> Overflow
- (-) add (-), result sign is 0 -> Overflow

Subtract

- (+) subtract (+), or (-) subtract (-) -> No overflow
- (+) subtract (-), result sign is 1 -> Overflow
- (-) subtract (+), result sign is 0 -> Overflow

1.1.2. How MIPS deals with overflow

on overflow:

- save PC in EPC (exception program counter) register (for returning later)
- jump to predefined handler address (to handle this overflow, if any)
- use mfc0 instruction to retrieve EPC value to return after corrective action

1.2. Multiplication

MIPS allows multiplication of two 32-bit registers, the product is stored into 2 registers:

- Upper part (aka most significant 32 bits): HI
- Lower part (aka least significant 32 bits): LO

Formula: mult rs, rt

To read result (2 x 32-bit registers)

- mfhi rd: move HI to rd
- mflo rd: move LO to rd

Note: mul rd, rs, rt does work too, but the result only stores least-significant 32-bit (i.e. LO)

1.3. Division

MIPS also uses HI/LOW for division but in a different way:

- HI: stores the remainder, in 32-bit.
- LO: stores the quotient, in 32-bit.

Formula: div rs, rt

1.4. Floating Point

1.4.1. Scientific Notation

Normalzied form

• Decimal value must be in the form of $\pm x$. $yyy * 10^{zzz}$. There must be only 1 digit on the left of the

floating point.

• Binrary value must be in the form of $\pm 1.xxxxxxx_2 * 2^{yyyy}$. There must be value '1' on the left of the floating point.

IEEE Std 754-1985

There are 2 "modes" (personal opinions) to represent binary floating number:

• The first mode is the "human mode", it is how we present the number in writing, and it is the normalized form described above: $\pm 1.xxxxxx_2 * 2^{yyyy}$

$$x = (-1)^{S} \times (1 + Fraction) \times 2^{(Exponent-Bias)}$$

• The second mode is the "machine mode", it is how the machine reads and operates on floating point.

single: 8 bits single: 23 bits double: 11 bits double: 52 bits

S Exponent Fraction

1.4.1.1. To convert from "human mode" to "machine mode":

- Make sure the value in "human mode" is already normalized before proceed.
- Record Sign bit (S) as 1 if this is a negative number, 0 if positive.
- The fraction is taken from the matissa of the floating number in "human mode". For e.g. fraction of 1.10101 is 10101. This goes straight to the Fraction bit section, starts from <u>LEFT MOST BIT TO THE</u> <u>RIGHT</u> on bit 10 for single precision, or bit 13 for double precision.
- The Exponent value of the bit section is the binary value of the Exponent in the human mode, plus the Bias, which is 127 for Single Precision, and 1023 for Double Precision.

Invert the process to get "human mode" writing from "machine mode" floating binary.

1.4.1.2. Smallest and Largest in Single-precision

Exponents 00000000 and 11111111 reserved

in machine ande

IN IEEE formati

Smallest value

NOT ALLOWED

- Exponent: 00000001
 - \Rightarrow actual exponent = 1 127 = -126
- Fraction: 000...00 ⇒ significand = 1.0
- 1.0 × 2⁻¹²⁶ ≈ 1.2 × 10⁻³⁸

Largest value

- exponent: 11111110)
 - \Rightarrow actual exponent = 254 127 = +127
- Fraction: 111...11 ⇒ significand ≈ 2.0
- 2.0 × 2⁺¹²⁷ ≈ 3.4 × 10⁺³⁸

1.4.1.3. Smallest and Largest in Double-precision

Exponents 0000...00 and 1111...11 reserved

Smallest value

- Exponent: 0000000001
 - \Rightarrow actual exponent = 1 1023 = -1022
- Fraction: 000...00 ⇒ significand = 1.0
- 1.0 × 2⁻¹⁰²² ≈ 2.2 × 10⁻³⁰⁸

Largest value

- Exponent: 11111111110
 - \Rightarrow actual exponent = 2046 1023 = +1023
- Fraction: 111...11 ⇒ significand ≈ 2.0
- 2.0 × 2⁺¹⁰²³ ≈ 1.8 × 10⁺³⁰⁸

1.4.2. Practice

1.4.2.1. Convert Base 10 Floating number to IEEE Binary

Represent -0.75significand (if an active to digits $\Rightarrow 1.100$) $-0.75 = (-1)^1 \times 1.1_2 \times 2^{-1}$ S = 1

S = 1

Fraction = $1000...00_2$ Exponent = -1 + BiasSingle: $-1 + 127 = 126 = 01111110_2$

■ Double: −1 + 1023 = 1022 = 011111111110₂

Single: 1011111101000...00

Double: 10111111111101000...00

1.4.2.2. Convert IEEE Binary to Base 10 Floating number

What number is represented by the singleprecision float

11000000101000...00

1.4.2.3. Addition of Floating Point numbers in Base 10

Consider a 4-digit decimal example

- 9.999 × 10¹ + 1.610 × 10⁻¹
- 1. Align decimal points

- Shift fractional number on smaller exponent
- 9.999 × 10¹ + 0.016 × 10¹
- Add significands

$$\bullet$$
 9.999 × 10¹ + 0.016 × 10¹ = 10.015 × 10¹

- Normalize result & check for over/underflow
 - 1.0015 × 10²
- 4. Round and renormalize if necessary
- 1.002 × 10²

1.4.2.4. Addition of Floating Point numbers in Base 2

Now consider a 4-digit binary example

$$1.000_2 \times 2^{-1} + -1.110_2 \times 2^{-2} (0.5 + -0.4375)$$

- 1. Align binary points
- Shift number with smaller exponent
- $1.000_2 \times 2^{-1} + -0.111_2 \times 2^{-1}$
- 2. Add significands

$$1.000_2 \times 2^{-1} + -0.111_2 \times 2^{-1} = 0.001_2 \times 2^{-1}$$

- 3. Normalize result & check for over/underflow
- 1.000₂ × 2⁻⁴, with no over/underflow
- 4. Round and renormalize if necessary
 - $1.000_2 \times 2^{-4}$ (no change) = 0.0625

Convert floating binary number to base 10

1.4.2.5. Multiplication of Floating Point numbers in Base 10

- Consider a 4-digit decimal example
 - 1.110 × 10¹⁰ × 9.200 × 10⁻⁵
- 1. Add exponents
 - For biased exponents, subtract bias from sum
 - New exponent = 10 + -5 = 5
- 2. Multiply significands
 - $1.110 \times 9.200 = 10.212 \Rightarrow 10.212 \times 10^{5}$
- 3. Normalize result & check for over/underflow
 - 1.0212 × 10⁶
- 4. Round and renormalize if necessary

Adights 1.021 × 106

- 5. Determine sign of result from signs of operands
 - +1.021 × 10⁶

1.4.2.6. Multiplication of Floating Point numbers in Base 2

Now consider a 4-digit binary example

- $1.000_2 \times 2^{-1} \times -1.110_2 \times 2^{-2} (0.5 \times -0.4375)$
- Add exponents
 - Unbiased: -1 + -2 = -3
 - Biased: (-1 + 127) + (-2 + 127) = -3 + 254 127 = -3 + 127
- 2. Multiply significands
 - $1.000_2 \times 1.110_2 = 1.110_2 \Rightarrow 1.110_2 \times 2^{-3}$
- 3. Normalize result & check for over/underflow
- 1.110₂ × 2⁻³ (no change) with no over/underflow
- 4. Round and renormalize if necessary if an does not esk,

 1 110. × 2-3 (no change)
 - 1.110₂ × 2⁻³ (no change)
- 5. Determine sign: +ve \times -ve \Rightarrow -ve
 - $-1.110_2 \times 2^{-3} = -0.21875$

1.4.3. Load/Store Floating Point Instructions in MIPS

Using different instructions:

lwc1, ldc1, swc1, sdc1
 e.g., ldc1 \$f8, 32(\$sp)
 load word floating.

and different registers:

32 single-precision: \$f0, \$f1, ... \$f31

1.4.4. Other Operational Floating Point Instructions

Single-precision arithmetic

add.s, sub.s, mul.s, div.s

e.g., add.s \$f0, \$f1, \$f6

Double-precision arithmetic

add.d, sub.d, mul.d, div.d

e.g., mul.d \$f4, \$f4, \$f6

Single- and double-precision comparison

c.xx.s, c.xx.d (xx is eq, lt, le, ...)

Sets or clears FP condition-code bit

e.g. c.lt.s \$f3, \$f4

Branch on FP condition code true or false

bc1t, bc1f

e.g., bc1t TargetLabel

2. Other Notes

- Shift Left/Right only works correctly on unsigned numbers, NOT signed number.
- MIPS ISA: uses mostly 54 core instructions, the rests are less frequent.

3. Excercise

- 1. Use the MIPS algorithm in this chapter to get the binary sum for these two decimal numbers, verify your result is correct. $5_{10}+9_{10}=?_2$
- 2. Use the MIPS algorithm in this chapter to get the binary difference for these two decimal numbers, verify your result is correct. 5_{10} - 9_{10} = $?_2$
- 3. Use the MIPS algorithm in this chapter to get the binary product for these two decimal numbers, verify your result is correct. $5_{10} \times 9_{10} = ?_2$
- 4. Use the MIPS algorithm in this chapter to get the binary quotient and binary remainder for these two decimal numbers, verify your result is correct. $9_{10}/2_{10} = ?_2$
- Use the IEEE754 binary floating point format to show the decimal number "-1.37510" in single and double precision binary floating point format.
- Add following two decimal floating numbers together, use the binary normalized scientific notation and show the steps, keep the result significand in 4 digits, the exponent in two decimal digits: -0.810 0.62510
- Multiply following two decimal floating numbers together, use the binary normalized scientific notation and show the steps, keep the result significand in 4 digits, the exponent in two decimal digits: -0.810 0.62510