# Snaptodo—A Snap-to-the-Correct-Side Todo

Hsin-Po Wang\*

November 22, 2021

#### Abstract

Snaptodo package is an alternative to the todonote package that differs in the following ways: (A) Depending on where you call \todo, the note is put on the left or right margin, whichever is closer. (B) The notes bump each other down so they never overlap; the lines never overlap either; and they don't trigger the marginpar warning. (C) Minimalistic, aesthetic, and customizable style.

## 1 Installation

Copy and paste snaptodo.sty to your working directory.

## 2 Minimal Working Example

\documentclass{article}
\usepackage{snaptodo}
\begin{document}
 Your done
 \todo{Your todo}
\end{document}

# 3 Showcase of Examples

Calling Calling \todo! Using snaptodo is as simple as calling \todo and compile twice. If the calling point! point is on the left of a page, the todo note, after compiling twice of course, will Compile appear to the left margin. And vice versa. Left of a twice! page! Customization 4 Vice versa! On the left I defined \snaptodoset that works like \tikzset and \pgfplotsset. While margin!

you can access dedicated options by \snaptodoset{<some\_option>}, you can

<sup>\*</sup>A.Simple.People@gmail.com

also assess the exact same options by \pgfkeys{/snaptodo/<some\_option>}. For local changes, you can put them here \todo[<some\_option>]{}.

#### 4.1 Color

The color of the broken line is snaptodo@chain. The default color for that is red!50!black. Saying \colorlet{snaptodo@chain}{green!50!white} lets you to change this color globally. On the other hand, for locally changing this color, one may prefer using \todo[call chain/.style=green!50!white].

New broken line color

The color of the note text is snaptodo@block. The default color for that is yellow!50!black. Saying \colorlet{snaptodo@block}{blue!50!white} lets you change this color. On the other hand, for locally changing this color, one may prefer using \todo[margin block/.style=blue!50!white].

New note text color

## 4.2 Length

The gap between two note blocks is stored in /snaptodo/block sep. The default length is \baselineskip. Use \snaptodoset{block sep=0pt} for global setting and use \todo[block sep=0pt] {note}\_+ for local setting this.

2 blocks close.

The gap between two horizontal lines is stored in /snaptodo/chain sep. The default length is 0.5ex. To change, use \snaptodoset{chain sep=0pt} for global setting and \todo[chain sep=0pt] {note} for local setting.

..to each other

The width of the note block is \marginparwidth. The width where the broken line has slope is \marginparsep. These are the built-in dimensions. (So modify them with care!)

close.

other

2 chains

#### 4.3 Bias

Forced to the left

The tipping point between snapping to the left versus to the right is the center of the page, by default. You can change this by /snaptodo/chain bias=-99in. That way, all todo notes are forcedly snapped to the left hand side. Alternatively, by /snaptodo/call bias=99in, all todo notes are forcedly snapped to the right hand side.

Forced to the right

#### Rising

# 4.4 Rise

to leave

room.

If your document is really busy, e.g., like stress\_testing.tex, consider setting a positive /snaptodo/block rise\_\_\_\_ For instance, \todo[block rise=2em]{}. That way, a note will rise by that amount to leave more rooms for later notes. (But if there will be overlay, the notes automatically bump down.)

### 4.5 Alignment

The alignment of text is controlled by: margin block/.style={align=???}. The default setting is align=flush \std@leftright, which flushes the text toward the page edges. If you do align=flush \std@rightleft, the text will

# flush toward text body

be flushed toward the text body. Don't forget that you need \makeatletter and \makeatother to handel control sequences with the at character.

## 4.6 Font

