#### Computer arithmetic

Victor Eijkhout and Lars Koesterke

Spring 2021



### **Justification**

This short session will explain the basics of floating point arithmetic, mostly focusing on round-off and its influence on computations.



# 1 Numbers in scientific computing

- Integers: ..., -2, -1, 0, 1, 2, ...
- Rational numbers: 1/3,22/7: not often encountered
- Real numbers  $0, 1, -1.5, 2/3, \sqrt{2}, \log 10, \dots$
- Complex numbers  $1 + 2i, \sqrt{3} \sqrt{5}i, \dots$

Computers use a finite number of bits to represent numbers, so only a finite number of numbers can be represented, and no irrational numbers (even some rational numbers).



### First we dig into bits



# 2 Bit operations

	boolean	bitwise (C)	bitwise (Py)
and	& &	&	&
or			
not	!		~
xor		^	

#### Bit string operations:

left shift	<<
right shift	>>



# 3 Arithmetic with bit ops

• Left-shift is multiplication by 2:

• Extract bits:

(How does that last one work?)



## **Exercise 1: Bit operations**

Use bit operations to test whether a number is odd or even. Can you think of more than one way?



### **Integers**



## 4 Integers

Scientific computation mostly uses real numbers. Integers are mostly used for array indexing.

#### We look at

- 1. integers as supported by the hardware;
- 2. integers as they exist in programming languages;
- 3. (and not software-defined integers)



#### 5 In C and Fortran

#### C:

- A short int is at least 16 bits;
- An integer is at least 16 bits, but often 32 bits;
- A long integer is at least 32 bits, but often 64;
- A long long integer is at least 64 bits.

#### Fortran:

```
integer(2) :: i2
integer(4) :: i4
integer(8) :: i8
```

Specify the number of decimal digits with selected\_int\_kind(n).



#### **Exercise 2: Powers of two**

Print  $2^n$  for n = 0, ..., 31. There are at least two ways of generating these powers.

Also print the bit pattern. What is unexpected?



## **6 Negative integers**

#### Problem:

- How do we represent them?
- How do we do efficient arithmetic on them?

Define

rep: 
$$\mathbb{Z} \to 2^n$$

'representation of the number  $N \in \mathcal{Z}$  as bitstring of length n.'

int: 
$$2^n \to Z$$

'interpretation of the bitstring of length n as number  $N \in \mathbb{Z}$ '



## 7 Negative integers

More

Use of sign bit: typically first bit

$$s \mid i_1 \dots i_n$$

Simplest solution:

$$\begin{cases} n \ge 0 & \text{rep}(n) = 0, i_1, \dots i_{31} \\ n < 0 & \text{rep}(-n) = 1, i_1, \dots i_{31} \end{cases}$$



# 8 Sign bit

#### Interpretation

bitstring	000	 01 · · · 1	100	 11 · · · 1
as unsigned int	0	 $2^{31} - 1$	2 <sup>31</sup>	 2 <sup>32</sup> – 1
as naive signed	0	 $2^{31} - 1$	-0	 $-2^{31}+1$



# 9 Shifting

#### Interpret unsigned number n as n - B

bitstring	00 · · · 0	 01 · · · 1	100	 11 · · · 1
as unsigned int	0	 $2^{31} - 1$	2 <sup>31</sup>	 $2^{32}-1$
as shifted int	$-2^{31}$	 -1	0	 $2^{31} - 1$



# 10 2's Complement

Let m be a signed integer, then the 2's complement 'bit pattern' rep(m) is a non-negative integer defined as follows:

• If  $0 \le m \le 2^{31} - 1$ , the normal bit pattern for m is used, that is

$$0 \le m \le 2^{31} - 1 \Rightarrow \operatorname{rep}(m) = m.$$

• For  $-2^{31} \le n \le -1$ , n is represented by the bit pattern for  $2^{32} - |n|$ :

$$-2^{31} \le n \le -1 \Rightarrow \text{rep}(m) = 2^{32} - |n|.$$



# 11 2's complement visualized

bitstring	000	 01 · · · 1	100	 11 · · · 1
as unsigned int	0	 $2^{31} - 1$	2 <sup>31</sup>	 $2^{32}-1$
as 2's comp. integer	0	 $2^{31} - 1$	$-2^{31}$	 -1



## 12 Integer arithmetic

Problem: processor is very good at artithmetic on (unsigned) bit strings.

How does that translate to arithmetic on integers?

$$\operatorname{int}(\operatorname{rep}(x) * \operatorname{rep}(y)) \stackrel{?}{=} x * y$$



# 13 Addition in 2's complement

More

Add m + n, where m, n are representable:

$$0 \leq |m|, |n| < 2^{31}.$$

The easy case is 0 < m, n, as long as there is no overflow.




# 14 Addition in 2's complement (cont'd)

Case m > 0, n < 0, and m + n > 0. Then rep(m) = m and  $rep(n) = 2^{32} - |n|$ , so the unsigned addition becomes

$$\operatorname{rep}(m) + \operatorname{rep}(n) = m + (2^{32} - |n|) = 2^{32} + m - |n|.$$

Since m - |n| > 0, this result is  $> 2^{32}$ .



However, this is basically m+n with the overflow bit set.

# 15 Subtraction in 2's complement

#### Subtraction m-n:

- Case: m < n. Observe that -n has the bit pattern of  $2^{32} n$ . Also,  $m + (2^{32} n) = 2^{32} (n m)$  where  $0 < n m < 2^{31} 1$ , so  $2^{32} (n m)$  is the 2's complement bit pattern of m n.
- Case: m > n. The bit pattern for -n is  $2^{32} n$ , so m + (-n) as unsigned is  $m + 2^{32} n = 2^{32} + (m n)$ . Here m n > 0. The  $2^{32}$  is an overflow bit; ignore.



#### 16 Overflow

There is a limited number of bits, so numbers that are too large in absolute value can not be represented.

Overflow.

This is not a fatal error: your program continues with the wrong result.



## **Exercise 3: Integer overflow**

Investigate what happens when you perform an integer calculation that leads to overflow. What does your compiler say if you try to write down a nonrepresentible number explicitly, for instance in a declaration or assignment statement?

Language lawyer remark: signed integer overflow is undefined in C/C++.




### Floating point numbers



## 17 Floating point math is hard!

And the consequences if you get it wrong can be considerable.





## 18 Floating point numbers

Analogous to scientific notation  $x = 6.022 \cdot 10^{23}$ :

$$x = \pm \sum_{i=0}^{t-1} d_i \stackrel{-i}{\mathrm{fl}} \beta^e$$

- sign bit
- β is the base of the number system
- 0 ≤ d<sub>i</sub> ≤ β − 1 the digits of the mantissa: one digit before the radix point, so mantissa < β</li>
- $e \in [L, U]$  exponent, stored with bias: unsigned int where fl(L) = 0



### 19 Examples of floating point systems

	β	t	L	U
IEEE single (32 bit)	2	24	-126	127
IEEE double (64 bit)	2	53	-1022	1023
Old Cray 64bit	2	48	-16383	16384
IBM mainframe 32 bit	16	6	-64	63
packed decimal	10	50	-999	999

BCD is tricky: 3 decimal digits in 10 bits

(we will often use  $\beta=10$  in the examples, because it's easier to read for humans, but all practical computers use  $\beta=2$ )

Internal processing in 80 bit



#### 20 Limitations

Overflow: more than  $\beta(1-\beta^{-t+1})\beta^U$  or less than  $\beta(1-\beta^{-t+1})\beta^L$ 

Underflow: numbers less than  $\beta^{-t+1} \cdot \beta^L$ 



## **Exercise 4: Floating point overflow**

For real numbers 
$$x, y$$
, the quantity  $g = \sqrt{(x^2 + y^2)/2}$  satisfies

$$g \le \max\{|x|,|y|\}$$

so it is representable if x and y are. What can go wrong if you compute g using the above formula? Can you think of a better way?



## 21 The normalization problem

Do we allow

$$1.100 \cdot 10^0$$
,  $0.110 \cdot 10^1$ ,  $0.011 \cdot 10^2$ ?

This makes testing for equality hard.

Solution: normalized numbers have one nonzero before the radix point.



## 22 Normalized floating point numbers

Require first digit in the mantissa to be nonzero.

Equivalent: mantissa part  $1 \le x_m < \beta$ 

Unique representation for each number,

also: in binary this makes the first digit 1, so we don't need to store that

(do you see a problem?)

With normalized numbers, underflow threshold is  $1 \cdot \beta^L$ ; 'gradual underflow' possible, but usually not efficient.



# 23 IEEE 754, 32-bit pattern

sign	exponent	mantissa
р	$e=e_1\cdots e_8$	$s = s_1 \dots s_{23}$
31	30 · · · 23	220
±	2 <sup>e-127</sup>	$2^{-s_1} + \cdots + 2^{-s_{23}}$
	(except <i>e</i> = 0,255)	



## 24 IEEE 754, 32-bit, all cases

$(e_1 \cdots e_8)$	numerical value	range
$(0\cdots 0)=0$	$\pm 0.s_1 \cdots s_{23} \times 2^{-126}$	$s = 0 \cdots 01 \Rightarrow 2^{-23} \cdot 2^{-126} = 2^{-149} \approx 10^{-50}$
		$s = 1 \cdots 11 \Rightarrow (1 - 2^{-23}) \cdot 2^{-126}$
$(0\cdots 01)=1$	$\pm 1.s_1 \cdots s_{23} \times 2^{-126}$	
$(0\cdots 010)=2$	$\pm 1.s_1 \cdots s_{23} \times 2^{-125}$	
(011111111) = 127	$\pm 1.s_1 \cdots s_{23} \times 2^0$	$s = 0 \cdots 00 \Rightarrow 1 \cdot 2^0 = 1$
		$s = 0 \cdots 01 \Rightarrow 1 + 2^{-23} \cdot 2^0 = 1 + \varepsilon$
		$s = 1 \cdots 11 \Rightarrow (2 - 2^{-23}) \cdot 2^0 = 2 - \varepsilon$
(10000000) = 128	$\pm 1.s_1 \cdots s_{23} \times 2^1$	
(111111110) = 254	$\pm 1.s_1 \cdots s_{23} \times 2^{127}$	
(111111111) = 255	$s_1 \cdots s_{23} = 0 \Rightarrow \pm \infty$	
	$s_1\cdots s_{23}  eq 0 \Rightarrow  exttt{NaN}$	



#### **Exercise 5: Float vs Int**

Note that the exponent doesn't come at the end. This has an interesting consequence.

What is the interpretation of

 $0 \cdots 0111$ 

as int? What as float?

What is the largest integer that is representible as float?



## 25 Other precisions

- There is a 64-bit format, with 53 bits mantissa.
- IEEE envisioned a sliding scale of precisions: see Intel 80-bit registers
- Half precision, and recent invention bfloat16

FP32	s	8 bit exp			23 bit mantissa
FP16	s	5 bit exp	10 bit mantissa		
BF16	s	8 bit ex	7 bit mantissa		
					BFP10001



### Floating point math



## 26 Representation error

Error between number x and representation  $\tilde{x}$ :

absolute 
$$x - \tilde{x}$$
 or  $\left| x - \tilde{x} \right|$  relative  $\frac{x - \tilde{x}}{x}$  or  $\left| \frac{x - \tilde{x}}{x} \right|$ 

Equivalent: 
$$\tilde{x} = x \pm \varepsilon \Leftrightarrow |x - \tilde{x}| \le \varepsilon \Leftrightarrow \tilde{x} \in [x - \varepsilon, x + \varepsilon]$$
.

Also: 
$$\tilde{x} = x(1+\varepsilon)$$
 often shorthand for  $\left|\frac{\tilde{x}-x}{x}\right| \le \varepsilon$ 



# 27 Example

Decimal, t = 3 digit mantissa: let x = 1.256,  $\tilde{x}_{round} = 1.26$ ,  $\tilde{x}_{truncate} = 1.25$ 

Error in the 4th digit:  $|\epsilon| < \beta^{t-1}$  (this example had no exponent, how about if it does?)



### **Exercise 6: Round-off**

The number  $e \approx 2.72$ , the base for the natural logarithm, has various definitions. One of them is

$$e = \lim_{n \to \infty} (1 + 1/n)^n.$$

Write a single precision program that tries to compute e in this manner. Evaluate the expression for an upper bound  $n = 10^k$  with k = 1, ..., 10. Explain the output for large n. Comment on the behavior of the error.

Can you come up with a better way of computing *e*? How is this number actually computed?



## 28 Machine precision

Any real number can be represented to a certain precision:

$$\tilde{x}=x(1+\epsilon)$$
 where truncation:  $\epsilon=\beta^{-t+1}$  rounding:  $\epsilon=\frac{1}{2}\beta^{-t+1}$ 

This is called *machine precision*: maximum relative error.

32-bit single precision: 
$$mp \approx 10^{-7}$$
 64-bit double precision:  $mp \approx 10^{-16}$ 

Maximum attainable accuracy.

Another definition of machine precision: smallest number  $\epsilon$  such that  $1+\epsilon>1$ .



### **Exercise 7: Machine epsilon**

Write a small program that computes the machine epsilon for both single and double precision. Does it make any difference if you set the *compiler optimization levels* low or high?

(For C++ programmers: can you write a templated program that works for single and double precision?)



### 29 Addition

- 1. align exponents
- 2. add mantissas
- 3. adjust exponent to normalize

Example:  $1.00 + 2.00 \times 10^{-2} = 1.00 + .02 = 1.02$ . This is exact, but what happens with  $1.00 + 2.55 \times 10^{-2}$ ?

Example: 
$$5.00 \times 10^{1} + 5.04 = (5.00 + 0.504) \times 10^{1} \rightarrow 5.50 \times 10^{1}$$

Any error comes from limiting the mantissa: if x is the true sum and  $\tilde{x}$  the computed sum, then  $\tilde{x} = x(1+\epsilon)$  with  $|\epsilon| < 10^{-2}$ 



# 30 The 'correctly rounded arithmetic' model

Assumption (enforced by IEEE 754):

The numerical result of an operation is the rounding of the exactly computed result.

$$\mathrm{fl}(x_1\odot x_2)=(x_1\odot x_2)(1+\varepsilon)$$

where 
$$\odot = +, -, *, /$$

Note: this holds only for a single operation!



# 31 Guard digits

Correctly rounding is not trivial, especially for subtraction.

Example: 
$$t = 2, \beta = 10$$
:  $1.0 - 9.5 \times 10^{-1}$ , exact result  $0.05 = 5.0 \times 10^{-2}$ .

Simple approach:

$$1.0 - 9.5 \times 10^{-1} = 1.0 - 0.9 = 0.1 = 1.0 \times 10^{-1}$$

Using 'guard digit':

$$1.0 - 9.5 \times 10^{-1} = 1.0 - 0.95 = 0.05 = 5.0 \times 10^{-2}$$
, exact.

In general 3 extra bits needed.



#### 32 Fused Mul-Add instructions

(also 'fused multiply-accumulate')

$$c \leftarrow a * b + c$$

- Addition plus multiplication, but not independent
- Processors can have dedicated hardware for FMA (also IEEE 754-2008)
- Internally evaluated in higher precision: 80-bit.
- Very useful for certain linear algebra (which?) Not for other operations (examples?)



Computate 4+6+7 in one significant digit.

#### Evaluation left-to-right gives:

$$\begin{array}{c} \left(4\cdot10^0+6\cdot10^0\right)+7\cdot10^0 \Rightarrow 10\cdot10^0+7\cdot10^0 & \text{addition} \\ & \Rightarrow 1\cdot10^1+7\cdot10^0 & \text{rounding} \\ & \Rightarrow 1.0\cdot10^1+0.7\cdot10^1 & \text{using guard digit} \\ & \Rightarrow 1.7\cdot10^1 \\ & \Rightarrow 2\cdot10^1 & \text{rounding} \end{array}$$

On the other hand, evaluation right-to-left gives:

$$\begin{array}{lll} 4 \cdot 10^0 + \left(6 \cdot 10^0 + 7 \cdot 10^0\right) \Rightarrow 4 \cdot 10^0 + 13 \cdot 10^0 & \text{addition} \\ & \Rightarrow 4 \cdot 10^0 + 1 \cdot 10^1 & \text{rounding} \\ & \Rightarrow 0.4 \cdot 10^1 + 1.0 \cdot 10^1 & \text{using guard digit} \\ & \Rightarrow 1.4 \cdot 10^1 \\ & \Rightarrow 1 \cdot 10^1 & \text{rounding} \end{array}$$



## 34 Error propagation under addition

Let 
$$s = x_1 + x_2$$
, and  $x = \tilde{s} = \tilde{x}_1 + \tilde{x}_2$  with  $\tilde{x}_i = x_i(1 + \varepsilon_i)$ 

$$\tilde{x} = \tilde{s}(1 + \varepsilon_3)$$

$$= x_1(1 + \varepsilon_1)(1 + \varepsilon_3) + x_2(1 + \varepsilon_2)(1 + \varepsilon_3)$$

$$= x_1 + x_2 + x_1(\varepsilon_1 + \varepsilon_3) + x_2(\varepsilon_2 + \varepsilon_3)$$

$$\Rightarrow \tilde{x} = s(1 + 2\varepsilon)$$

⇒ errors are added

Assumptions: all  $\varepsilon_i$  approximately equal size and small;  $x_i > 0$ 



# 35 Multiplication

- 1. add exponents
- 2. multiply mantissas
- 3. adjust exponent

#### Example:

$$.123 \times .567 \times 10^{1} = .069741 \times 10^{1} \rightarrow .69741 \times 10^{0} \rightarrow .697 \times 10^{0}.$$

What happens with relative errors?



### **Examples**



### 36 Subtraction

Correct rounding only applies to a single operation.

Example:  $1.24 - 1.23 = 0.01 \rightarrow 1. \times 10^{-2}$ : result is exact, but only one significant digit.

What if 1.24 = fl(1.244) and 1.23 = fl(1.225)? Correct result  $1.9 \times 10^{-2}$ ; almost 100% error.

- Cancellation leads to loss of precision
- subsequent operations with this result are inaccurate
- this can not be fixed with guard digits and such
- ⇒ avoid subtracting numbers that are likely close.



### 37 ABC-formula

Example:  $ax^2 + bx + c = 0 \rightarrow x = \frac{-b \pm \sqrt{b^2 - 4ac}}{2a}$ 

suppose b > 0 and  $b^2 \gg 4ac$  then the '+' solution will be inaccurate

Better: compute  $x_- = \frac{-b - \sqrt{b^2 - 4ac}}{2a}$  and use  $x_+ \cdot x_- = -c/a$ .



### 38 Serious example

Evaluate  $\sum_{n=1}^{10000} \frac{1}{n^2} = 1.644834$ 

in 6 digits: machine precision is  $10^{-6}$  in single precision

First term is 1, so partial sums are  $\geq$  1, so  $1/n^2 < 10^{-6}$  gets ignored,  $\Rightarrow$  last 7000 terms (or more) are ignored,  $\Rightarrow$  sum is 1.644725: 4 correct digits

Solution: sum in reverse order; exact result in single precision Why? Consider ratio of two terms:

$$\frac{n^2}{(n-1)^2} = \frac{n^2}{n^2 - 2n + 1} = \frac{1}{1 - 2/n + 1/n^2} \approx 1 + \frac{2}{n}$$

with aligned exponents:

$$n-1$$
:  $.00\cdots0$  |  $10\cdots00$   
 $n$ :  $.00\cdots0$  |  $10\cdots01$  |  $0\cdots0$   
 $k = \log(n/2)$  positions

The last digit in the smaller number is not lost if  $n < 2/\epsilon$ 



## 39 Another serious example

Previous example was due to finite representation; this example is more due to algorithm itself.

Consider 
$$y_n = \int_0^1 \frac{x^n}{x-5} dx = \frac{1}{n} - 5y_{n-1}$$
 (monotonically decreasing)  $y_0 = \ln 6 - \ln 5$ .

#### In 3 decimal digits:

computation		correct result
$y_0 = \ln 6 - \ln 5 = .182   322 \times 10^1 \dots$		1.82
$y_1 = .900 \times 10^{-1}$		.884
$y_2 = .500 \times 10^{-1}$		.0580
$y_3 = .830 \times 10^{-1}$	going up?	.0431
$y_4 =165$	negative?	.0343

Reason? Define error as  $\tilde{y}_n = y_n + \varepsilon_n$ , then

$$\tilde{y}_n = 1/n - 5\tilde{y}_{n-1} = 1/n + 5n_{n-1} + 5\varepsilon_{n-1} = y_n + 5\varepsilon_{n-1}$$

so  $\varepsilon_n \geq 5\varepsilon_{n-1}$ : exponential growth.



## 40 Stability of linear system solving

Problem: solve Ax = b, where b inexact.

$$A(x + \Delta x) = b + \Delta b$$
.

Since Ax = b, we get  $A\Delta x = \Delta b$ . From this,

$$\left\{ \begin{array}{ll}
Ax &= b \\
\Delta x &= A^{-1} \Delta b
\end{array} \right\} \Rightarrow \left\{ \begin{array}{ll}
||A|| ||x|| &\geq ||b|| \\
||\Delta x|| &\leq ||A^{-1}|| ||\Delta b||
\end{array} \right.$$

$$\Rightarrow \frac{||\Delta x||}{||x||} \leq ||A|| ||A^{-1}|| \frac{||\Delta b||}{||b||}$$

'Condition number'. Attainable accuracy depends on matrix properties



# 41 Consequences of roundoff

Multiplication and addition are not associative: problems for parallel computations.

compute $a+b+c+d$		
sequential	parallel	
((a+b)+c)+d	(a+b)+(c+d)	

Operations with "same" outcomes are not equally stable: matrix inversion is unstable, elimination is stable



### **Exercise 8: Fixed-point iteration**

Consider the iteration

$$x_{n+1} = f(x_n) = \begin{cases} 2x_n & \text{if } 2x_n < 1 \\ 2x_n - 1 & \text{if } 2x_n \ge 1 \end{cases}$$

Does this function have a fixed point,  $x_0 \equiv f(x_0)$ , or is there a cycle  $x_1 = f(x_0)$ ,  $x_0 \equiv x_2 = f(x_1)$  et cetera?

Now code this function and see what happens with various starting points  $x_0$ . Can you explain this?



#### More



### **42 Complex numbers**

Two real numbers: real and imaginary part.

#### Storage:

- Store real/imaginary adjacent: easy to pass address of one number
- Store array of real, then array of imaginary. Better for stride 1 access if only real parts are needed. Other considerations.



## 43 Other arithmetic systems

Some compilers support higher precisions.

Arbitrary precision: GMPlib

Interval arithmetic

Half precision bfloat16

