Signals and Systems Using MATLAB

Luis F. Chaparro

Chapter 5 - Frequency Analysis The Fourier Transform

What is in this chapter?

- *From Fourier series to Fourier
 - transform
- Existence of Fourier

transform

- * Fourier and Laplace transforms
- * Time frequency relations and Fourier transform
- Spectral representation of periodic and aperiodic signals
 - * Modulation and signal

transmission

*Convolution and Filtering

3

From the Fourier Series to the Fourier Transform

Aperiodic signal x(t) is a periodic signal $\tilde{x}(t)$ with infinite period. From Fourier

series $\tilde{x}(t)$ and limiting process we obtain:

$$x(t) \Leftrightarrow X(\Omega)$$

where x(t) is transformed into $X(\Omega)$ in the frequency-domain by

Fourier transform:
$$X(\Omega) = \int_{-\infty}^{\infty} x(t)e^{-j\Omega t}dt$$

while $X(\Omega)$ is transformed into x(t) in the time-domain by

$$X(\Omega)$$
 is transformed into $x(t)$ in the time-domain by

Inverse Fourier Transform: $x(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} X(\Omega) e^{j\Omega t} d\Omega$

Aperiodic: $x(t) = \lim_{T_0 \to \infty} \tilde{x}(t)$ periodic of period T_0

Fourier Series:
$$\begin{split} \tilde{x}(t) &= \sum_{n=-\infty}^{\infty} X_n e^{jn\Omega_0 t} \qquad \Omega_0 = \frac{2\pi}{T_0} \\ X_n &= \frac{1}{T_0} \int_{-T_0/2}^{T_0/2} \tilde{x}(t) e^{-jn\Omega_0 t} dt \end{split}$$

$$T_0 J_{-T_0/2}$$

= $T_0 X_n$ where $\{\Omega_n = n\Omega_0\}$, harmonic frequencies and $\Delta\Omega$

Define $X(\Omega_n)=T_0X_n$ where $\{\Omega_n=n\Omega_0\}$, harmonic frequencies and $\Delta\Omega=2\pi/T_0=\Omega_0$ be frequency interval between harmonics then

$$\begin{split} \tilde{x}(t) &= \sum_{n=-\infty}^{\infty} \frac{X(\Omega_n)}{T_0} e^{j\Omega_n t} = \sum_n X(\Omega_n) e^{j\Omega_n t} \frac{\Delta\Omega}{2\pi} \\ X(\Omega_n) &= \int_{-T_0/2}^{T_0/2} \tilde{x}(t) e^{-j\Omega_n t} dt \end{split}$$

$$X(\Omega_n) = \int_{-T_0/2}^{T_0/2} \tilde{x}(t)e^{-j\Omega_n t} dt$$

As $T_0\to\infty$ then $\Delta\Omega\to d\Omega$, the line spectrum becomes denser, i.e. the lines in the line spectrum get closer, the sum becomes an integral, and $\Omega_n=n\Omega_0=n\Delta\Omega\to\Omega$ so that in the limit we obtain

Inverse FT:
$$x(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} X(\Omega) e^{j\Omega t} d\Omega$$

FT: $X(\Omega) = \int_{-\infty}^{\infty} x(t) e^{-j\Omega t} dt$

Existence of the Fourier Transform The Fourier transform

$$X(\Omega) = \int_{-\infty}^{\infty} x(t)e^{-j\Omega t}dt$$

of a signal x(t) exists (i.e., we can calculate its Fourier transform via this integral) provided

- x(t) is absolutely integrable or the area under |x(t)| is finite,
- x(t) has only a finite number of discontinuities as well as maxima and minima.

"It appears that almost nothing has a Fourier transform —nothing except practical communication signals. No signal amplitude goes to infinity and no signal lasts forever; therefore, no practical signal can have infinite area under it, and hence all have Fourier Transforms." (Prof. E. Craig)

Signals of practical interest have Fourier transforms and their spectra can be displayed using a $\mathbf{spectrum}$ analyzer

5

Fourier Transforms from the Laplace Transform

If ROC of $X(s) = \mathcal{L}[x(t)]$ contains the $j\Omega$ -axis, then

$$\begin{split} \mathcal{F}[x(t)] &= \mathcal{L}[x(t)]|_{s=j\Omega} = \int_{-\infty}^{\infty} x(t)e^{-j\Omega t}dt \\ &= X(s)|_{s=j\Omega} \end{split}$$

Rules of Thumb for Computing the Fourier Transform of a Signal $\boldsymbol{x}(t)$:

- If x(t) has a finite time support and in that support x(t) is finite, $\mathcal{F}[x(t)]$ exists
- If x(t) has a Laplace transform X(s) with ROC containing $j\Omega$ -axis, $X(\Omega) = X(s)|_{s=j\Omega}$.
- If x(t) is periodic its Fourier transform is obtained from its Fourier series using delta functions
- If x(t) is none of the above, if it has discontinuities (e.g., x(t) = u(t)), or it is
 has discontinuities and it is not finite energy (e.g., x(t) = cos(Ω₀t)u(t)) or it
 has possible discontinuities in the frequency domain even though it has finite
 energy (e.g., x(t) = sinc(t)) use properties of the Fourier transform.

Example Fourier transform using Laplace for

$$(a) \quad x_1(t) = u(t)$$

(b)
$$x_2(t) = e^{-2t}u(t)$$

$$(c) \quad x_3(t) = e^{-|t|}$$

(a) $\mathcal{L}[x_1(t)] = X_1(s) = 1/s$, ROC = $\{s = \sigma + j\Omega : \sigma > 0, -\infty < \Omega < \infty\}$, Laplace transform cannot be used to find $\mathcal{F}[x_1(t)]$

(b) $\mathcal{L}[x_2(t)] = X_2(s) = 1/(s+2)$, ROC = $\{s = \sigma + j\Omega : \sigma > -2, -\infty < \Omega < \infty\}$ containing $j\Omega$ -axis, then

$$X_2(\Omega) = \frac{1}{s+2} \mid_{s=j\Omega} = \frac{1}{j\Omega + 2}.$$

(c)
$$\mathcal{L}[x_3(t)] = X_3(s) = \frac{1}{s+1} + \frac{1}{-s+1} = \frac{2}{1-s^2}$$

 $\text{ROC} = \{s = \sigma + j\Omega: -1 < \sigma < 1, -\infty < \Omega < \infty\}$ containing $j\Omega\text{-axis, then}$

$$X_3(\Omega) = X_3(s)|_{s=j\Omega} = \frac{2}{1 - (j\Omega)^2} = \frac{2}{1 + \Omega^2}$$

7

Inverse Proportionality of Time and Frequency

The support of $X(\Omega)$ is inversely proportional to the support of x(t). If x(t) has a Fourier transform $X(\Omega)$ and $\alpha \neq 0$ is a real number, then $x(\alpha t)$ is

- is contracted $(\alpha > 1)$,
- is contracted and reflected ($\alpha < -1$),
- is expanded $(0 < \alpha < 1)$,
- is expanded and reflected $(-1 < \alpha < 0)$ or
- is reflected ($\alpha = -1$)

$$x(\alpha t) \quad \Leftrightarrow \quad \frac{1}{|\alpha|} X\left(\frac{\Omega}{\alpha}\right)$$

Frequency is inversely proportional to time:

- $x_1(t)=\delta(t),$ its support is only at t=0, $X_1(\Omega)=1, -\infty<\Omega<\infty$ with infinite support
- Opposite case: $x_2(t) = A, -\infty < t < \infty, X_2(\Omega) = 2\pi A \delta(\Omega)$ since the inverse Fourier transform is

$$\frac{1}{2\pi} \int_{-\infty}^{\infty} X_2(\Omega) e^{j\Omega t} d\Omega = \frac{1}{2\pi} \int_{-\infty}^{\infty} 2\pi A \delta(\Omega) e^{j\Omega t} d\Omega = A$$

 \bullet Transition $x_2(t)$ to $x_1(t)$: consider $x_3(t) = A[u(t+\tau/2) - u(t-\tau/2)]$ with

$$X_3(s) = \frac{A}{s} \left[e^{s\tau/2} - e^{-s\tau/2} \right]$$

so that

$$X_3(\Omega) = X(s)|_{s=j\Omega} = A\tau \frac{\sin(\Omega\tau/2)}{\Omega\tau/2}$$

 $A=1/\tau$ as $\tau\to 0$ the pulse $x_3(t)$ becomes $\delta(t)$ and $X_3(\Omega)$ becomes unity $\tau\to\infty,\;x_3(t)\quad\to\quad A\;X_3(\Omega)\quad\to\quad\delta(\Omega)$


NOTE: $x(t) \Leftrightarrow X(\Omega)$ means to x(t) in time domain corresponds a FT $X(\Omega)$ in the frequency domain. This is NOT an equality, far from it!

Example If x(t) = u(t) - u(t-1), find FT of $x_1(t) = x(2t)$

$$\begin{split} X(s) &= \frac{1-e^{-s}}{s} \qquad \text{ROC: whole s-plane} \\ X(\Omega) &= \frac{1-e^{-j\Omega}}{j\Omega} = \frac{e^{-j\Omega/2}(e^{j\Omega/2}-e^{-j\Omega/2})}{2j\Omega/2} = \frac{\sin(\Omega/2)}{\Omega/2}e^{-j\Omega/2}. \end{split}$$

$$\begin{array}{rcl} x_1(t) & = & x(2t) = u(2t) - u(2t-1) = u(t) - u(t-0.5) \\ X_1(\Omega) & = & \frac{1 - e^{-j\Omega/2}}{j\Omega} = \frac{e^{-j\Omega/4}(e^{j\Omega/4} - e^{-j\Omega/4})}{j\Omega} \\ & = & \frac{1}{2}\frac{\sin(\Omega/4)}{\Omega/4}e^{-j\Omega/4} = \frac{1}{2}X(\Omega/2) \end{array}$$

.



Duality
To the Fourier transform pair

$$x(t) \quad \Leftrightarrow \quad X(\Omega)$$

corresponds the following dual Fourier transform pair

$$X(t)$$
 \Leftrightarrow $2\pi x(-\Omega)$

Inverse Fourier transform

$$x(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} X(\rho) e^{j\rho t} d\rho$$

replace t by $-\Omega$ and multiply by 2π :


$$2\pi x (-\Omega) \quad = \quad \int_{-\infty}^{\infty} X(\rho) e^{-j\rho\Omega} d\rho = \int_{-\infty}^{\infty} X(t) e^{-j\Omega t} dt = \mathcal{F}[X(t)]$$

 ρ and t are dummy variables inside the integral

• Example: Fourier transform pair

$$\begin{array}{ccc} A\delta(t) & \Leftrightarrow & A \\ A & \Leftrightarrow & 2\pi A\delta(-\Omega) = 2\pi A\delta(\Omega) \end{array}$$

11



Application of duality to find Fourier transform of x(t)=10 sinc(0.5t). Notice that $X(\Omega)=2\pi x_1(\Omega)\approx 6.28x_1(\Omega)=63.8[u(\Omega+0.5)-u(\Omega-0.5)]$

Example Find the Fourier transform of $x(t) = A\cos(\Omega_0 t)$ using duality Consider the following Fourier pair

$$\delta(t-\rho_0) + \delta(t+\rho_0) \ \Leftrightarrow \ e^{-j\rho_0\Omega} + e^{j\rho_0\Omega} = 2\cos(\rho_0\Omega)$$

$$2\cos(\rho_0 t) \Leftrightarrow 2\pi[\delta(-\Omega-\rho_0)+\delta(-\Omega+\rho_0)] = 2\pi[\delta(\Omega+\rho_0)+\delta(\Omega-\rho_0)]$$

Replacing ρ_0 by Ω_0 and canceling the 2 in both sides we have

$$x(t) = \cos(\Omega_0 t) \quad \Leftrightarrow \quad X(\Omega) = \pi [\delta(\Omega + \Omega_0) + \delta(\Omega - \Omega_0)]$$

indicating that it only exists at $\pm\Omega_0$

 ${\bf Spectral~Representation}$ — Unification of the spectral representation of both periodic and aperiodic signals

Signal Modulation

Frequency shift: If $X(\Omega)$ is the Fourier transform of x(t), then we have the pair

$$x(t)e^{j\Omega_0t} \Leftrightarrow X(\Omega - \Omega_0)$$

Modulation: The Fourier transform of the modulated signal

 $x(t)\cos(\Omega_0 t)$

is given by

$$0.5\left[X(\Omega-\Omega_0)+X(\Omega+\Omega_0)\right]$$

i.e., $X(\Omega)$ is shifted to frequencies Ω_0 and $-\Omega_0$, and multiplied by 0.5.

Remarks

 \bullet Amplitude modulation: consists in multiplying message x(t) by a sinusoid of frequency higher than the maximum frequency of the incoming signal


Modulated signal
$$x(t)\cos(\Omega_0 t) = 0.5[x(t)e^{j\Omega_0 t} + x(t)e^{-j\Omega_0 t}]$$

 $\mathcal{F}[x(t)\cos(\Omega_0 t)] = 0.5[X(\Omega - \Omega_0) + X(\Omega + \Omega_o)]$

Modulation shifts the frequencies of x(t) to frequencies around $\pm\Omega_0$

- Modulation using a sine, instead of a cosine, changes the phase of the Fourier transform of the incoming signal besides performing the frequency shift
- \bullet According to eigenfunction property of LTI systems, modulation systems are not LTI.

13





2.
$$x_2(t) = 0.2[r(t+5) - 2r(t) + r(t+5)].$$

The modulated signals are

$$(i) \quad y_1(t) = x_1(t)\cos(10t) = e^{-|t|}\cos(10t), \qquad -\infty < t < \infty$$

$$(ii) \quad y_2(t) = x_2(t)\cos(10t) = 0.2[r(t+5) - 2r(t) + r(t+5)]\cos(10t)$$





Why Modulation? Modulation changes frequency content of a message from its baseband frequencies to higher frequencies making its transmission over the airwaves possible

Music (0 \leq f \leq 22KHz), and speech (100 \leq f \leq 5KHz) relatively low frequency signals requiring an antenna of length

$$\frac{\lambda}{4} = \frac{3\times 10^8}{4f} \quad \text{meters}$$
 if $f = 30 \text{KHz} \Rightarrow \text{ length of antenna } 2.5 \text{km} \approx 1.5 \text{miles}$

thus need to increase baseband frequencies.

15

Fourier Transform of Periodic Signals

A periodic signal x(t) of period T_0 :

$$x(t) = \sum_{k} X_k e^{jk\Omega_0 t} \qquad \Leftrightarrow \qquad X(\Omega) = \sum_{k} 2\pi X_k \delta(\Omega - k\Omega_0)$$

obtained by representing x(t) by its Fourier series.

Fourier series of x(t):

$$\begin{split} x(t) &= \sum_k X_k e^{jk\Omega_0 t} &\quad \Omega_0 = 2\pi/T_0 \\ X(\Omega) &= \sum_k \mathcal{F}[X_k e^{jk\Omega_0 t}] = \sum_k 2\pi X_k \delta(\Omega - k\Omega_0) \end{split}$$

Remarks

- $|X(\Omega)|$ vs $\Omega,$ the Fourier magnitude spectrum of periodic x(t) is analogous to its line spectrum
- ullet Direct computation

$$\mathcal{F}[\cos(\Omega_0 t)] \quad = \quad \mathcal{F}[0.5 e^{j\Omega_0 t} + 0.5 e^{-j\Omega_0 t}] = \pi \delta(\Omega - \Omega_0) + \pi \delta(\Omega + \Omega_0)$$

$$\begin{split} \mathcal{F}[\sin(\Omega_0 t)] &= & \mathcal{F}\left[\frac{0.5}{j}e^{j\Omega_0 t} - \frac{0.5}{j}e^{-j\Omega_0 t}\right] = \frac{\pi}{j}\delta(\Omega - \Omega_0) - \frac{\pi}{j}\delta(\Omega + \Omega_0) \\ &= & \pi e^{-j\pi/2}\delta(\Omega - \Omega_0) + \pi e^{j\pi/2}\delta(\Omega + \Omega_0) \end{split}$$

Parseval's Energy Conservation A finite-energy signal x(t), with Fourier trans-

form $X(\Omega)$, its energy is

$$E_x = \int_{-\infty}^{\infty} |x(t)|^2 dt = \frac{1}{2\pi} \int_{-\infty}^{\infty} |X(\Omega)|^2 d\Omega$$

 $|X(\Omega)|^2$ energy density : energy per frequency $|X(\Omega)|^2$ vs Ω : energy spectrum of x(t), energy of the signal distributed over frequency

Example Is $\delta(t)$ a finite energy signal?

Using Parseval's result: $\mathcal{F}\delta(t) = 1$ for all frequencies then its energy is infinite In time-domain:

$$\begin{split} p_{\Delta}(t) &= \frac{1}{\Delta}[u(t+\Delta/2) - u(t-\Delta/2)] \quad \Rightarrow \quad \delta(t) \text{as } \Delta \to 0, \text{ unit area} \\ p_{\Delta}^2(t) &= \frac{1}{\Delta^2}[u(t+\Delta/2) - u(t-\Delta/2)] \quad \Rightarrow \quad \delta^2(t) \text{as } \Delta \to 0, \text{ infinite area } 1/\Delta t = 0. \end{split}$$

 $\delta(t)$ is not finite energy

Symmetry of Spectral Representations

If $X(\Omega)$ is FT of real-valued signal x(t), periodic or aperiodic then

Magnitude |X(Ω)| even function of Ω:

$$|X(\Omega)| = |X(-\Omega)|$$

• Phase $\angle X(\Omega)$ odd function of Ω :

$$\angle X(\Omega) = -\angle X(-\Omega)$$

 $|X(\Omega)| vs \Omega$ Magnitude Spectrum $\angle X(\Omega)$ vs Ω Phase Spectrum

 $|X(\Omega)|^2 vs \Omega$ Energy/Power Spectrum.

Remarks

- $\bullet\,$ If signal is complex, the above symmetry will not hold
- Meaning of "negative" frequencies:
 - only positive frequencies exist and can be measured,
 - spectrum of a real signal requires negative frequencies

Example MATLAB to compute Fourier transform of

(a)
$$x(t) = u(t) - u(t-1)$$

$$(b) \quad x(t) = e^{-t}u(t)$$

For $x(t) = e^{-t}u(t)$

% Example 5.11

sym t x2=exp(-t)*heaviside(t);

X2=fourier(x2)

X2m=sqrt((real(X2))^2+(imag(X2))^2; % magnitude

X2p=imag(log(X2); % phase

Magnitude:

$$|X_2(\Omega)| = \sqrt{\Re[X_2(\Omega)]^2 + \Im[X_2(\Omega)]^2}.$$

$$\log(X_2(\Omega)) = \log(|X_2(\Omega)| e^{j \angle X_2(\Omega)} = \log(|X_2(\Omega)| + j \angle X_2(\Omega)$$

so that

$$\angle X_2(\Omega) = \mathcal{I}m[\log(X_2(\Omega))].$$

$$z(t) = x_1(t+0.5) = u(t+0.5) - u(t-0.5)$$

$$Z(\Omega) = \frac{\sin(\Omega/2)}{\Omega/2} \quad \text{real-valued}$$

$$\angle Z(\Omega) = \begin{cases} 0 & Z(\Omega) \ge 0 \\ \pm \pi & Z(\Omega) < 0 \end{cases}$$

$$z(t) = x_1(t+0.5) \Rightarrow Z(\Omega) = X_1(\Omega)e^{j0.5\Omega}$$

$$X_1(\Omega) = e^{-j0.5\Omega}Z(\Omega)$$

$$\angle X_1(\Omega) = e^{-j0.5\Omega}Z(\Omega)$$

$$\angle X_1(\Omega) = \angle Z(\Omega) - 0.5\Omega = \begin{cases} -0.5\Omega & Z(\Omega) \ge 0 \\ \pm \pi - 0.5\Omega & Z(\Omega) < 0 \end{cases}$$

Convolution and Filtering If x(t) (periodic or aperiodic) is input to a stable LTI

system with a frequency response $H(j\Omega) = \mathcal{F}[h(t)]$, h(t) impulse response of the system, the output of the LTI system is the convolution integral y(t) = (x*h)(t). with Fourier transform

$$Y(\Omega) = \mathcal{F}[(x*h)] = X(\Omega)\ H(j\Omega)$$

If x(t) is periodic the output is also periodic with Fourier transform

$$Y(\Omega) = \sum_{k=-\infty}^{\infty} 2\pi \ X_k \ H(jk \ \Omega_0) \delta(\Omega - k\Omega_0)$$

where X_k are the Fourier series coefficients of x(t) and Ω_0 its fundamental fre-

Eigenfunction property of LTI systems: Aperiodic signals

$$\begin{split} x(t) &=& \frac{1}{2\pi} \int_{-\infty}^{\infty} X(\Omega) e^{j\Omega t} d\Omega \Rightarrow \\ y(t) &=& \frac{1}{2\pi} \int_{-\infty}^{\infty} \left[X(\Omega) H(j\Omega) \right] e^{j\Omega t} d\Omega = \frac{1}{2\pi} \int_{-\infty}^{\infty} Y(\Omega) e^{j\Omega t} d\Omega \end{split}$$

Periodic signal of perio ${\cal T}_0$

$$X(\Omega) = \sum_{k=-\infty}^{\infty} 2\pi X_k \delta(\Omega - k\Omega_0) \ \Rightarrow \ Y(\Omega) \ = \ X(\Omega) H(j\Omega) = \sum_{k=-\infty}^{\infty} 2\pi X_k H(jk\Omega_0) \delta(\Omega - k\Omega_0)$$

output y(t) is periodic

$$y(t) = \sum_{k=-\infty}^{\infty} \underbrace{Y_k}_{X_k H(jk\Omega_0)} e^{jk\Omega_0 t}$$
 21


Basics of Filtering

• Filtering consists in getting rid of undesirable components of a signal, e.g., noise $\eta(t)$ is added to a desired signal x(t)

$$y(t) = x(t) + \eta(t)$$

Filter design: find H(s)=B(s)/A(s) satisfying certain specifications to get rid of noise.

 Frequency discriminating filters keep the frequency components of a signal in a certain frequency band and attenuate the rest.



FS coefficients:

$$X_0 = \frac{2}{\pi}$$

$$X_k = \frac{2(-1)^k}{\pi(1 - 4k^2)} \qquad k \neq$$

Filter out all harmonics and leave average component: ideal low-pass filter $\,$

$$H(j\Omega) = \left\{ \begin{array}{ll} A & -\Omega_0 < \Omega_c < \Omega_0, \ \ \text{where} \ \ \Omega_0 = 2\pi/T_0 = 2\pi \\ 0 & \text{otherwise} \end{array} \right.$$

22

Ideal Filters

• Low-pass filter (keeps low-frequency components)

$$|H_{lp}(j\Omega)| = \begin{cases} 1 & -\Omega_1 \le \Omega \le \Omega_1 \\ 0 & \text{otherwise} \end{cases}$$

$$\angle H_{lp}(j\Omega) = -\alpha\Omega$$

• Band-pass filter (keeps middle frequency components)

$$|H_{bp}(j\Omega)| = \left\{ \begin{array}{ll} 1 & \Omega_1 \leq \Omega \leq \Omega_2 & \text{and} & -\Omega_2 \leq \Omega \leq -\Omega_1 \\ 0 & \text{otherwise} \end{array} \right.$$

linear phase in the passband

 $\bullet\,$ High-pass filter (keeps high-frequency components)

$$|H_{hp}(j\Omega)| = \left\{ \begin{array}{ll} 1 & \Omega \geq \Omega_2 \quad \text{and} \quad \Omega \leq -\Omega_2 \\ 0 & \text{otherwise} \end{array} \right.$$

linear phase in the passband


 $\bullet\,$ Band-stop filter (attenuates middle frequency components)

$$|H_{bs}(j\Omega)| = 1 - |H_{bp}(j\Omega)|$$

• All-pass filter (keeps all frequency components, changes phase)

$$|H_{ap}(j\Omega)| = |H_{lp}(j\Omega)| + |H_{bp}(j\Omega)| + |H_{hp}(j\Omega)| = 1$$

• Multi-band filter: combination of the low-, band-, and high-pass filters



Example Gibb's phenomenon of Fourier series: ringing around discontinuities of periodic signals. Consider a periodic train of square pulses x(t) of period T_0 displaying discontinuities at $kT_0/2$, for $k=\pm 1, \pm 2, \cdots$. Show Gibb's phenomenon is due to ideal low-pass filtering. Ideal low-pass filter

$$H(j\Omega) = \left\{ \begin{array}{ll} 1 & -\Omega_c \leq \Omega \leq \Omega_c \\ 0 & \text{otherwise} \end{array} \right.$$

Periodic signal x(t), of fundamental frequency $\Omega_0 = 2\pi/T_0$, is


$$X(\Omega) = \mathcal{F}[x(t)] = \sum_{k=-\infty}^{\infty} 2\pi X_k \delta(\Omega - k\Omega_0)$$

Output of the filter:

$$\begin{array}{lcl} x_N(t) & = & \mathcal{F}^{-1}[X(\Omega)H(j\Omega)] = \mathcal{F}^{-1}\left[\sum_{k=-N}^N 2\pi X_k\delta(\Omega-k\Omega_0)\right] \\ \\ & = & [x*h](t) & \text{cutoff frequency:} & N\Omega_0 < \Omega_c < (N+1)\Omega_0 \end{array}$$

convolution around the discontinuities of x(t) causes ringing before and after them, independent of N 24

Example Obtain different filters from an RLC circuit by choosing different outputs. Let R= 1 Ω , L = 1 H, and C= 1 F, and IC=0



Low-pass Filter: Output $V_c(s)$

$$H_{lp}(s) = \frac{V_C(s)}{V_i(s)} = \frac{1}{s^2 + s + 1}$$

- input a de source (frequency $\Omega=0),$ inductor short circuit, capacitor open circuit, so $V_c(s)=V_i(s)$
- input of very high frequency, $\Omega \to \infty,$ inductor open circuit, capacitor short circuit $V_c(s) = V_i(s) = 0$

High-pass Filter: Output $V_L(s)$

$$H_{hp}(s)=\frac{V_L(s)}{V_i(s)}=\frac{s^2}{s^2+s+1}$$

- $\bullet\,$ dc input (frequency zero), inductor is short circuit $V_L(s)=0$
- • input of very high frequency, $\Omega \to \infty,$ inductor is open circuit $V_L(s) = V_i(s)$

Band-pass Filter: Output $V_R(s)$

$$H_{bp}(s) = \frac{V_R(s)}{V_i(s)} = \frac{s}{s^2 + s + 1}$$

- For zero frequency, capacitor is open circuit so voltage across the resistor is zero.
- $\bullet\,$ For very high frequency, inductor is open circuit, voltage across resistor is zero
- \bullet For some middle frequency, serial LC combination resonates (zero impedance) maximum voltage across resistor

Band-stop Filter: Output voltage across inductor and the capacitor

$$H_{bs}(s) = \frac{s^2 + 1}{s^2 + s + 1}$$

- At the resonance frequency $\Omega_r=1$ the impedance of the LC connection is zero, so the output voltage is zero

26


Frequency Response from Poles and Zeros

For a filter with transfer function

$$H(s) = \frac{\prod_i (s-z_i)}{\prod_k (s-p_k)}$$
 where z_i, p_k are zeros and poles of $H(s)$

with vectors $\vec{Z}_i(\Omega)$ and $\vec{P}_k(\Omega)$, going from each of the zeros and poles to the frequency at which we are computing the magnitude and phase response in the $j\Omega$ -axis, gives

$$\begin{split} H(j\Omega) &= H(s)|_{s=j\Omega} &= \underbrace{\frac{\prod_i \vec{Z}_i(\Omega)}{\prod_k \vec{P}_k(\Omega)}}_{\prod_k |\vec{P}_k(\Omega)|} \\ &= \underbrace{\frac{\prod_i |\vec{Z}_i(\Omega)|}{\prod_k |\vec{P}_k(\Omega)|}}_{|H(j\Omega)|} \underbrace{e^{j\left[\sum_i \angle(\vec{Z}_i(\Omega)) - \sum_k \angle(\vec{P}_k(\Omega)\right]}}_{e^{j\angle H(j\Omega)}} \end{split}$$



Example RC circuit in series with voltage source $v_i(t)$. Choose the output to obtain low-pass and high-pass filters and use the poles and zeros of the transfer functions to determine their frequency responses. Let $R=1~\Omega,~C=1~\mathrm{F}$ and the initial conditions be zero.

Low-pass filter:

$$\begin{array}{lcl} H(s) & = & \frac{V_C(s)}{V_i(s)} = \frac{1/Cs}{R+1/Cs} = \frac{1}{1+s} \\ H(j\Omega) & = & \frac{1}{1+j\Omega} = \frac{1}{\vec{P}(\Omega)} \end{array}$$

Geometrically

$$\begin{split} \Omega &= 0 \qquad \vec{P}(0) &= 1e^{j0}H(j0) = 1e^{j0} \\ \Omega &= 1 \qquad \vec{P}(1) = \sqrt{2}e^{j\pi/4} \ \Rightarrow \ H(j1) = 0.707e^{-j\pi/4} \\ \Omega &= \infty \qquad \vec{P}(\infty) = \infty \ e^{j\pi/2} \ \Rightarrow \ H(j\infty) = 0e^{-j\pi/2} \end{split}$$

High-pass filter:

$$\begin{split} H(s) &=& \frac{V_r(s)}{V_s(s)} = \frac{CRs}{CRs+1} = \frac{s}{s+1} \\ H(j\Omega) &=& \frac{j\Omega}{1+j\Omega} = \frac{\vec{Z}(\Omega)}{\vec{P}(\Omega)} \end{split}$$

$$\begin{split} \Omega &= 0 \qquad \vec{P}(0) = 1e^{j0} \qquad \vec{Z}(0) = 0e^{j\pi/2} \qquad H(j0) = \frac{\vec{Z}(0)}{\vec{P}(0)} = 0e^{j\pi/2} \\ \Omega &= 1 \qquad \vec{P}(1) = \sqrt{2}e^{j\pi/4} \qquad \vec{Z}(1) = 1e^{j\pi/2} \qquad H(j1) = \frac{\vec{Z}(1)}{\vec{P}(1)} = 0.707e^{j\pi/4} \\ \Omega &= \infty \qquad \vec{P}(\infty) = \infty \ e^{j\pi/2} \qquad \vec{Z}(\infty) = \infty \ e^{j\pi/2} \qquad H(j\infty) = \frac{\vec{Z}(\infty)}{\vec{P}(\infty)} = 1e^{j0} \end{split}$$

28

Remarks

- Poles create "hills" at frequencies in the $j\Omega$ -axis in front of their imaginary
- \bullet Zeros create "valleys" at the frequencies in the $j\Omega\text{-axis}$ in front of their imaginary parts

Example Use MATLAB to find and plot the poles and zeros and the corresponding magnitude and phase frequency responses of:

- (a) A second-order band-pass and a high-pass filters realized using an RLC se-
- ries connection (R=1, L=1, C=1) (b) An all-pass filter with a transfer function

$$H(s) = \frac{s^2 - 2.5s + 1}{s^2 + 2.5s + 1}$$

(a) From previous example,

$$H_{bp}(s) = \frac{s}{s^2 + s + 1}$$

 $H_{hp}(s) = \frac{s^2}{s^2 + s + 1}$

XXXXXXXXXXXXXXXXXXXXXXXXXXX

% Example 5.18 --- Frequency response

% Example 5.18 --- Frequency response

WXXXXXXXXXXXXXXXXXXXXXXXXX

n=[0 1 0]; % numerator coefficients -- bandpass

% n=[1 0 0]; % numerator coefficients -- highpass


d=[1 1 1]; % denominator coefficients

wmax=10; % maximum frequency

(w,Hm,Ha]=freqresp_s(n,d,max); % frequency response

splane(n,d) % plotting of poles and zeros

function [w,Hm,Ha]=freqresp_s(b,a,wmax)
w=0:0.01:wmax; H=freqs(b,a,w); Hm=abs(H); % magnitude Ha=angle(H)*180/pi; % phase in degrees



 $\begin{tabular}{ll} \textbf{The Spectrum Analyzer-} Device that measures the spectral characteristics of a signal \\ \end{tabular}$

• Implemented as a bank of narrow-band band-pass filters with fixed band-widths covering the desired frequencies (used for the audio range of the spectrum) Input x(t), output of one of bandpass filter with very narrow bandwidth $\Delta\Omega$:


$$\begin{split} y(t) &= \frac{1}{2\pi} \int_{\Omega_0 - 0.5 \Delta \Omega}^{\Omega_0 + 0.5 \Delta \Omega} X(\Omega) e^{j\Omega t} d\Omega \\ &\approx \frac{1}{2\pi} \Delta \Omega \ X(\Omega_0) e^{j\Omega_0 t} \end{split}$$

mean square of this signal

$$\frac{1}{T}\int_{T}|y(t)|^{2}dt=\left(\frac{\Delta\Omega}{2\pi}\right)^{2}\;|X(\Omega_{0})|^{2}$$

proportional to the power or the energy of the signal in $\Omega_0\pm\Delta\Omega$. A similar computation can be done at each of the frequencies of the input signal

 $\bullet\,$ Radio frequency spectrum analyzers resemble an AM demodulator



What have we accomplished?

- * Unification of frequency representation of periodic and aperiodic signals
- * Frequency response of LTI systems
- Duality in time and frequency
- Convolution and Filtering
 - **Connection of Fourier series and Laplace
 - transform
 **Inverse time frequency
 relation

Where do we go from here?

- *Application of Laplace analysis and transient response
- * Application of Fourier analysis and steady state response
 - * Filter design
- * Application of time-frequency relation in sampling theory