

Enable Azure Cost Management (ACM)



Type:	4. Instruction	Version:	1.2
Status:	Final	Effective:	12/15/2023

1. Purpose

To provide instructions to enable Azure Cost Management in an end user tenant.

Note: For CSP subscription, Azure Cost Management can only be enabled but the Direct/Indirect Provider.

2. Table of Contents

1. Purpose.....	1
2. Table of Contents.....	1
3. Notes.....	1
4. End User Permissions	1
5. Instructions.....	2
6. Associated Documents	4
7. Document Approval	4
8. Document Revision History	4
9. Appendix A – Contributor without ACM	5
10. Appendix B – Reader without ACM.....	6

3. Notes

- The user who enables ACM must be a member of the AdminAgents group.
- ACM may only be enabled for Azure Plan subscriptions. It is not available for legacy subscriptions. Legacy subscriptions should be converted to Azure Plan.
- ACM is enabled for all Azure Plan subscriptions in a tenant. Not per subscription.
- End user customers will be able to report on one subscription at a time. In CSP, there is not an ability to report on all subscriptions in ACM at the same time. There are instructions referencing reporting on all subscriptions simultaneously; however, they apply to non-CSP subscriptions.

4. End User Permissions

Users with the following permissions to a subscription will have access to ACM.

- Owner / Contributor / Reader
- Billing Reader
- Cost Management Reader / Cost Management Contributor
- Direct/Indirect Provider Admin Agents

Azure AD Global Administrators also have the ability to give themselves these permissions using elevated GA permissions.

Enable Azure Cost Management (ACM)




Type:	4. Instruction	Version:	1.2
Status:	Final	Effective:	12/15/2023

If the reseller/end user does not want a Contributor or Reader to have access to ACM data, they may create a custom role. A custom Owner role would not work as intended since the custom Owner could give themselves the regular Owner role and have access to ACM.


See also: [Understand and work with Cost Management scopes - Microsoft Cost Management](#)

5. Instructions


- Access the TD Synnex [Azure Portal](#) for the appropriate management tenant.
IMPORTANT: Do not access an end user tenant. This must be done from the PAC management tenant.
- Login using credentials for the appropriate PAC.
- In the menu, click on Cost Management + Billing.



- In the new menu, click on Customers.



- Search for the customer by tenant name




Note: The name in the search must match the billing name from Partner Center. If the customer does not appear, verify you have the correct spelling and that the customer has an Azure Plan subscription.


Enable Azure Cost Management (ACM)




Type:	4. Instruction	Version:	1.2
Status:	Final	Effective:	12/15/2023




- Click on the Customer name.



- In the menu, click on Policies



- Select Yes then click Save



- ACM is not enabled for the tenant. The end user may need to log out and close browsers to get access.

Enable Azure Cost Management (ACM)



Type:	4. Instruction	Version:	1.2
Status:	Final	Effective:	12/15/2023

6. Associated Documents

- [Get started with Cost Management for partners - Microsoft Cost Management](#)
- [Cost Management + Billing - Microsoft Cost Management](#)
- [Understand and work with Cost Management scopes - Microsoft Cost Management](#)
- [Azure custom roles - Azure RBAC](#)

7. Document Approval

This document has been approved by:

- Manager, Cloud Sales Engineering

8. Document Revision History

Number	Effective Date	Revision History	Author
1.0	2/16/2023	Initial Draft	David Bloom
1.1	5/5/2023	Added note about custom roles	David Bloom
1.2	12/15/2023	Added Appendix with custom roles	David Bloom

9. Appendix A – Contributor without ACM

```
{
  "id": "/providers/Microsoft.Authorization/roleDefinitions/12345678-9012-3456-7890-123456789012",
  "properties": {
    "roleName": "Contributor without ACM",
    "description": "Grants all the permissions of Contributor except access to Cost Management.",
    "assignableScopes": [
      "/"
    ],
    "permissions": [
      {
        "actions": [
          "*"
        ],
        "notActions": [
          "Microsoft.Authorization/*/Delete",
          "Microsoft.Authorization/*/Write",
          "Microsoft.Authorization/elevateAccess/Action",
          "Microsoft.Blueprint/blueprintAssignments/write",
          "Microsoft.Blueprint/blueprintAssignments/delete",
          "Microsoft.Compute/galleries/share/action",
          "Microsoft.Purview/consents/write",
          "Microsoft.Purview/consents/delete",
          "Microsoft.CostManagement/*"
        ],
        "dataActions": [],
        "notDataActions": []
      }
    ]
  }
}
```

10. Appendix B – Reader without ACM

```
{
  "id": "/providers/Microsoft.Authorization/roleDefinitions/12345678-9012-3456-7890-123456789012",
  "properties": {
    "roleName": "Reader without ACM",
    "description": " Grants all the permissions of Reader except access to Cost Management.",
    "assignableScopes": [
      "/"
    ],
    "permissions": [
      {
        "actions": [
          "**/read"
        ],
        "notActions": [
          "Microsoft.CostManagement/**"
        ],
        "dataActions": [],
        "notDataActions": []
      }
    ]
  }
}
```