

PDTool Archive Module User Guide

An Open Source Asset for use with TIBCO® Data Virtualization

TIBCO Software empowers executives, developers, and business users with Fast Data solutions that make the right data available in real time for faster answers, better decisions, and smarter action. Over the past 15 years, thousands of businesses across the globe have relied on TIBCO technology to integrate their applications and ecosystems, analyze their data, and create real-time solutions. Learn how TIBCO turns data—big or small—into differentiation at www.tibco.com.

Project Name	AS Assets PDTool (Promotion and Deployment Tool)
Document Location	This document is only valid on the day it was printed. The source of the document will be found in the PDTool and PDToolRelease folder (https://github.com/TIBCOSoftware)
Purpose	User's Guide



www.tibco.com

Global Headquarters 3303 Hillview Avenue Palo Alto, CA 94304 **Tel:** +1 650-846-1000 +1 800-420-8450

Fax: +1 650-846-1005

Revision History

Version	Date	Author	Comments
1.0	6/9/2011	Mike Tinius	Initial revision for Archive User Guide
1.0.1	8/1/2011	Mike Tinius	Revision due to Architecture changes.
2.0	7/13/2012	Alex Dedov	Document enhancements to support full set of command-line options
2.1	8/24/2012	Mike Tinius	Updated the archive attribute options.
3.0	8/21/2013	Mike Tinius	Updated docs to Cisco format
3.1	1/31/2014	Mike Tinius	Updated documentation for Includesourceinfo attribute and the use of encrypt flag and https. See PDTool Installation Guide for https configuration.
3.2	2/18/2014	Mike Tinius	Added section on debugging. Fixed some of the options that were upper case and made them lower case. Prepare docs for open source.
3.3	3/24/2014	Mike Tinius	Changed references of XML namespace to www.dvbu.cisco.com
3.4	11/17/2014	Mike Tinius	Updated license.
3.5	03/04/05	Mike Tinius	Updated table of contents to include methods and updated docs to Cisco format.
4.0	12/14/2017	Mike Tinius	Initial revision with Tibco

Related Documents

Name	Author
PDTool User's Guide.pdf	Mike Tinius
AdministrationGuide.pdf	TIBCO Software

Supported Versions

Name	Version	
TIBCO® Data Virtualization	7.0.4 or later	

Table of Contents

1	Introduction	4
	Purpose	4
	Audience	
	References	4
2	Archive Module Definition	5
	Method Definitions and Signatures	5
	1. pkg_import	5
	2. pkg_export	
	3. backup_export4. backup_import	
3	Archive Module XML Configuration	7
•	Description of the Module XML	
	Attributes of Interest	
	Complete List of Attributes	13
	Attribute Value Restrictions	17
4	How To Execute	18
	Script Execution	18
	Ant Execution	19
5	PDTool Examples	22
	Scenario 1 – Export resources from a DV instance	22
	Scenario 2 – Import a DV Archive (.car)	23
6	Debugging	24
7	Exceptions	25
8	Conclusion	26
	Concluding Remarks	26
	How you can help!	

1 Introduction

Purpose

The purpose of the Archive User Guide is to demonstrate how to effectively use the Archive Module for importing, exporting, backing up and restoring Data Virtualization (DV) resources. The scripts in this module will interact directly with a Data Virtualization (DV) server. There is no version control associated with this module. For version control, review the VCS Module documentation. This will module will focus on exporting and importing resources via Data Virtualization (DV) Archive files (.car). It will also show how to use backup and restore features which also use the DV Archive files. The Archive Module is completely shell/batch script based.

Audience

This document is intended to provide guidance for the following users:

- Architects
- Developers
- Administrators
- Operations personnel

References

Product references are shown below. Any references to CIS or DV refer to the current TIBCO® Data Virtualization.

- TIBCO® Data Virtualization was formerly known as
 - Cisco Data Virtualization (DV)
 - Composite Information Server (CIS)

2 Archive Module Definition

Method Definitions and Signatures

1. pkg_import

Import a CAR file into a local or remote DV instance with options.

```
@param serverId - target server id from servers config xml
@param archiveIds - list of comma separate archive Ids containing the
archive instructions
@param pathToArchiveXML - path to the archive module xml
@param pathToServersXML - path to the server values xml
@throws CompositeException

public void pkg_import(String serverId, String archiveIds, String
pathToArchiveXML, String pathToServersXML) throws CompositeException
```

2. pkg_export

Export a CAR file from a local or remote DV instance by designating a list of resources to export.

```
@param serverId - target server id from servers config xml
@param archiveIds - list of comma separate archive Ids containing the
archive instructions
@param pathToArchiveXML - path to the archive module xml
@param pathToServersXML - path to the server values xml
@throws CompositeException

public void pkg_export(String serverId, String archiveIds, String
pathToArchiveXML, String pathToServersXML) throws CompositeException]
```

3. backup_export

Perform a complete backup of a local or remote DV server instance.

```
Restore a full server backup from a backup car file

@param serverId - target server id from servers config xml

@param archiveIds - list of comma separated archive Ids containing the archive instructions

@param pathToArchiveXML - path to the archive module xml

@param pathToServersXML - path to the server values xml
```

@throws CompositeException
public void backup_export(String serverId, String archiveIds, String
pathToArchiveXML, String pathToServersXML) throws CompositeException

4. backup_import

Perform a complete restore of a local or remote DV server instance.

```
Create a full server backup of a DV instance to a car file

@param serverId - target server id from servers config xml

@param archiveIds - list of comma separated archive Ids containing the archive instructions

@param pathToArchiveXML - path to the archive module xml

@param pathToServersXML - path to the server values xml

@throws CompositeException

public void backup_import(String serverId, String archiveIds, String pathToArchiveXML, String pathToServersXML) throws CompositeException
```

General Notes:

The arguments pathToArchiveXML and pathToServersXML will be located in PDTool/resources/modules. The value passed into the methods will be the fully qualified path. The paths get resolved when executing the property file and evaluating the \$MODULE_HOME variable.

3 Archive Module XML Configuration

A full description of the PDToolModule XML Schema can be found by reviewing /docs/PDToolModules.xsd.html.

Description of the Module XML

The Archive Module performs various DV archiving operations with CAR (DV Archive) files such as backup, restore, import and export.

```
<?xml version="1.0"?>
<pl:ArchiveModule xmlns:p1="http://www.dvbu.cisco.com/ps/deploytool/modules">
   <!--Element archive is optional, maxOccurs=unbounded-->
   <archive>
        <id>example id</id>
        <archiveMethod>CAR</archiveMethod>
        <archiveFileName>$PROJECT HOME/test01.car</archiveFileName>
       <!--Element includeDependencies is optional-->
       <includeDependencies>false</includeDependencies>
       <!--Element resources is optional-->
        <resources>
            <!-- 'Choice' block, maxOccurs=unbounded-->
            <export>/shared/examples/CompositeView</export>
            <relocate>
                <oldPath>/shared/examples/CompositeView</oldPath>
                <newPath>/shared/examples/newdir/CompositeView</newPath>
            </relocate>
            <rebind>
                <oldPath>/shared/examples/ViewSales</oldPath>
                <newPath>/shared/examples/newds/ViewSales</newPath>
            </rebind>
        </resources>
        <!--Element encrypt is optional-->
        <encrypt>false</encrypt>
        <!--Element description is optional-->
        <description>Export CompositeView</description>
        <!--Element includeaccess is optional-->
        <includeaccess>true</includeaccess>
        <!--Element includeallusers is optional-->
        <includeallusers>false</includeallusers>
        <!--Element includerequiredusers is optional-->
       <includerequiredusers>false</includerequiredusers>
       <!--Element includecaching is optional-->
       <includecaching>true</includecaching>
       <!--Element includejars is optional-->
       <includejars>true</includejars>
       <!--Element includesourceinfo is optional-->
       <includesourceinfo>false</includesourceinfo>
       <!--Element includestatistics is optional-->
       <includestatistics>false</includestatistics>
       <!--Element messagesonly is optional-->
        <messagesonly>false</messagesonly>
        <!--Element overridelocks is optional-->
        <overridelocks>false</overridelocks>
        <!--Element overwrite is optional-->
        <overwrite>false</overwrite>
```

```
<!--Element pkgName is optional-->
       <pkgName>Composite Server Archive File via PDTool</pkgName>
       <!--Element printinfo is optional-->
       <printinfo>false</printinfo>
       <!--Element printroots is optional-->
       <printroots>false</printroots>
       <!--Element printusers is optional-->
       <printusers>false</printusers>
       <!--Element printcontents is optional-->
       <printcontents>false</printcontents>
       <!--Element printreferences is optional-->
       <printreferences>false</printreferences>
       <!--Element setAttributes is optional-->
       <setAttributes>
           <!--Element resourceAttribute, maxOccurs=unbounded-->
           <resourceAttribute>
               <resourcePath>/shared/examples/ds inventory</resourcePath>
               <re>ourceType>DATA SOURCE</resourceType>
               <attribute>annotation</attribute>
               <value>sample data source</value>
           </resourceAttribute>
       </setAttributes>
       <!--Element users is optional-->
           <!--'Choice' block is optional, maxOccurs=unbounded-->
           <!--Element export, maxOccurs=unbounded-->
           <export>
               <domain>composite</domain>
               <!--Element group is optional-->
               <group>group1</group>
           </export>
           <export>
               <domain>composite</domain>
               <!--Element user is optional-->
               <user>user1</user>
           </export>
           <import>merge</import>
        </users>
   </archive>
</pl></re>
```

Attributes of Interest

id – a uniquely named value identifying an archive operation.

archiveMethod – export archive file (CAR).

archiveFileName – full path to the archive file name and location. The value may contain variables defined via deploy.dp, JAVA Environment or System Environment. A variable is defined with the format of VAR=myvalue and referenced as \$VAR. For example the entry archiveFileName may look like this:

<archiveFileName>\$PROJECT HOME/resources/carfiles/test00.car</archiveFileName>

includeDependencies - (true/false) Include resource dependencies on export.

resources

export – unbound list of DV resources to export

relocate

oldPath - the old path to the resource

newPath – the new path to the resource

rebind

oldPath – the old path to the resource to be rebound

newPath – the new path the resource to be rebound

encrypt – (true/false) Encrypts communication between the command line and DV using SSL sent over the dedicated HTTPS port. The PDTool Installation Guide provides setup information for both PDTool and DV. For additional information, see DV Administration guide chapter 11 for complete details.

description – Package description of the archive file. Notation appears when DV Studio is used to import the CAR.

includeaccess - (true/false)

- ON IMPORT: The -includeaccess option must be used if you want to preserve ownership and privilege information. This option is ignored if you are not logged in as a member of the admin group.
- ON EXPORT: Includes the current user access controls (privilege specifications) on the
 resources in the export file. Default setting does NOT include access control even when
 exported by an administrator. An error can occur if this option is used and the exporting
 user is not a member of the admin group with the Read All Resources right and include
 access on export.

includerequiredusers – (true/false)

ON PACKAGE EXPORT: Exports all domains, groups, and users to the export file.
 Requires the Read All Users right.

includecaching - (true/false)

- ON IMPORT: Caching configuration is imported by default. The -nocaching option must be used if you want to ignore cache configurations.
- ON EXPORT: Includes the details of caching on views and procedures in the export file.
 This option must be specified to include cached data from materialized views, or configurations that include scheduling for cache refreshes.

includejars - (true/false)

- ON PACKAGE EXPORT: Exports any included custom Java procedure data source's JAR.
- ON BACKUP EXPORT: Can suppress export of custom Java procedure data source JARs.
- ON PACKAGE IMPORT: Can suppress import of any custom Java procedure data source's JAR within the CAR file.

includesourceinfo - (true/false)

- ON PACKAGE EXPORT: Data source connection details such as user name, password, host name, and port are not included by default. When the Includesourceinfo flag is set to true, (equivalent to the -includesourceinfo flag for pkg_export) then include the data source connection details. If passwords are included, they are encrypted. If the Includesourceinfo flag is set to false, (equivalent to the -nosourceinfo flag for pkg_export), then the data source connection information is not included. The minimum requirement is for Hotfix 7.0.00.00 or higher for pkg_import -nosourceinfo to work properly.
- ON PACKAGE IMPORT: An overwrite safeguard. Suppresses import of the following preexisting connection attributes when an otherwise identical resource is already present at the target: Driver, ConnectionURL, Port, Database Name, Login, Password, and Pass-through Login.

Supports re-import without need for explicit "-set" options and without altering original data source attributes.

includestatistics - (true/false)

 ON PACKAGE EXPORT and BACKUP EXPORT: Includes any known resource cardinality statistics about data source table boundaries, column boundaries, and configurations when statistics gathering is enabled.

messagesonly – (true/false)

• ON PACKAGE IMPORT ONLY: Prints the messages generated in a package import to a log4j file without actually performing the import.

overridelocks - (true/false)

• ON PACKAGE IMPORT ONLY: Overrides Studio locks when importing resources from a CAR file.

overwrite - (true/false)

- ON BACKUP IMPORT: This option does a destructive import clearing all resources prior to importing the backup CAR. Using the backup_import utility with the -overwrite option ensures that DV matches the contents of the imported CAR file.
- ON PACKAGE IMPORT: Use of the -overwrite option ensures that DV will exactly match the directories present in the CAR file. The -overwrite option clears targeted folder directories before copying the CAR file contents to those cleared directories. The pkg_import utility clears only those folders that have representative resources in the CAR file from those directories. DV directories that do not have representative resources in the CAR file remain untouched even if the -overwrite option is specified.

pkgName - Names an attribute in the contents.xml within the exported backup file.

printinfo – (true/false) The "printinfo" option causes the archive file to be examined and for information about it to be printed to the display. The archive file is NOT imported when this option is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO.

printroots – (true/false) Prints the new paths to the imported resources. The archive file is NOT imported when this option is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO.

printusers – (true/false) Prints the user names of the owners of the imported resources and their associated user groups. The archive file is NOT imported when this option is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO.

printcontents – (true/false) This option disables actual import, and prints properties of the CAR file to the command window. The archive file is NOT imported when this option is is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO.

printreferences – (true/false) Prints a list of resources referred to by the imported resources. The archive file is NOT imported when this option is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO.

setAttributes – Enables resource attribute changes during import. The set option can be repeated to set different attributes. Multiple class paths can be set with a single statement.

- resourcePath The DV resource location and name.
- The **"resourceType"** is equal to "DATA_SOURCE" when attribute is classpath, host, port, database, user, or password.
- The "attribute" can be one of the following in the restriction list:
 - <u>Restriction List</u>: user, password, user2, password2, host, port, database, path, annotation
 - · user "login" or "username" or error depending on source type
 - password "password" or error depending on source type
 - user2 "appUserName" or error if not Oracle EBS
 - password2 "appPassword" or error if not Oracle EBS
 - host "urlIP" or "dsn" or "server" or "appServer" or "url" or "root" or error depending on the source type
 - port "urlPort" or "port" or error depending on source type
 - database "urlDatabaseName" or "enterprise" or "appServer" or error depending on the source type
 - path "root" or "url" or error depending on source type
 - annotation "description of view"
- Set "value" to a valid entry for the selected attribute. String values can be enclosed with double quotes to allow for spaces.
 - For Windows systems, use the semicolon delimiter:
 C:\DevZone\ATeam\Jars\my.jar;D:\Current\Ref\classes.
 - For UNIX systems, use colons as the delimiter: /lib/ext/classes:/lib/src/jars

users – Provides the ability to set users for export and import.

(See DV Admin Guide for details)

```
</export>
<export>
<domain>composite</domain>
<!--Element user is optional-->
<user>user1</user>
</export>
<import>merge</import>
</user>
</user>>
```

 Archive Security Type for package export command: Used to include specified user, group and domain info in the export file. This option can be repeated to export multiple entities.

export

```
domain – domain such as DVgroup – group within DVuser – user within DV
```

- Archive Security Type for package import command:
 - "overwrite" option imports all users present in the exported package car. By default domain, groups, and user information are not included in export or import packages.
 - "merge" imports all users present in the CAR file who are not already present in the server target. This option takes precedence over "overwrite" option.

import – one of overwrite or merge.

Complete List of Attributes

The below table summarizes the attributes supported within *ArchiveModule.xml* file. A brief explanation of each attribute is also provided. Please refer to the DV Admin Guide, Chapter 11 "CIS Command-Line Utilities" for their usage details and complete description.

(Common node prefix /ArchiveModule/archive/is omitted from the XPath definitions in the table in order to save space, i.e. XPath "archiveFileName" should be actually read as "/ArchiveModule/archive/archiveFileName".)

		Applicable Archive Module operation			
Attribute XPath	Description	BACKUP	RESTORE	EXPORT	IMPORT
id	ID is a unique name identifier within the list of archive actions (backup, import, export, etc.).	Х	Х	Х	Х
archiveFileName	Name of a CAR file to be used	Х	Х	Х	Х
archiveMethod	Archive Method must be 'CAR' (future support for VCS is planned)	Х	Х	Х	Х
description	Package description of the archive file. Notation appears when DV Studio is used to import the CAR.	Х		Х	
pkgName	Names an attribute in the contents.xml within the exported backup file.	Х		Х	
resources/export	Defines the resources to be exported.			Х	
resources/relocate/oldPath resources/relocate/newPath	This option can be used to change the location for the import.		Х		Х
resources/rebind/oldPath resources/rebind/newPath	Sets a new resource path for a dependency resource.				Х
encrypt	Encrypts communication between the command line and DV using SSL sent over the dedicated HTTPS port. The PDTool Installation Guide provides setup information for both PDTool and DV. For additional information, see DV Administration guide chapter 11 for complete details.	Х	х	х	Х
setAttributes/resourceAttribute/resourcePathsetAttributes/resourceAttribute/resourceTypesetAttributes/resourceAttribute/attributessetAttributes/resourceAttributesetAttributes/resourceAttribute/value	Enables resource attribute changes during import. The set option can be repeated to set different attributes. Multiple class paths can be set with a single statement. • The DV resource name is the <resourcepath>. • The <resourcetype> is equal to "DATA_SOURCE" when attribute is classpath, host, port, database, user, or password. • The <attribute> can be: classpath, host, port, database, user, or password, with associated value dependent on source type: • user <login> or <username> or error • password <password> or error • user2 <appusername> or error if not Oracle EBS • password2 <apppassword> or error if not Oracle EBS • o host <urlip> or <dsn> or <server> or <appserver> or <url> or <root> or error • o and taribase <urldatabasename> or <enterprise> or <appserver> or <url> or</url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></appserver></enterprise></urldatabasename></root></url></appserver></server></dsn></urlip></apppassword></appusername></password></username></login></attribute></resourcetype></resourcepath>		X		X
printcontents	This option disables actual import, and prints properties of the CAR file to the command window. The archive file is NOT imported when this option is given. This requires the following				Х

	log4j.property setting:		·	
	log4j.logger.com.compositesw.cmdline.archive=INFO			
printinfo	Causes the archive file to be examined and for	Χ		Х
	information about it to be printed to the log file.			
	The archive file is NOT imported when this option			
	is given. This requires the following log4j.property			
	setting:			
	log4j.logger.com.compositesw.cmdline.archive=INFO			
printroots	Prints the new paths to the imported resources.			Х
	The archive file is NOT imported when this option			
	is given. This requires the following log4j.property			
	setting:			
	log4j.logger.com.compositesw.cmdline.archive=INFO			
printusers	Prints the user names of the owners of the			Х
	imported resources and their associated user			
	groups. The archive file is NOT imported when			
	this option is given. This requires the following			
	log4j.property setting:			
	log4j.logger.com.compositesw.cmdline.archive=INFO			
printreferences	Prints a list of resources referred to by the			Х
	imported resources. The archive file is NOT			
	imported when this option is given. This requires			
	the following log4j.property setting:			
	log4j.logger.com.compositesw.cmdline.archive=INFO			
messagesonly	Prints the messages generated in a package			
	import to a log4j file without actually performing			
	the import. This requires the following			Х
	log4j.property setting:			
	log4j.logger.com.compositesw.cmdline.archive=INFO			
overwrite	ON RESTORE: This option does a destructive	Χ		Х
	import clearing all resources prior to importing			
	the backup CAR. Using it ensures that DV matches			
	the contents of the imported CAR file.			
	ON IMPORT: Ensures that DV will exactly match			
	the directories present in the CAR file. This option			
	clears targeted folder directories before copying			
	the CAR file contents to those cleared directories.			
	Only those folders that have representative			
	resources in the CAR file from those directories.			
	DV directories that do not have representative			
	resources in the CAR file remain untouched even if			
	the -overwrite option is specified.			
overrideLocks	Overrides Studio locks when importing resources			
overnueLocks	from a CAR file.			Х
:			V	V
includeaccess	ON IMPORT: This option must be used if you want		Х	Х
	to preserve ownership and privilege information.			
	This option is ignored if does not belong to admin			
	group.			
	ON EXPORT: Includes the current user access			
	controls (privilege specifications) on the resources			
	in the export file. Default setting does NOT include			
	access control even when exported by an			
	administrator.			

includecaching	ON IMPORT: Caching configuration is imported by default. The includecaching must be explicitly set to 'false' if you want to ignore cache configurations.		Х	X
	ON EXPORT: Includes the details of caching on views and procedures in the export file. This			
	option must be specified to include cached data			
	from materialized views, or configurations that			
	include scheduling for cache refreshes.			
includeDependencies	On export, gathers and includes all dependent			Х
meiadebependencies	resources for the resources specified in the		Х	^
	<pre><resources> section.</resources></pre>		^	
includesourceinfo	ON EXPORT: Data source connection details such		Х	Х
meradesourcenito	as user name, password, host name, and port are		^	
	not included by default. Specify -includesourceinfo			
	to include these. If passwords are included, they			
	are encrypted.			
	ON IMPORT: Used as an overwrite safeguard.			
	Suppresses import of the following pre-existing			
	connection attributes when an otherwise identical			
	resource is already present at the target:			
	o Driver,			
	· · · · · · · · · · · · · · · · · · ·			
	o ConnectionURL,			
	o Port,			
	o Database Name,			
	o Login, Password, and			
	o Pass-through Login.			
	Supports re-import without need for explicit "-set"			
	options and without altering original data source			
	attributes.			
includejars	ON EXPORT: Exports any included custom Java	Х	Χ	Х
	procedure data source's JAR.			
	ON BACKUP: Can be used to suppress export of			
	custom Java procedure data source JARs.			
	ON IMPORT: Can suppress import of any custom			
	Java procedure data source's JAR within the CAR			
	file.			
includeallusers	Exports all domains, groups, and users to the		v	
	export file. Requires the Read All Users right.		Х	
users/export/domain	Used to include specified user, group and domain			
users/ export/ domain	info in the export file.		Χ	
users/export/group	Used to include specified user, group and domain			
users/export/group	info in the export file.		Χ	
users/export/user	Used to include specified user, group and domain			
users/export/user	, , , , , , , , , , , , , , , , , , , ,		Χ	
	info in the export file.			
users/import	Allows to update target server with user			X
	information from the exported package CAR.			
	o "overwrite" option imports all users that are			
	present in the car-file			
	o "merge" imports all users present in the CAR file			
	who are not already present in the server target.			
	This option takes precedence over "overwrite"			
	option.			
	By default domain, groups, and user information			
	are not included in export or import packages.			

	See DV Admin Guide for complete details of how these parameters work in combination with Resource overwrite option.			
includerequiredusers	Includes the information about the required users in the export file.		Х	
includestatistics	DURING EXPORT and BACKUP: Includes any known resource cardinality statistics about data source table boundaries, column boundaries, and configurations when statistics gathering is enabled.	Х	Х	

Attribute Value Restrictions

```
<xs:element name="import" maxOccurs="1">
     <xs:simpleType>
       <xs:restriction base="xs:string">
         <xs:enumeration value="overwrite"/>
         <xs:enumeration value="merge"/>
       </xs:restriction>
  </xs:simpleType>
</xs:element>
<xs:element name="attribute">
  <xs:simpleType>
    <xs:restriction base="xs:string">
       <xs:enumeration value="user"/>
       <xs:enumeration value="password"/>
       <xs:enumeration value="user2"/>
       <xs:enumeration value="password2"/>
<xs:enumeration value="host"/>
       <xs:enumeration value="port"/>
       <xs:enumeration value="database"/>
       <xs:enumeration value="path"/>
       <xs:enumeration value="annotation"/>
    </xs:restriction>
  </xs:simpleType>
</xs:element>
```

4 How To Execute

The following section describes how to setup a property file for both command line and Ant and execute the script. This script will use the ArchiveModule.xml that was described in the previous section.

Script Execution

The full details on property file setup and script execution can be found in the document "PDTool User's Guide.pdf". The abridged version is as follows:

Windows: ExecutePDTool.bat -exec ../resources/plans/UnitTest-Archive.dp Unix: ./ExecutePDTool.sh -exec ../resources/plans/UnitTest-Archive.dp **Properties File (UnitTest-Archive.dp):**

Property File Rules:

```
# UnitTest-Archive.dp
   1. All parameters are space separated. Commas are not used.
         a. Any number of spaces may occur before or after any parameter and are
trimmed.
   2. Parameters should always be enclosed in double quotes according to these rules:
         a. when the parameter value contains a comma separated list:
                                    ANSWER: "ds1, ds2, ds3"
         b. when the parameter value contain spaces or contains a dynamic variable that
will resolve to spaces
                 There is no distinguishing between Windows and Unix variables. Both
UNIX style variables ($VAR) and
                 and Windows style variables (%VAR%) are valid and will be parsed
accordingly.
            ii. All parameters that need to be grouped together that contain spaces
are enclosed in double quotes.
            iii. All paths that contain or will resolve to a space must be enclosed in
double quotes.
                 An environment variable (e.g. $MODULE_HOME) gets resolved on
invocation PDTool.
                        Paths containing spaces must be enclosed in double quotes:
                               ANSWER: "$MODULE HOME/LabVCSModule.xml"
                       Given that MODULE HOME=C:/dev/Cis Deploy Tool/resources/modules,
PDTool automatically resolves the variable to
                        "C:/dev/Cis Deploy Tool/resources/modules/LabVCSModule.xml".
         c. when the parameter value is complex and the inner value contains spaces
                    i. In this example $PROJECT HOME will resolve to a path that
contains spaces such as C:/dev/Cis Deploy Tool
                        For example take the parameter -pkgfile
$PROJECT HOME$/bin/carfiles/testout.car.
```

```
# Since the entire command contains a space it must be enclosed in double quotes:

# ANSWER: "-pkgfile $PROJECT_HOME/bin/carfiles/testout.car"

# 3. A comment is designated by a # sign preceding any other text.

# a. Comments may occur on any line and will not be processed.

# 4. Blank lines are not processed

# a. Blank lines are counted as lines for display purposes

# b. If the last line of the file is blank, it is not counted for display purposes.

#
```

Property File Parameters:

Property File Example:

```
# -----
# Begin task definition list for UNIX:
# Backup
     TRUE ExecuteAction backup export $SERVERID backup
$MODULE HOME/ArchiveModule.xml $MODULE HOME/servers.xml
# Restore
     TRUE ExecuteAction
                             backup import $SERVERID restore
$MODULE HOME/ArchiveModule.xml $MODULE HOME/servers.xml
# Export
     TRUE ExecuteAction
                                          $SERVERID export
                             pkg export
$MODULE HOME/ArchiveModule.xml $MODULE HOME/servers.xml
# Import
PASS TRUE ExecuteAction
                             pkg import
                                           $SERVERID import
$MODULE HOME/ArchiveModule.xml $MODULE HOME/servers.xml
```

Ant Execution

The full details on build file setup and ant execution can be found in the document "PDTool User's Guide.pdf". The abridged version is as follows:

Windows: ExecutePDTool.bat -ant ../resources/ant/build-Archive.xml Unix: ./ExecutePDTool.sh -ant ../resources/ant/build-Archive.xml *Build File:*

```
<?xml version="1.0" encoding="UTF-8"?>
coding="UTF-8"?>
```

```
<description>description</description>
 <!-- Default properties -->
 property name="SERVERID"
                                          value="localhost"/>
 cproperty name="noarguments"
                                          value="" ""/>
 <!-- Default Path properties -->
 property name="RESOURCE HOME"
                                          value="${PROJECT HOME}/resources"/>
 property name="MODULE HOME"
                                          value="${RESOURCE HOME}/modules"/>
 cproperty name="pathToServersXML"
                                          value="${MODULE HOME}/servers.xml"/>
 cproperty name="pathToArchiveXML"
                                          value="${MODULE HOME}/ArchiveModule.xml"/>
                                          value="${MODULE HOME}/DataSourceModule.xml"/>
 cproperty name="pathToDataSourcesXML"
 cproperty name="pathToGroupsXML"
                                          value="${MODULE HOME}/GroupModule.xml"/>
 cproperty name="pathToPrivilegeXML"
                                          value="${MODULE HOME}/PrivilegeModule.xml"/>
 cproperty name="pathToRebindXML"
                                          value="${MODULE HOME}/RebindModule.xml"/>
 cproperty name="pathToRegressionXML"
                                          value="${MODULE HOME}/RegressionModule.xml"/>
 property name="pathToResourceXML"
                                          value="${MODULE HOME}/ResourceModule.xml"/>
 property name="pathToResourceCacheXML"
                                          value="${MODULE HOME}/ResourceCacheModule.xml"/>
 value="${MODULE HOME}/TriggerModule.xml"/>
 cproperty name="pathToTriggerXML"
 cproperty name="pathToUsersXML"
                                          value="${MODULE HOME}/UserModule.xml"/>
 cproperty name="pathToVCSModuleXML"
                                          value="${MODULE HOME}/VCSModule.xml"/>
 <!-- Custom properties -->
 property name="archiveIds"
                                         value="import1"/>
 <!-- Default Classpath [Do Not Change] -->
 <path id="project.class.path">
       <fileset dir="${PROJECT HOME}/lib"><include name="**/*.jar"/></fileset>
      <fileset dir="${PROJECT HOME}/dist"><include name="**/*.jar"/></fileset>
       <fileset dir="${PROJECT HOME}/ext/ant/lib"><include name="**/*.jar"/></fileset>
 </path>
  <taskdef name="executeJavaAction" description="Execute Java Action"</pre>
classname="com.tibco.ps.deploytool.ant.CompositeAntTask" classpathref="project.class.path"/>
target: default
<target name="default" description="Update CIS with environment specific parameters">
 <!-- Windows / UNIX -->
       <executeJavaAction action="backup_export"</pre>
arguments="${SERVERID}^backup1^${pathToArchiveXML}^${pathToServersXML}"
endExecutionOnTaskFailure="TRUE"/>
       <executeJavaAction action="pkg import"</pre>
arguments = "\${SERVERID}^import1^\${pathToArchiveXML}^\${pathToServersXML}"
endExecutionOnTaskFailure="TRUE"/>
       <executeJavaAction action="pkg_export"</pre>
arguments="${SERVERID}^export1^${pathToArchiveXML}^${pathToServersXML}"
endExecutionOnTaskFailure="TRUE"/>
 </target>
</project>
```

5 PDTool Examples

The following are common scenarios when using the Archive Module.

Scenario 1 – Export resources from a DV instance

Description:

Utilize the Archive Module to export a series of folders from a DV instance into a DV Archive (.car) file.

XML Configuration Sample:

Use the ArchiveModule XML file found in the /resources/module directory. Modify the option nodes to use paths that are pertinent to your environment. The entry for export should look like something this:

Execution Sample:

Unix: ./ExecutePDTool.sh -exec ../resources/plans/UnitTest-Archive.dp Property file setup for UnitTest-Archive.dp:

```
# ------
# Begin task definition list:
# ------
# Export

PASS TRUE ExecuteAction pkg_export $SERVERID export
$MODULE_HOME/ArchiveModule.xml $MODULE_HOME/servers.xml
```

Results Expected:

The script will report "PASS" for the execution of this action. Check timestamp of the output file (PDTool/bin/carfiles) to make sure it is current.

Scenario 2 – Import a DV Archive (.car)

Description:

Utilize the Archive Module to import resources from a DV Archive (.car) file into a target DV instance

XML Configuration Sample:

Use the ArchiveModule XML file found in the /resources/module directory. To prove that the import worked, use DV Studio to remove a folder resource prior to executing the import. The entry for export should look like something this:

Execution Sample:

Unix: ./ExecutePDTool.sh -exec ../resources/plans/UnitTest-Archive.dp Property file setup for UnitTest-Archive.dp:

```
# ------
# Begin task definition list for UNIX:
# -------
# Import
PASS TRUE ExecuteAction    pkg_import    $SERVERID import
$MODULE_HOME/ArchiveModule.xml $MODULE_HOME/servers.xml
```

Results Expected:

The script will report "PASS" for the execution of this action. Use DV Studio to verify that the resources that were deleted previously are not present again. You may have to refresh Studio to see the imported resources.

6 Debugging

The following describes how to setup debugging.

Set the log4j.properties file.

INFO setting (default): Required for any of the archive print options such as "printinfo".

DV Archive [INFO, DEBUG, WARN]

INFO: required for any of the print options such as printinfo log4j.logger.com.compositesw.cmdline.archive=INFO

DEBUG setting: print out debug information in console window

log4j.logger.com.compositesw.cmdline.archive=DEBUG

WARN setting: print out warnings in console window (suppress INFO)

log4j.logger.com.compositesw.cmdline.archive=WARN

7 Exceptions

The following are common exceptions and messages that may occur.

8 Conclusion

Concluding Remarks

The Promotion and Deployment Tool is a set of pre-built modules intended to provide a turn-key experience for promoting DV resources from one DV instance to another. The user only requires system administration skills to operate and support. The code is transparent to operations engineers resulting in better supportability. It is easy for users to swap in different implementations of a module using the Spring framework and configuration files.

How you can help!

Build a module and donate the code back to Professional Services for the advancement of the "*Promotion and Deployment Tool*".