

# PDTool Archive Module User Guide

# An Open Source Asset for use with TIBCO® Data Virtualization

TIBCO Software empowers executives, developers, and business users with Fast Data solutions that make the right data available in real time for faster answers, better decisions, and smarter action. Over the past 15 years, thousands of businesses across the globe have relied on TIBCO technology to integrate their applications and ecosystems, analyze their data, and create real-time solutions. Learn how TIBCO turns data—big or small—into differentiation at www.tibco.com.

Project Name	AS Assets PDTool (Promotion and Deployment Tool)
Document Location	This document is only valid on the day it was printed. The source of the document will be found in the PDTool and PDToolRelease folder (https://github.com/TIBCOSoftware)
Purpose	User's Guide



www.tibco.com

Global Headquarters 3303 Hillview Avenue Palo Alto, CA 94304 **Tel:** +1 650-846-1000 +1 800-420-8450

Fax: +1 650-846-1005

## **Revision History**

Version	Date	Author	Comments
1.0	6/9/2011	Mike Tinius	Initial revision for Archive User Guide
1.0.1	8/1/2011	Mike Tinius	Revision due to Architecture changes.
2.0	7/13/2012	Alex Dedov	Document enhancements to support full set of command-line options
2.1	8/24/2012	Mike Tinius	Updated the archive attribute options.
3.0	8/21/2013	Mike Tinius	Updated docs to Cisco format
3.1	1/31/2014	Mike Tinius	Updated documentation for Includesourceinfo attribute and the use of encrypt flag and https. See PDTool Installation Guide for https configuration.
3.2	2/18/2014	Mike Tinius	Added section on debugging. Fixed some of the options that were upper case and made them lower case. Prepare docs for open source.
3.3	3/24/2014	Mike Tinius	Changed references of XML namespace to www.dvbu.cisco.com
3.4	11/17/2014	Mike Tinius	Updated license.
3.5	03/04/05	Mike Tinius	Updated table of contents to include methods and updated docs to Cisco format.
4.0	12/14/2017	Mike Tinius	Initial revision with Tibco
5.0	08/27/2020	Mike Tinius	Updated documentation
5.1	10/20/2020	Mike Tinius	Fixed includesourceinfo to issue -nosourceinfo instead of -includesourceinfo when includesourceinfo=falseincludesourceinfo is no longer supported by TDV.

## **Related Documents**

Name	Author
PDTool User's Guide.pdf	Mike Tinius
AdministrationGuide.pdf	TIBCO Software

## **Supported Versions**

Name	Version
TIBCO® Data Virtualization	7.0.8 or later

# **Table of Contents**

1	Introduction	4
	Purpose	4
	Audience	
	References	
2	Archive Module Definition	5
	Method Definitions and Signatures	
	1. pkg_import	
	2. pkg_export	
	3. backup_export	
	4. backup_import	6
3	<b>9</b>	
	Description of the Module XML	7
	Attributes of Interest	
	Complete List of Attributes	
	Attribute Value Restrictions	22
4	How To Execute	23
	Script Execution	23
	Ant Execution	24
5	PDTool Examples	26
	Scenario 1 – Export resources from a DV instance	
	Scenario 2 – Import a DV Archive (.car)	
6	Debugging	28
7	Exceptions	29
8	Conclusion	30
	Concluding Remarks	30
	How you can help!	

### 1 Introduction

#### **Purpose**

The purpose of the Archive User Guide is to demonstrate how to effectively use the Archive Module for importing, exporting, backing up and restoring Data Virtualization (DV) resources. The scripts in this module will interact directly with a Data Virtualization (DV) server. There is no version control associated with this module. For version control, review the VCS Module documentation. This will module will focus on exporting and importing resources via Data Virtualization (DV) Archive files (.car). It will also show how to use backup and restore features which also use the DV Archive files. The Archive Module is completely shell/batch script based.

#### **Audience**

This document is intended to provide guidance for the following users:

- Architects
- Developers
- Administrators
- Operations personnel

#### References

Product references are shown below. Any references to CIS or DV refer to the current TIBCO® Data Virtualization.

- TIBCO® Data Virtualization was formerly known as
  - Cisco Data Virtualization (DV)
  - Composite Information Server (CIS)

#### 2 Archive Module Definition

#### **Method Definitions and Signatures**

#### 1. pkg\_import

Import a CAR file into a local or remote DV instance with options.

```
@param serverId - target server id from servers config xml
@param archiveIds - list of comma separate archive Ids containing the
archive instructions
@param pathToArchiveXML - path to the archive module xml
@param pathToServersXML - path to the server values xml
@throws CompositeException

public void pkg_import(String serverId, String archiveIds, String
pathToArchiveXML, String pathToServersXML) throws CompositeException
```

#### 2. pkg\_export

Export a CAR file from a local or remote DV instance by designating a list of resources to export.

```
@param serverId - target server id from servers config xml
@param archiveIds - list of comma separate archive Ids containing the archive instructions
@param pathToArchiveXML - path to the archive module xml
@param pathToServersXML - path to the server values xml
@throws CompositeException

public void pkg_export(String serverId, String archiveIds, String pathToArchiveXML, String pathToServersXML) throws CompositeException]
```

### 3. backup\_export

Perform a complete backup of a local or remote DV server instance.

```
Restore a full server backup from a backup car file

@param serverId - target server id from servers config xml

@param archiveIds - list of comma separated archive Ids containing the archive instructions

@param pathToArchiveXML - path to the archive module xml

@param pathToServersXML - path to the server values xml
```

@throws CompositeException
public void backup\_export(String serverId, String archiveIds, String pathToArchiveXML, String pathToServersXML) throws CompositeException

#### 4. backup\_import

Perform a complete restore of a local or remote DV server instance.

```
Create a full server backup of a DV instance to a car file

@param serverId - target server id from servers config xml

@param archiveIds - list of comma separated archive Ids containing the archive instructions

@param pathToArchiveXML - path to the archive module xml

@param pathToServersXML - path to the server values xml

@throws CompositeException

public void backup_import(String serverId, String archiveIds, String pathToArchiveXML, String pathToServersXML) throws CompositeException
```

#### General Notes:

The arguments pathToArchiveXML and pathToServersXML will be located in PDTool/resources/modules. The value passed into the methods will be the fully qualified path. The paths get resolved when executing the property file and evaluating the \$MODULE\_HOME variable.

# 3 Archive Module XML Configuration

A full description of the PDToolModule XML Schema can be found by reviewing /docs/PDToolModules.xsd.html.

#### **Description of the Module XML**

The Archive Module performs various DV archiving operations with CAR (DV Archive) files such as backup, restore, import and export.

```
<?xml version="1.0"?>
   <!--Element archive is optional, maxOccurs=unbounded-->
    <archive>
        <id>ALL ATTRIBUTES EXMPLE</id>
        <archiveMethod>CAR</archiveMethod>
        <archiveFileName>$PROJECT HOME/test01.car</archiveFileName>
        <!--Element includeDependencies is optional-->
        <includeDependencies>false</includeDependencies>
       <!--Element resources is optional-->
        <resources>
            <!-- 'Choice' block, maxOccurs=unbounded-->
            <export>/shared/examples/CompositeView</export>
            <relocate>
                <oldPath>/shared/examples/CompositeView</oldPath>
                <newPath>/shared/examples/newdir/CompositeView</newPath>
            </relocate>
            <rebind>
                <oldPath>/shared/examples/ViewSales</oldPath>
                <newPath>/shared/examples/newds/ViewSales</newPath>
            </rebind>
            <export>/shared/examples/ViewOrder</export>
            <relocate>
                <oldPath>string</oldPath>
                <newPath>string</newPath>
            </relocate>-->
                    <!--
            <rebind>
                <oldPath>string</oldPath>
                <newPath>string</newPath>
```

```
</rebind>-->
</resources>
<!--Element encrypt is optional-->
<encrypt>false</encrypt>
<!--Element description is optional-->
<description>Export CompositeView</description>
<!--Element includeaccess is optional-->
<includeaccess>false</includeaccess>
<!--Element includeallusers is optional-->
<includeallusers>false</includeallusers>
<!--Element includerequiredusers is optional-->
<includerequiredusers>false</includerequiredusers>
<!--Element includecaching is optional-->
<includecaching>false</includecaching>
<!--Element includejars is optional-->
<includejars>true</includejars>
<!--Element includesourceinfo is optional-->
<includesourceinfo>false</includesourceinfo>
<!--Element includestatistics is optional-->
<includestatistics>false</includestatistics>
<!--Element messagesonly is optional-->
<messagesonly>false</messagesonly>
<!--Element overridelocks is optional-->
<overridelocks>false</overridelocks>
<!--Element overwrite is optional-->
<overwrite>false</overwrite>
<!--Element pkgName is optional-->
<pkgName>Composite Server Archive File via PD Tool</pkgName>
<!--Element printinfo is optional-->
<printinfo>false</printinfo>
<!--Element printroots is optional-->
<printroots>false</printroots>
<!--Element printusers is optional-->
<printusers>false</printusers>
<!--Element printcontents is optional-->
<printcontents>false</printcontents>
<!--Element printreferences is optional-->
<printreferences>false</printreferences>
<!--Element setAttributes is optional-->
```

```
<setAttributes>
     <!--Element resourceAttribute, maxOccurs=unbounded-->
     <resourceAttribute>
<re>ourcePath>/shared/examples/ds_inventory</resourcePath>
      <re>ourceType>DATA_SOURCE</resourceType>
      <attribute>annotation</attribute>
      <value>sample data source</value>
     </resourceAttribute>
     <resourceAttribute>
         <resourcePath>string</resourcePath>
         <resourceType>string</resourceType>
         <attribute>annotation</attribute>
         <value>string</value>
     </resourceAttribute>
 </setAttributes>
 <!--Element users is optional-->
 <users>
     <!--'Choice' block is optional, maxOccurs=unbounded-->
     <!--Element export, maxOccurs=unbounded-->
     <export>
         <domain>string</domain>
         <!--Element group is optional-->
         <group>string</group>
         <!--Element user is optional-->
         <user>string</user>
     </export>
     <export>
         <domain>string</domain>
         <!--Element group is optional-->
         <group>string</group>
         <!--Element user is optional-->
         <user>string</user>
     </export>
             <!--<import>merge</import>-->
 </users>
 <!--Element verbose is optional-->
 <verbose>false</verbose>
 <!--Element quiet is optional-->
```

```
<quiet>false</quiet>
<!--Element excludeJars is optional-->
<excludeJars>false</excludeJars>
<!--Element nosourceinfo is optional-->
<nosourceinfo>false/nosourceinfo>
<!--Element mergeusers is optional-->
<mergeusers>false</mergeusers>
<!--Element nocaching is optional-->
<nocaching>false</nocaching>
<!--Element nocachepolicy is optional-->
<nocachepolicy>false</nocachepolicy>
<!--Element noscheduling is optional-->
<noscheduling>false</noscheduling>
<!--Element createcachetables is optional-->
<createcachetables>false</createcachetables>
<!--Element updateCacheTables is optional-->
<updateCacheTables>false</updateCacheTables>
<!--Element reintrospect is optional-->
<reintrospect>false</reintrospect>
<!--Element reintrospectNone is optional-->
<reintrospectNone>false</reintrospectNone>
<!--Element rebindableResources is optional-->
<rebindableResources>
    <!--Element rebindablePaths, maxOccurs=unbounded-->
   <rebindablePaths>
        <path>string</path>
        <description>string</description>
    </rebindablePaths>
   <rebindablePaths>
        <path>string</path>
        <description>string</description>
    </rebindablePaths>
</rebindableResources>
<!--Element sso is optional-->
<sso>false</sso>
<!--Element sspi is optional-->
<sspi>false</sspi>
<!--Element spn is optional-->
<spn>string</spn>
```

#### **Attributes of Interest**

id – a uniquely named value identifying an archive operation.

archiveMethod - export archive file (CAR).

archiveFileName – full path to the archive file name and location. The value may contain variables defined via deploy.dp, JAVA Environment or System Environment. A variable is defined with the format of VAR=myvalue and referenced as \$VAR. For example the entry archiveFileName may look like this:

<archiveFileName>\$PROJECT\_HOME/resources/carfiles/test00.car</archiveFileName>

includeDependencies - (true/false) Include resource dependencies on export.

#### resources

```
export – unbound list of DV resources to exportrelocateoldPath – the old path to the resource
```

**newPath** – the new path to the resource

#### rebind

oldPath – the old path to the resource to be rebound

**newPath** – the new path the resource to be rebound

**encrypt** – (true/false) Encrypts communication between the command line and DV using SSL sent over the dedicated HTTPS port. The PDTool Installation Guide provides setup information

for both PDTool and DV. For additional information, see DV Administration guide chapter 11 for complete details.

**description** – Package description of the archive file. Notation appears when DV Studio is used to import the CAR.

#### includeaccess - (true/false)

- ON IMPORT: The -includeaccess option must be used if you want to preserve ownership and privilege information. This option is ignored if you are not logged in as a member of the admin group.
- ON EXPORT: Includes the current user access controls (privilege specifications) on the
  resources in the export file. Default setting does NOT include access control even when
  exported by an administrator. An error can occur if this option is used and the exporting
  user is not a member of the admin group with the Read All Resources right and include
  access on export.

#### **includerequiredusers** – (true/false)

• ON PACKAGE EXPORT: Exports all domains, groups, and users to the export file. Requires the Read All Users right.

#### includecaching - (true/false)

- ON IMPORT: Caching configuration is imported by default. When includecaching=false, the -nocaching option is set on the command line to ignore cache configurations.
- ON EXPORT: Includes the details of caching on views and procedures in the export file.
   This option must be specified to include cached data from materialized views, or configurations that include scheduling for cache refreshes.

#### includejars - (true/false)

- ON PACKAGE EXPORT: Exports any included custom Java procedure data source's JAR.
- ON BACKUP EXPORT: Can suppress export of custom Java procedure data source JARs.
- ON PACKAGE IMPORT: Can suppress import of any custom Java procedure data source's JAR within the CAR file. When includejars=false, -excludejars is set on the command line.

#### includesourceinfo - (true/false)

- ON PACKAGE EXPORT: Data source connection details (such as user name, password, host name, and port) are included by default. When includesourceinfo=false, the command line uses -nosourceinfo to exclude connection information. If data source information is included then passwords are encrypted
- ON PACKAGE IMPORT: (An overwrite safeguard.) Data source connection details (such as user name, password, host name, and port) are included by default. When includesourceinfo=false, the command line uses -nosourceinfo to suppress import of the following pre-existing connection attributes when an otherwise identical resource is already present in the target: driver, connectionURL, port, database name, login, password, and pass-through login. Supports re-import without need for explicit set options and without altering original data source attributes.

#### includestatistics - (true/false)

 ON PACKAGE EXPORT and BACKUP EXPORT: Includes any known resource cardinality statistics about data source table boundaries, column boundaries, and configurations when statistics gathering is enabled.

#### messagesonly – (true/false)

 ON PACKAGE IMPORT ONLY: Prints the messages generated in a package import to a log4j file without actually performing the import.

#### overridelocks - (true/false)

• ON PACKAGE IMPORT ONLY: Overrides Studio locks when importing resources from a CAR file.

#### overwrite - (true/false)

- ON BACKUP IMPORT: This option does a destructive import clearing all resources prior to importing the backup CAR. Using the backup\_import utility with the -overwrite option ensures that DV matches the contents of the imported CAR file.
- ON PACKAGE IMPORT: Use of the -overwrite option ensures that DV will exactly match the directories present in the CAR file. The -overwrite option clears targeted folder directories before copying the CAR file contents to those cleared directories. The pkg\_import utility clears only those folders that have representative resources in the CAR file from those directories. DV directories that do not have representative resources in the CAR file remain untouched even if the -overwrite option is specified.

**quiet** – Command information is not reported if this option is mentioned.

**verbose** – Reports problems encountered during the import. If neither verbose nor quiet is mentioned, verbose is the default behavior.

**pkgName** – Names an attribute in the contents.xml within the exported backup file.

**printinfo** – (true/false) The "printinfo" option causes the archive file to be examined and for information about it to be printed to the display. The archive file is NOT imported when this option is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO.

**printroots** – (true/false) Prints the new paths to the imported resources. The archive file is NOT imported when this option is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO.

**printusers** – (true/false) Prints the user names of the owners of the imported resources and their associated user groups. The archive file is NOT imported when this option is given. This requires the following log4j.property setting:

log4j.logger.com.compositesw.cmdline.archive=INFO.

**printcontents** – (true/false) This option disables actual import, and prints properties of the CAR file to the command window. The archive file is NOT imported when this option is is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO.

**printreferences** – (true/false) Prints a list of resources referred to by the imported resources. The archive file is NOT imported when this option is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO.

**setAttributes** – Enables resource attribute changes during import. The set option can be repeated to set different attributes. Multiple class paths can be set with a single statement.

- resourcePath The DV resource location and name.
- The "resourceType" is equal to "DATA\_SOURCE" when attribute is classpath, host, port, database, user, or password.
- The "attribute" can be one of the following in the restriction list:
  - <u>Restriction List</u>: user, password, user2, password2, host, port, database, path, annotation

- user "login" or "username" or error depending on source type
- password "password" or error depending on source type
- user2 "appUserName" or error if not Oracle EBS
- password2 "appPassword" or error if not Oracle EBS
- host "urlIP" or "dsn" or "server" or "appServer" or "url" or "root" or error depending on the source type
- port "urlPort" or "port" or error depending on source type
- database "urlDatabaseName" or "enterprise" or "appServer" or error depending on the source type
- path "root" or "url" or error depending on source type
- annotation "description of view"
- Set "value" to a valid entry for the selected attribute. String values can be enclosed with double quotes to allow for spaces.
  - For Windows systems, use the semicolon delimiter:
     C:\DevZone\ATeam\Jars\my.jar;D:\Current\Ref\classes.
  - For UNIX systems, use colons as the delimiter: /lib/ext/classes:/lib/src/jars

**users** – Provides the ability to set users for export and import.

(See DV Admin Guide for details)

 Archive Security Type for package export command: Used to include specified user, group and domain info in the export file. This option can be repeated to export multiple entities.

#### export

domain – domain such as DVgroup – group within DVuser – user within DV

- Archive Security Type for package **import** command:
  - "overwrite" option imports all users present in the exported package car. By default domain, groups, and user information are not included in export or import packages.
  - "merge" imports all users present in the CAR file who are not already present in the server target. This option takes precedence over "overwrite" option.

**import** – one of overwrite or merge.

#### **Complete List of Attributes**

The below table summarizes the attributes supported within *ArchiveModule.xml* file. A brief explanation of each attribute is also provided. Please refer to the DV Admin Guide, Chapter 11 "CIS Command-Line Utilities" for their usage details and complete description.

(Common node prefix /ArchiveModule/archive/is omitted from the XPath definitions in the table in order to save space, i.e. XPath "archiveFileName" should be actually read as "/ArchiveModule/archive/archiveFileName".)

		Applicable Archive Module operation			
Attribute XPath	Description	BACKUP	RESTORE	EXPORT	IMPORT
id	ID is a unique name identifier within the list of archive actions (backup, import, export, etc.).	Х	Х	Х	Х
encrypt	Encrypts communication between the command line and DV using SSL sent over the dedicated HTTPS port. The PDTool Installation Guide provides setup information for both PDTool and DV. For additional information, see DV Administration guide chapter 11 for complete details.	Х	Х	Х	Х
encryptionPassword	The password used to encrypt /decrypt sensitive data in your car file, for example, data source password, etc. You do not need to specify this parameter if you are importing a car file from a TDV version prior to 8.0.	Х	X	X	Х
SSO	Enables SSO authentication. Must be used with the - spn option. You do not need to input a user name or password.	Х	Х	Х	Х
sspi	For Windows environments configured with SSPI, you can use this parameter after -sso and -spn.	Х	Х	Х	Х
spn <spn></spn>	Use this parameter after specifying -sso, to indicate what the service principal name is. Use one of the following formats depending on the protocol you are using:  • sspi is <servicename full_computername@realm="">  • JGSS is <servicename@full_computername></servicename@full_computername></servicename>	х	х	х	х
krb5conf	For environments configured with multiple Kerberos authentication files, you can use this parameter after -sso and -spn to specify which authentication file to use. <krb5conf> must specify the full path and filename to use. If this parameter is not specified, the default Kerberos system file is used.</krb5conf>	Х	Х	Х	Х
archiveFileName	Name of a CAR file to be used	Х	Х	Х	Х
archiveMethod	Archive Method must be 'CAR' (future support for VCS is planned)	Х	Х	Х	Х
optfile <file_name></file_name>	Specifies an options file to pass options without using the command line. The options file is useful for hiding password information. For example: pkg_export -server localhost -user test -password password -pkgfile sample.car is the same as: pkg_export -optfile sample.opt where sample.opt contains: -server localhost -user test -password password -pkgfile sample.car	х	х	х	х
genopt	By giving this option and an opt file name, the parameters will be stored in the opt file with the password encrypted. While doing an export or import operation the password saved will not be shown as a clear text.	х	х	Х	Х

Attribute XPath	Description	BACKUP	RESTORE	EXPORT	IMPORT
verbose	Reports problems encountered during the import. If neither verbose nor quiet is mentioned, verbose is the default behavior	Х	Х	Х	Х
quiet	Command information is not reported if this option is mentioned.			Х	Х
description	Package description of the archive file. Notation appears when DV Studio is used to import the CAR.	Х		Х	
pkgName	Names an attribute in the contents.xml within the exported backup file.	Х		Х	
resources/export	Defines the resources to be exported.			Х	
resources/relocate/oldPath resources/relocate/newPath	This option can be used to change the location for the import.		Х		Х
resources/rebind/oldPath resources/rebind/newPath	Sets a new resource path for a dependency resource.				Х
setAttributes/resourceAttribu te/resourcePath setAttributes/resourceAttribu te/resourceType setAttributes/resourceAttribu te/attribute setAttribute setAttributes/resourceAttribu te/value	Enables resource attribute changes during import. The set option can be repeated to set different attributes. Multiple class paths can be set with a single statement.  • The DV resource name is the <resourcepath>.  • The <resourcetype> is equal to "DATA_SOURCE" when attribute is classpath, host, port, database, user, or password.  • The <attribute> can be: classpath, host, port, database, user, or password, with associated value dependent on source type:  • user <login> or <username> or error  • password <password> or error  • o user2 <appusername> or error if not Oracle EBS  • o host <urllp> or <dsn> or <server> or <appserver> or <url> or <root> or error  • o port <urllport> or <port> or error  • o database <urldatabasename> or <enterprise> or <appserver> or or path <root> or <url> o</url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></url></root></appserver></enterprise></urldatabasename></port></urllport></root></url></appserver></server></dsn></urllp></appusername></password></username></login></attribute></resourcetype></resourcepath>		X		X
messagesonly	Prints the messages generated in a package import to a log4j file without actually performing the import. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO				Х
overrideLocks	Overrides Studio locks when importing resources from a CAR file.				Х
printcontents	This option disables actual import, and prints properties of the CAR file to the command window. The archive file is <b>NOT imported</b> when this option is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO				х

Attribute XPath	Description	BACKUP	RESTORE	EXPORT	IMPORT
printinfo	Causes the archive file to be examined and for information about it to be printed to the log file. The archive file is <b>NOT imported</b> when this option is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO		Х		х
printroots	Prints the new paths to the imported resources. The archive file is <b>NOT imported</b> when this option is given. This requires the following log4j.property setting:  log4j.logger.com.compositesw.cmdline.archive=INFO				Х
printusers	Prints the user names of the owners of the imported resources and their associated user groups. The archive file is <b>NOT imported</b> when this option is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO				Х
printreferences	Prints a list of resources referred to by the imported resources. The archive file is <b>NOT imported</b> when this option is given. This requires the following log4j.property setting: log4j.logger.com.compositesw.cmdline.archive=INFO				х
overwrite	ON RESTORE: This option does a destructive import clearing all resources prior to importing the backup CAR. Using it ensures that DV matches the contents of the imported CAR file.  ON IMPORT: Ensures that DV will exactly match the directories present in the CAR file. This option clears targeted folder directories before copying the CAR file contents to those cleared directories. Only those folders that have representative resources in the CAR file from those directories. DV directories that do not have representative resources in the CAR file remain untouched even if the -overwrite option is specified.		X		X
includeaccess	ON IMPORT: This option must be used if you want to preserve ownership and privilege information. This option is ignored if does not belong to admin group. ON EXPORT: Includes the current user access controls (privilege specifications) on the resources in the export file. Default setting does NOT include access control even when exported by an administrator.			Х	х
includecaching	ON IMPORT: Caching configuration is imported by default. The includecaching must be explicitly set to 'false' if you want to ignore cache configurations.  ON EXPORT: Includes the details of caching on views and procedures in the export file. This option must be specified to include cached data from materialized views, or configurations that include scheduling for cache refreshes.			Х	

Attribute XPath	Description	BACKUP	RESTORE	EXPORT	IMPORT
nocaching	Caching configuration is imported by default. This option must be used if you want to ignore cache configurations.				Х
includeDependencies	On export, gathers and includes all dependent resources for the resources specified in the <resources> section.</resources>			Х	Х
includesourceinfo	ON PACKAGE EXPORT: Data source connection details (such as user name, password, host name, and port) are included by default. When includesourceinfo=false, the command line uses - nosourceinfo to exclude connection information. If data source information is included then passwords are encrypted			х	х
	ON PACKAGE IMPORT: (An overwrite safeguard.) Data source connection details (such as user name, password, host name, and port) are included by default. When includesourceinfo=false, the command line uses -nosourceinfo to suppress import of the following pre-existing connection attributes when an otherwise identical resource is already present in the target:				
nosourceinfo	(An overwrite safeguard.) Suppresses import of the following pre-existing connection attributes when an otherwise identical resource is already present in the target: driver, connectionURL, port, database name, login, password, and pass-through login. Supports re-import without need for explicit set options and without altering original data source attributes.			х	х
includejars	ON EXPORT: Exports any included custom Java procedure data source's JAR.  ON BACKUP: Can be used to suppress export of custom Java procedure data source JARs.  ON IMPORT: Can suppress import of any custom Java procedure data source's JAR within the CAR file.	Х		Х	Х
excludejars	ON BACKUP: Suppresses export of custom Java procedure data source JAR files. ON IMPORT: Does not import custom Java procedure data source's JAR files within the CAR file.	Х			Х

Attribute XPath	Description	BACKUP	RESTORE	EXPORT	IMPORT
includeallusers	Exports all domains, groups, and users to the export file. Requires the Read All Users right.			Х	
includerequiredusers	Includes the information about the required users in the export file.			Х	
includeusers	Imports all users present in the exported package CAR file unless mergeusers is specified. By default domain, groups, and user information are not included in export or import packages.				Х
mergeusers	Imports all users present in the CAR file who are not already present in the server target. This option takes precedence over the includeusers option, and can have different behavior when combined with the overwrite option.				X
users/export/domain	Used to include specified user, group and domain info in the export file.			Х	
users/export/group	Used to include specified user, group and domain info in the export file.			Х	
users/export/user	Used to include specified user, group and domain info in the export file.			Х	
users/import	Allows to update target server with user information from the exported package CAR.  o "overwrite" option imports all users that are present in the car-file  o "merge" imports all users present in the CAR file who are not already present in the server target. This option takes precedence over "overwrite" option.  By default, domain, groups, and user information are not included in export or import packages. See DV Admin Guide for complete details of how these parameters work in combination with Resource overwrite option.				X
nocaching	Caching configuration is imported by default. This option must be used if you want to ignore cache configurations.				X
nopolicy	CBS, RBS and Security policies are imported by default. Set this option if you want to ignore the configuration.				X
createcachetables	If used, the cache status, tracking and target tables required by cached resources are created, if not already present in the database for your data source as it is described in the metadata of the CAR file you are importing.  The import process does not create the TDV resources for cache_status, cache_tracking, and target tables if they are not described in the CAR file metadata.		Х		х
updateCacheTables	Yes or no. Use this optional value to indicate whether you want to have the cache tables dropped and recreated with any potential changes that are included in the CAR file.		Х		Х
reintrospect	This option is used to control if it does re- introspections for all data sources at end of the import or not		Х		

Attribute XPath	Description	BACKUP	RESTORE	EXPORT	IMPORT
reintrospectNone	Do no reintrospect any data sources upon import.		Х		
includeParentResources	By enabling this option, the parent resources are included while exporting the data source metadata.			Х	
ignoreEncryption	If this option is used, then all backup data will be imported regardless of whether a valid encryption key was provided. This means that the import will not fail. This option can be used to allow partially importing any backed up data. However, the import process will only import data that is not encrypted or can be decrypted using the provided encryption key. All encrypted portions of the backup data that cannot be decrypted will be imported as empty values and the import will otherwise succeed. This affects all encrypted values in the backup data, which includes, but is not limited to data source and LDAP domain connection passwords.		х		х
includestatistics	DURING EXPORT and BACKUP: Includes any known resource cardinality statistics about data source table boundaries, column boundaries, and configurations when statistics gathering is enabled.	Х		Х	

#### **Attribute Value Restrictions**

```
<xs:element name="import" maxOccurs="1">
    <xs:simpleType>
       <xs:restriction base="xs:string">
         <xs:enumeration value="overwrite"/>
         <xs:enumeration value="merge"/>
       </xs:restriction>
  </xs:simpleType>
</xs:element>
<xs:element name="attribute">
  <xs:simpleType>
    <xs:restriction base="xs:string">
       <xs:enumeration value="user"/>
       <xs:enumeration value="password"/>
<xs:enumeration value="user2"/>
       <xs:enumeration value="password2"/>
       <xs:enumeration value="host"/>
       <xs:enumeration value="port"/>
       <xs:enumeration value="database"/>
       <xs:enumeration value="path"/>
       <xs:enumeration value="annotation"/>
    </xs:restriction>
  </xs:simpleType>
</xs:element>
```

#### 4 How To Execute

The following section describes how to setup a property file for both command line and Ant and execute the script. This script will use the ArchiveModule.xml that was described in the previous section.

#### **Script Execution**

The full details on property file setup and script execution can be found in the document "PDTool User's Guide.pdf". The abridged version is as follows:

Windows: ExecutePDTool.bat -exec ../resources/plans/UnitTest-Archive.dp Unix: ./ExecutePDTool.sh -exec ../resources/plans/UnitTest-Archive.dp **Properties File (UnitTest-Archive.dp):** 

#### Property File Rules:

```
UnitTest-Archive.dp
   1. All parameters are space separated. Commas are not used.
          a. Any number of spaces may occur before or after any parameter and are
trimmed.
   2. Parameters should always be enclosed in double quotes according to these rules:
          a. when the parameter value contains a comma separated list:
                                     ANSWER: "ds1, ds2, ds3"
         b. when the parameter value contain spaces or contains a dynamic variable that
will resolve to spaces
            i.
                 There is no distinguishing between Windows and Unix variables. Both
UNIX style variables ($VAR) and
                  and Windows style variables (%VAR%) are valid and will be parsed
accordingly.
            ii. All parameters that need to be grouped together that contain spaces
are enclosed in double quotes.
            iii. All paths that contain or will resolve to a space must be enclosed in
double quotes.
                 An environment variable (e.g. $MODULE HOME) gets resolved on
invocation PDTool.
                        Paths containing spaces must be enclosed in double quotes:
                               ANSWER: "$MODULE HOME/LabVCSModule.xml"
                        Given that MODULE HOME=C:/dev/Cis Deploy Tool/resources/modules,
PDTool automatically resolves the variable to
                        "C:/dev/Cis Deploy Tool/resources/modules/LabVCSModule.xml".
          c. when the parameter value is complex and the inner value contains spaces
                    i. In this example $PROJECT HOME will resolve to a path that
contains spaces such as C:/dev/Cis Deploy Tool
                        For example take the parameter -pkgfile
$PROJECT HOME$/bin/carfiles/testout.car.
```

```
# Since the entire command contains a space it must be enclosed in double quotes:

# ANSWER: "-pkgfile $PROJECT_HOME/bin/carfiles/testout.car"

# 3. A comment is designated by a # sign preceding any other text.

# a. Comments may occur on any line and will not be processed.

# 4. Blank lines are not processed

# a. Blank lines are counted as lines for display purposes

# b. If the last line of the file is blank, it is not counted for display purposes.

#
```

#### Property File Parameters:

#### Property File Example:

```
# -----
# Begin task definition list for UNIX:
PASS TRUE ExecuteAction backup export $SERVERID backup
$MODULE HOME/ArchiveModule.xml $MODULE HOME/servers.xml
# Restore
PASS TRUE ExecuteAction
                             backup import $SERVERID restore
$MODULE HOME/ArchiveModule.xml $MODULE HOME/servers.xml
# Export
    TRUE ExecuteAction
                             pkg export
                                          $SERVERID export
$MODULE HOME/ArchiveModule.xml $MODULE HOME/servers.xml
# Import
PASS TRUE ExecuteAction
                             pkg import
                                          $SERVERID import
$MODULE HOME/ArchiveModule.xml $MODULE HOME/servers.xml
```

#### **Ant Execution**

The full details on build file setup and ant execution can be found in the document "PDTool User's Guide.pdf". The abridged version is as follows:

Windows: ExecutePDTool.bat -ant ../resources/ant/build-Archive.xml Unix: ./ExecutePDTool.sh -ant ../resources/ant/build-Archive.xml

#### **Build File:**

```
<?xml version="1.0" encoding="UTF-8"?>
cproject name="PDTool" default="default" basedir=".">
```

```
<description>description</description>
 <!-- Default properties -->
 property name="SERVERID"
                                           value="localhost"/>
 cproperty name="noarguments"
                                           value="" ""/>
 <!-- Default Path properties -->
 property name="RESOURCE HOME"
                                           value="${PROJECT HOME}/resources"/>
 property name="MODULE HOME"
                                           value="${RESOURCE HOME}/modules"/>
 property name="pathToServersXML"
                                           value="${MODULE HOME}/servers.xml"/>
 cproperty name="pathToArchiveXML"
                                           value="${MODULE HOME}/ArchiveModule.xml"/>
                                           value="${MODULE HOME}/DataSourceModule.xml"/>
 property name="pathToDataSourcesXML"
 cproperty name="pathToGroupsXML"
                                          value="${MODULE HOME}/GroupModule.xml"/>
                                          value="${MODULE HOME}/PrivilegeModule.xml"/>
 cproperty name="pathToPrivilegeXML"
                                           value="${MODULE HOME}/RebindModule.xml"/>
 cproperty name="pathToRebindXML"
                                           value="${MODULE HOME}/RegressionModule.xml"/>
 cproperty name="pathToRegressionXML"
 property name="pathToResourceXML"
                                           value="${MODULE HOME}/ResourceModule.xml"/>
 property name="pathToResourceCacheXML"
                                           value="${MODULE HOME}/ResourceCacheModule.xml"/>
 cproperty name="pathToTriggerXML"
                                          value="${MODULE HOME}/TriggerModule.xml"/>
 property name="pathToUsersXML"
                                           value="${MODULE HOME}/UserModule.xml"/>
 property name="pathToVCSModuleXML"
                                           value="${MODULE HOME}/VCSModule.xml"/>
 <!-- Custom properties -->
 property name="archiveIds"
                                         value="import1"/>
 <!-- Default Classpath [Do Not Change] -->
 <path id="project.class.path">
       <fileset dir="${PROJECT HOME}/lib"><include name="**/*.jar"/></fileset>
       <fileset dir="${PROJECT HOME}/dist"><include name="**/*.jar"/></fileset>
       <fileset dir="${PROJECT HOME}/ext/ant/lib"><include name="**/*.jar"/></fileset>
 </path>
 <taskdef name="executeJavaAction" description="Execute Java Action"</pre>
classname="com.tibco.ps.deploytool.ant.CompositeAntTask" classpathref="project.class.path"/>
<!-- =======
target: default
     <target name="default" description="Update CIS with environment specific parameters">
 <!-- Windows / UNIX -->
       <executeJavaAction action="backup export"</pre>
arguments="${SERVERID}^backup1^${pathToArchiveXML}^${pathToServersXML}"
endExecutionOnTaskFailure="TRUE"/>
       <executeJavaAction action="pkg import"</pre>
arguments="${SERVERID}^import1^${pathToArchiveXML}^${pathToServersXML}"
endExecutionOnTaskFailure="TRUE"/>
       <executeJavaAction action="pkg export"</pre>
arguments="${SERVERID}^export1^${pathToArchiveXML}^${pathToServersXML}"
endExecutionOnTaskFailure="TRUE"/>
 </target>
</project>
```

## 5 PDTool Examples

The following are common scenarios when using the Archive Module.

#### Scenario 1 - Export resources from a DV instance

#### **Description:**

Utilize the Archive Module to export a series of folders from a DV instance into a DV Archive (.car) file.

#### XML Configuration Sample:

Use the ArchiveModule XML file found in the /resources/module directory. Modify the option nodes to use paths that are pertinent to your environment. The entry for export should look like something this:

#### **Execution Sample:**

Unix: ./ExecutePDTool.sh -exec ../resources/plans/UnitTest-Archive.dp Property file setup for UnitTest-Archive.dp:

```
# ------
# Begin task definition list:
# ------
# Export
PASS TRUE ExecuteAction pkg_export $SERVERID export
$MODULE HOME/ArchiveModule.xml $MODULE HOME/servers.xml
```

#### **Results Expected:**

The script will report "PASS" for the execution of this action. Check timestamp of the output file (PDTool/bin/carfiles) to make sure it is current.

#### Scenario 2 - Import a DV Archive (.car)

#### **Description:**

Utilize the Archive Module to import resources from a DV Archive (.car) file into a target DV instance

#### XML Configuration Sample:

Use the ArchiveModule XML file found in the /resources/module directory. To prove that the import worked, use DV Studio to remove a folder resource prior to executing the import. The entry for export should look like something this:

#### **Execution Sample:**

Unix: ./ExecutePDTool.sh -exec ../resources/plans/UnitTest-Archive.dp Property file setup for UnitTest-Archive.dp:

```
# ------
# Begin task definition list for UNIX:
# ------
# Import
PASS TRUE ExecuteAction    pkg_import    $SERVERID import
$MODULE_HOME/ArchiveModule.xml $MODULE_HOME/servers.xml
```

#### **Results Expected:**

The script will report "PASS" for the execution of this action. Use DV Studio to verify that the resources that were deleted previously are not present again. You may have to refresh Studio to see the imported resources.

# 6 Debugging

The following describes how to setup debugging.

Set the log4j.properties file.

INFO setting (default): Required for any of the archive print options such as "printinfo".

# DV Archive [INFO, DEBUG, WARN]

# INFO: required for any of the print options such as printinfo log4j.logger.com.compositesw.cmdline.archive=INFO

DEBUG setting: print out debug information in console window

log4j.logger.com.compositesw.cmdline.archive=DEBUG

WARN setting: print out warnings in console window (suppress INFO)

log4j.logger.com.compositesw.cmdline.archive=WARN

# 7 Exceptions

The following are common exceptions and messages that may occur.

## 8 Conclusion

#### **Concluding Remarks**

The Promotion and Deployment Tool is a set of pre-built modules intended to provide a turn-key experience for promoting DV resources from one DV instance to another. The user only requires system administration skills to operate and support. The code is transparent to operations engineers resulting in better supportability. It is easy for users to swap in different implementations of a module using the Spring framework and configuration files.

#### How you can help!

Build a module and donate the code back to Professional Services for the advancement of the "*Promotion and Deployment Tool*".