
Chapter 3 Transport Layer

1


Transport Services and Protocols

- Provide Logical Communication between application processes running on different hosts
- Transport protocols run in end systems
 - Sender side: breaks application messages into Segments, passes to network layer
 - Receiver side: reassembles segments into Messages, passes to application layer
- more than one transport protocol available to applications
 - Internet: TCP and UDP



Type of Data Deliveries

- Data link layer: logical communication between nodes
- Network layer: logical communication between hosts
- *Transport layer:*logical communication between **processes**
 - relies on, enhances, network layer services



Process-to-Process Delivery

- OS today support both multiuser and multiprogramming environments
 - Computer can run several programs at the same time
- Client-Server Paradigm
- Process on local host (client) needs services from process on remote host (server)
- Both <u>processes</u> (client and server) have the same name, ex. ftp, DNS
- For communication, we must define
 - Local Host
 - Local Process
 - Remote Host
 - **Remote** Process

Addressing

 We need address, when we need to deliver something to one specific destination among many

Data link layer : MAC address

Network Layer : IP address


Transport Layer : Port Number

- Internet model, port number are 16-bit integer between 0 and 65,535
- Client process defines itself with port number, chosen randomly called <u>ephemeral (temporary) port</u> <u>number</u>
- Server process must also define itself with port number, which cannot chosen randomly

5

Addressing (cont.)

- For Server, Internet has decided to use universal port number called <u>well-known port</u> <u>numbers</u>
- Every client process knows well-known port number




6

Addressing (cont.)

■ It should be clear that *IP addresses* and *Port Numbers* play different roles in selecting final destination of

data

- Destination IP address defines host among different hosts in the world
- Port number defines one of process on this particular host









Well-known Ports

- ranging from 0 to 1023
- Are assigned and controlled by IANA



(http://www.iana.com)

- Registered Ports
 - Ranging from 1,024 to 49,151
 - Not assigned and controlled by IANA
 - They can only be registered with IANA to prevent duplication
- Dynamic (or private) Ports
 - Ranging from 49,152 to 65,535
 - Neither controlled nor registered
 - They can be used by any process
 - These are *ephemeral ports or temporary ports*

Socket Address

 Socket Address is combination of IP Address and Port Number




- Transport layer protocol needs a pair of socket addresses: <u>client socket address</u> and <u>server socket</u> <u>address</u>
- These four pieces of information are part of IP header and Transport layer protocol header
- IP header contains IP address; UDP or TCP header contains port number

Multiplexing and Demultiplexing

Multiplexing

- There may be several processes that need to send packet
- Protocol accepts messages from different processes, differentiated by their port number


 After adding header, transport layer passes packet to network layer _ _ _ _



Multiplexing and Demultiplexing (cont.)

Demultiplexing

- Transport layer receives datagrams from network layer
- After error checking and dropping of header, transport layer delivers each message to appropriate process based on port number



11

physical


12

Multiplexing/Demultiplexing (cont.)

Demultiplexing at receiving host:

physical

Multiplexing at sending host:




host 1 host 2 host 3

physical

How demultiplexing works

- Host receives IP datagrams
 - each datagram has source IP address, destination IP address
 - each datagram carries 1 transport-layer segment
 - each segment has source, destination port number
- host uses <u>IP addresses</u> & <u>port numbers</u> to direct segment to appropriate socket



TCP/UDP segment format

13

Connectionless demultiplexing

Create sockets with port numbers:

DatagramSocket mySocket1 = new DatagramSocket(49152);

DatagramSocket mySocket2 = new DatagramSocket(49153);


UDP socket identified by twotuple:

- When host receives UDP segment:
 - checks destination port number in segment
 - directs UDP segment to socket with that port number
- IP datagrams with different source IP addresses and/or source port numbers directed to same socket

(destination IP address, destination Port number)

Connectionless demux (cont)

DatagramSocket serverSocket = new DatagramSocket(26428);




Connection-oriented demux

- TCP socket identified by 4-tuple:
 - Source IP address
 - Source Port number
 - Destination IP address
 - Destination Port number
- Receiver host uses all four values to direct segment to appropriate socket

- Server host may support many simultaneous TCP sockets:
 - each socket identified by its own 4-tuple
- Web servers have different sockets for each connecting client
 - non-persistent HTTP will have different socket for each request

Connection-oriented demux (cont)



17

Connectionless versus Connection-Oriented Service

- Connectionless Service
 - Packet are sent from one party to another with no need for connection establishment or connection release
 - Packet are not numbered
 - They may be delayed or lost or may arrive out of sequence
 - No acknowledgment
 - **UDP** is connectionless

Connectionless versus Connection-Oriented Service

- Connection-Oriented Service
 - Connection is first established between sender and receiver
 - Data are transferred; at the end, connection is released
 - Acknowledgement is needed
 - **TCP** is connection-oriented protocol

20

Reliable versus Unreliable

- Transport layer service can be reliable or unreliable
- Reliable transport layer protocol
 - implementing flow and error control at transport layer
 - Slower and more complex service
- Unreliable transport layer protocol
 - No flow and error control
 - Faster service

Reliable versus Unreliable (cont.)

Question?

■ If data link layer is reliable and has flow and error control, do we need this at transport layer, too?

— Error is checked in these paths by the data link layer

Transport
Network
Data link
Physical

AN

WAN

WAN

LAN

Error is not checked in these paths by the data link layer

Transport
Network
Data link
Physical


Answer

- Reliability at data link layer is between two nodes
- We need reliability between two ends
- Because network layer in Internet is unreliable (besteffort delivery), we need to implement reliability at transport layer

22

Internet Transport-layer Protocols

- Reliable, in-order delivery: (Transmission Control Protocol, TCP)
 - Connection setup
 - Flow control
 - Error control
 - Congestion control
- Unreliable, unordered delivery: (User Datagram Protocol, UDP)
 - no-frills extension of "best-effort" IP
 - No connection setup
 - No flow control
 - No error control
 - No congestion control
- services not available:
 - delay guarantees
 - bandwidth guarantees



UDP: User Datagram Protocol [RFC 768]

- UDP does not add anything to service of Internet Protocol except to provide process-to-process communication
- Unreliable transport Protocol (best effort service), UDP segments may be:
 - lost
 - delivered out of order to application
- connectionless:
 - no handshaking between UDP sender, receiver
 - each UDP segment handled independently of others

24

UDP: User Datagram Protocol

Why is there a UDP?

- No connection establishment (which can add delay)
- Simple protocol using minumum of overhead: no connection state at sender, receiver
- small segment header
- no congestion control: UDP can blast away as fast as desired


Well-Known Ports for UDP

Port	Protocol	Description
7	Echo	Echoes a received datagram back to the sender
9	Discard	Discards any datagram that is received
11	Users	Active users
13	Daytime	Returns the date and the time
17	Quote	Returns a quote of the day
19	Chargen	Returns a string of characters
53	Nameserver	Domain Name Service
67	BOOTPs	Server port to download bootstrap information
68	ВООТРС	Client port to download bootstrap information
69	TFTP	Trivial File Transfer Protocol
111	RPC	Remote Procedure Call
123	NTP	Network Time Protocol
161	SNMP	Simple Network Management Protocol
162	SNMP	Simple Network Management Protocol (trap)

26

UDP Segment Format

UDP segments have fixed-size header of 8 bytes



- **Total length** defines total length of UDP segment, <u>header plus data</u>
- Checksum is used to detect error over the entire segment (header plus data)

UDP checksum

Goal: detect "errors" (e.g., flipped bits) in transmitted segment

Sender:

- treat segment contents as sequence of 16-bit integers
- Checksum: addition (1's complement sum) of segment contents
- Sender puts checksum value into UDP checksum field


Receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - NO error detected
 - YES no error detected.

_**)**(


Internet Checksum Example

- Note
 - When adding numbers, a carry out from the most significant bit needs to be added to the result
- Example: add two 16-bit integers



Principles of Reliable Data Transfer


• important in application, transport, link layers



 characteristics of unreliable channel will determine complexity of Reliable Data Transfer protocol (rdt)

39


Reliable Data Transfer: getting started



Reliable Data Transfer: getting started

We'11:


- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
 - but control info will flow on both directions!
- use Finite State Machines (FSM) to specify sender,




Rdt1.0: reliable transfer over a reliable channel

• underlying channel perfectly reliable

- no bit errors
- no loss of packets
- separate FSMs for sender, receiver:



- sender sends data into underlying channel
- receiver read data from underlying channel




Rdt2.0: channel with bit errors

- Underlying channel may flip bits in packet
 - Checksum to detect bit errors
- Question: how to recover from errors:
 - *ACKnowledgements (ACKs)*: receiver explicitly tells sender that packet received OK
 - Negative ACKnowledgements (NAKs): receiver explicitly tells sender that packet has errors
 - sender retransmits packet on receipt of NAK
- new mechanisms in rdt2.0 (beyond rdt1.0):
 - Error Detection
 - Receiver Feedback:
 - control messages (ACK,NAK) receiver->sender


43

rdt2.0: FSM specification




44

rdt2.0: operation with no errors



rdt2.0: error scenario



rdt2.0 has a fatal flaw!

What happens if ACK/NAK corrupted?

- Sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate

Handling duplicates:

- sender retransmits current pkt if ACK/NAK garbled
- sender adds Sequence Number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt

stop and wait

Sender sends one packet, then waits for receiver response

47

rdt3.0: channels with errors and loss

New assumption:

underlying channel can also lose packets (data or ACKs)


 checksum, seq. #, ACKs, retransmissions will be of help

But not enough


Approach: sender waits "reasonable" amount of time for ACK

- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
 - retransmission will be duplicate, but use of seq. #'s already handles this
 - receiver must specify seq # of pkt being ACKed
- requires countdown timer


rdt3.0 sender



rdt3.0 in action




rdt3.0 in action




56

TCP Services

- Process-to-Process Communication
- Stream Delivery Service
 - TCP allows sending process to delivery data as a stream of bytes and allows receiving process to obtain data as a stream of bytes
 - TCP creates an environment in which two process seem to be connected that carries data across Internet



TCP Services: Stream Delivery Service (continued)




Sending and Receiving Buffers

- Because sending and receiving processes may not write or read data at the same speed, TCP needs buffers for storage
- There are two buffers, sending buffer and receiving buffer
- Buffers are also necessary for flow and error control mechanisms used by TCP

59

TCP Services: Stream Delivery Service (continued)



Segment

- TCP groups a number of bytes together into a packet called Segment
- TCP adds header to each segment (for control purposes) and delivers segment to IP layer for transmission
- Segment are encapsulated in IP datagram and transmitted
- The entire operation is transparent to receiving process

TCP Services (continued)

- TCP offers full-duplex service
 - Data can flow in both directions at the same time
 - Each TCP has sending and receiving buffer and segments move in both direction
- Connection-Oriented Service
 - Before sending and receiving data, following processes occur
 - Two TCP establish a connection between them
 - Data are exchanged in both directions
 - Connection is terminated
- Reliable Service
 - TCP is reliable transport protocol by using acknowledgement mechanism

61

TCP Segment Structure

source port # dest port #

sequence number

acknowledgement number

head not len used UAPRSF Receive window
checksum Urg data pnter

Options (variable length)

application
data
(variable length)

- Source and Destination ports this identifies the upper layer applications using the connection
- Sequence Number this 32-bit number ensures that data is correctly sequenced.
- Each byte of data is assigned a sequence number.
- Acknowledgement Number this 32-bit number indicates next sequence number that sending device is expecting from the other station.

TCP Segment Structure

32 bits

source port # dest port #

sequence number

acknowledgement number

head not UAPRSF Receive window
checksum Urg data pnter

Options (variable length)

application data (variable length)

- Header Length(4 bits)- No.of 4 byte words in TCP header length 20-60 bytes
- Reserved (6 bits) always set to 0 (for future use)
- Code bits (6 bits)
 - URG-value of Urgent Pointer field is valid
 - ACK-value of acknowledgement field is valid
 - PSH-to let receiving TCP know that segment includes data that must be delivered to receiving application program as soon as possible and not to wait for more data to come (generally not used)
 - RST-Reset connection
 - SYN-Synchronize sequence number during connection
 - FIN-Terminate connection

64

TCP Segment Structure

_____ 32 bits

source port # dest port #

sequence number

acknowledgement number

head not UAPRSF Receive window


checksum Urg data pnter

Options (variable length)

application data (variable length)

- Receive window (16 bits)
 - Number of bytes receiver willing to accept
 - indicates range of acceptable sequence numbers beyond last segment that was successfully received.
 - It is allowed number of octets that sender of ACK is willing to accept before acknowledgement.
- Urgent Data Pointer (16 bits)-
 - shows end of urgent data so that interrupted data streams can continue
 - When URG bit is set, data is given priority over other data streams

TCP Segment Structure



TCP Features

- To provide services mentioned in previous section, TCP has several features as follows:
 - Numbering System
 - Flow Control
 - Error Control
 - Congestion Control

TCP Features: Numbering System

- Although TCP keeps track of segments being transmitted or received
- No field for segment number value in segment header
- Instead, there are two field called
 - Sequence Number

refer to byte number

Acknowledgement Number

and not segment number

- Bytes of data being transferred in each connection are numbered by TCP
- Numbering starts with a randomly generated number. $(0-2^{32}-1)$
 - Ex. Random generate No. = 1,057, for 6,000 bytes data
 - Range of data is start from 1,057 to 7,056

68

TCP Features: Numbering System

- What is Sequence Number
 - After bytes have been numbered, TCP assigns a sequence number to each segment that is being sent
- Sequence number for each segment is number of the first byte carried in that segment

TCP Features: Numbering System

- Example :
 - Suppose TCP connection is transferring file of 5,000 bytes.
 - The first byte is numbered 10001.
 - What are sequence numbers for each segment if data is sent in five segments, each carrying 1000 bytes?

```
| 10,001-11,000 | 11,001-12,000 | 12,001-13,000 | 13,001-14,000 | 14,001-15,000 | 1--1,000 bytes----|
|---1,000 bytes----|
| Segment 1 → Sequence Number: 10,001 (range: 10,001 to 11,000) |
| Segment 2 → Sequence Number: 11,001 (range: 11,001 to 12,000) |
| Segment 3 → Sequence Number: 12,001 (range: 12,001 to 13,000) |
| Segment 4 → Sequence Number: 13,001 (range: 13,001 to 14,000) |
| Segment 5 → Sequence Number: 14,001 (range: 14,001 to 15,000) |
```

Value of sequence number field of segment defines number of the first data byte contained in that segment

TCP Features : Numbering System

What is Acknowledgment Number?

> Value of acknowledgment field in segment defines number of next byte a party expects to receive

Acknowledgment number is cumulative Host A Host B Seq=10,001 ACK=11,001 Seq=11,001 ACK=12,001

10,001-11,000 | 11,001-12,000 | 12,001-13,000 | 13,001-14,000 | 14,001-15,000

71

70


TCP Sequence Number and Acknowledgement Number (ACK)

Seq. #'s:

byte stream "number" of first byte in segment's data

ACKs:

- seq # of next byte expected from other side
- cumulative ACK



When Segment carries a combination of data and control information

called "Piggybacking"

TCP Round Trip Time and Timeout

Q: how to set TCP timeout value?

- longer than RTT
 - but RTT varies
- too short: premature timeout
 - unnecessary retransmissions
- too long: slow reaction to segment loss

- O: how to estimate RTT?
- SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT

72

TCP Round Trip Time and Timeout


EstimatedRTT = $(1-\alpha)$ *EstimatedRTT + α *SampleRTT

- Exponential weighted moving average
- influence of past sample decreases exponentially fast
- typical value: $\alpha = 0.125$ [(1- α) = 0.875]

74

Example RTT estimation:

RTT: gaia.cs.umass.edu to fantasia.eurecom.fr



TCP Round Trip Time and Timeout

- Setting the timeout
- EstimtedRTT plus "safety margin"
 - large variation in EstimatedRTT -> larger safety margin
- first estimate of how much SampleRTT deviates from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

Then set timeout interval:

```
TimeoutInterval = EstimatedRTT + 4*DevRTT
```

76

TCP reliable data transfer

- TCP creates reliable data transfer (rdt) service on top of IP's unreliable service
- Pipelined segments
- Cumulative acknowledges
- TCP uses single retransmission timer

- Retransmissions are triggered by:
 - Timeout events
 - Duplicate acknowledges
- Initially consider simplified TCP sender:
 - ignore duplicate acknowledges
 - ignore flow control, congestion control

7

TCP sender events:

Data received from app:

- Create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running (think of timer as for oldest unacked segment)
- expiration interval: TimeOutInterval

Timeout:


- retransmit segment that caused timeout
- restart timer

Ack received:

- If acknowledges previously unacked segments
 - update what is known to be acked
 - start timer if there are outstanding segments

TCP sender NextSeqNum = InitialSeqNum SendBase = InitialSeqNum (simplified) loop (forever) { switch(event) event: data received from application above Seq=92, 8 bytes data create TCP segment with sequence number NextSegNum if (timer currently not running) SendBase= start timer pass segment to IP NextSeqNum = NextSeqNum + length(data) event: timer timeout Seq=92, 8 bytes data retransmit not-yet-acknowledged segment with smallest sequence number SendBase= start timer event: ACK received, with ACK field value of y ACK=100 if (y > SendBase) { SendBase = y if (there are currently not-yet-acknowledged segments) start timer SendBase=100. Lost ACK scenario } /* end of loop forever */

```
TCP sender
NextSeqNum = InitialSeqNum
SendBase = InitialSegNum
                                                                      (simplified)
loop (forever) {
  switch(event)
                                                                                      Host B
                                                                             SendBase
  event: data received from application above
                                                                        Seq=92, 8 bytes data
      create TCP segment with sequence number NextSegNum
      if (timer currently not running)
                                                                        Seq≈100, 20 bytes data
                                                                 Seq=92 timeout
                                                SendBase=92
         start timer
      pass segment to IP
      NextSeqNum = NextSeqNum + length(data)
  event: timer timeout
                                                                        Seq=92, 8 bytes data
      retransmit not-yet-acknowledged segment with
           smallest sequence number
                                                     Sendbase
                                                       = 100
      start timer
                                                                  Seq=92 timeout
                                                      SendBase
                                                                                  ACK=120
                                                        = 120
  event: ACK received, with ACK field value of y
      if (y > SendBase) {
         SendBase = y
         if (there are currently not-yet-acknowledged segments)
SendBase
               start timer
                                                        = 120
                                                                 time Premature timeout
} /* end of loop forever */
                                                                                             80
```



Fast Retransmit

- Time-out period often relatively long:
 - long delay before resending lost packet
- Detect lost segments via duplicate ACKs.
 - Sender often sends many segments backto-back
 - If segment is lost, there will likely be many duplicate ACKs.

already ACKed segment

- If sender receives 3 ACKs for the same data, it supposes that segment after ACKed data was lost:
 - Fast Retransmit: resend segment before timer expires

ใหว

Fast retransmit algorithm:

```
event: ACK received, with ACK field value of y


if (y > SendBase) {
    SendBase = y
    if (there are currently not-yet-acknowledged segments)
        start timer
    }
    else {
        increment count of dup ACKs received for y
        if (count of dup ACKs received for y = 3) {
            resend segment with sequence number y
        }

a duplicate ACK for

fast retransmit
```

TCP Flow Control


receive side of TCP connection has a receive buffer: -Flow Control
sender won't overflow
receiver's buffer by
transmitting too much,
too fast



 application process may be slow at reading from buffer speed-matching service: matching the send rate to the receiving app's drain rate


84

TCP Flow control: how it works




(Suppose TCP receiver discards out-of-order segments)





85

TCP Flow control: how it works




TCP Connection

- TCP is connection-oriented.
- Connection-oriented transport protocol establishes virtual path between source and destination.
- All of segments belonging to message are then sent over this virtual path.
- Connection-oriented transmission requires three phases:
 - Connection Establishment,
 - Data transfer, and
 - Connection Termination.

87


Connection Establishment using Three-Way Handshaking




- SYN segment cannot carry data, but it consumes one sequence number.
- SYN + ACK segment cannot carry data, but does consume one sequence number
- ACK segment, if carrying no data, consumes no sequence number.

88

Data Transfer




Connection termination using three-way handshaking



- FIN segment consumes one sequence number if it does not carry data.
- FIN + ACK segment consumes one sequence number if it does not carry data
- ACK segment, if carrying no data, consumes no sequence number


90

Half-Close



- In TCP, one end can stop sending data while still receiving data called <u>Half-</u> <u>close</u>
- Client half-close connection by sending FIN segment
- Server accepts this halfclose by sending ACK segment
- Data transfer from client to server stops
- Server can still send data
- After sending all data, server sends FIN segment, which is acknowledged by ACK from client

Connection Establishment and Termination




Principles of Congestion Control

Congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- Congestion control refers to mechanisms and techniques to keep load below capacity.


Router Queues



- Packet is placed at end of input queue while waiting to be checked
- Processing module of router removes packet from input queue one it reaches the front of queue and uses its routing table and destination address to find route
- Packet is put in appropriate output queue and waits its turn to be sent

98

Network Performance



- Congestion control involves two factors that measure performance of network
 - Delay
 - Throughput number of packets passing through network in a unit of time

Approaches towards congestion control

Two broad approaches towards congestion control:

- 1. Network-assisted congestion control:
- routers provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN (Explicit Congestion Notification), ATM)

2. End-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed <u>loss</u>, <u>delay</u>
- approach taken by TCP


105

Case study: ATM ABR congestion control

ABR: Available Bit Rate:

- "elastic service"
- if sender's path "underloaded":
 - sender should use available bandwidth
- if sender's path congested:
 - sender throttled to minimum guaranteed rate

Case study: ATM ABR congestion control




RM (Resource Management) cells:

- Sent by sender, interspersed with data cells (one RM cell every 32 data cell)
- bits in RM cell set by switches ("network-assisted")
 - NI bit: no increase in rate (mild congestion)
 - CI bit: congestion indication
- two-byte ER (Explicit Rate) field in RM cell
 - congested switch may lower ER value in cell
 - sender' send rate thus maximum supportable rate on path
- RM cells returned to sender by receiver, with bits intact

107

Case study: ATM ABR congestion control



■ EFCI bit in data cells:


- Each data cell contains an Explicit Forward Congestion Indication (EFCI) bit
- EFCI bit may be set to 1 in congested switch
- if data cell preceding RM cell has EFCI set, receiver sets CI bit in returned RM cell

<u> 10</u>8

TCP Congestion Control: Additive Increase (AI), Multiplicative Decrease (MD)


- Approach: increase transmission rate (window size), probing for usable bandwidth, until loss occurs
 - additive increase: increase CongWin by 1 MSS every RTT until loss detected
 - multiplicative decrease: cut CongWin in half after loss

Saw tooth behavior: probing for bandwidth




109

Slow Start, exponential increase



- When connection begins, increase rate exponentially until first loss event:
 - double Congestion Windows (cwnd) every RTT
 - done by incrementing cwnd for every ACK received
- Summary: initial rate is slow but ramps up exponentially fast 110

Congestion Avoidance, additive increase




 In congestion avoidance algorithm size of congestion window (cwnd) increases additively until congestion is detected

111

Most implementations react differently to congestion detection:


- If detection is by time-out, a new slow start phase starts
- If detection is by three ACKs, a new congestion avoidance phase starts
- Mechanism
 - AIMD (Additive Increase, Multiplicative Decrease)
 - Slow Start (SS)
 - Congestion Avoidance

TCP congestion policy summary



113

Congestion example



Summary: TCP Congestion Control

- When CongestionWindow(cwnd) is below Threshold, sender in slow-start phase, window grows exponentially
- When cwnd is above Threshold, sender is in congestion-avoidance phase, window grows linearly
- When triple duplicate ACK occurs, Threshold set to cwnd/2 and cwnd set to Threshold
- When timeout occurs, Threshold set to cwnd/2 and cwnd is set to 1 MSS

120