TOWiOS The Only Way is Open Source

MOODLE UPGRADE - UBUNTU 23.04 LTS

February 2024

- 1> CHECK FOR NEWER MOODLE VERSION, & DOWNLOAD
- 2> ENABLE 'MAINTENANCE MODE'
- 3> BACKUP CURRENT MOODLE SITE
- 4> EXTRACT THE MOODLE DOWNLOAD, RESTORE FILES & SET PERMISSIONS
- 5> INSTALL THE MOODLE UPGRADE
- 6> DISABLE 'MAINTENANCE MODE'



Note:

The following websites have been used for reference:

- https://download.moodle.org/
- https://docs.moodle.org/403/en/Administration via command line

The following instructions are to upgrade Moodle VLE locally on Ubuntu.

If you use these instructions you do so at your own risk. They are not considered 'perfect', and are purely for testing purposes.

1> CHECK FOR NEWER MOODLE VERSION, & DOWNLOAD

Go to your Moodle site:

http://localhost/moodle


Log in with an administrative account:

User:

Password:

Check for new Moodle release and compatibility:

Go to: Site administration > General (tab) > Notifications



Select a newer Moodle version to 'Download':

In this instance, 4.3+

This will then proceed to download a moodle zip file to the users Downloads directory.

Note: URL & credentials may differ. This set of instructions is based on the previous guide, Moodle Installation.

2> ENABLE 'MAINTENANCE MODE' Inform users site is offline: Site Administration > Server > Maintenance Mode. Maintenance Mode = 'Enable'. Enter an 'Optional Maintenance Message' = This will be seen by users who navigate to the site to log Save changes _ D X O localhost/moodle/admin/settings.php?section=maintenancemode ⊍ ⊻ ② ጏ ≡ The Only Way is Open Source Home Dashboard My courses Site administration ♣ **●** AU ∨ Edit mode ● **TOWiOS** Q Search General Users Courses Grades Plugins Appearance Server Reports Development Maintenance mode Maintenance mode Disable Default: Disable For upgrades and other work Edit View Insert Format Tools Table Help 6 words tiny / Default: Empty When users browse to the Moodle Site they will be presented with: Private browsing ¬ □ × O localhost/moodle/ 90% 🏠 **TOWIOS**

The site is undergoing maintenance and is currently not available

This site will be temporarily unavailable.

Note: This step is not a requirement but will help inform users as to why the site is inaccessible.

3> BACKUP CURRENT MOODLE SITE

Open a 'konsole' (aka Terminal/Command Prompt) & switch user:

su

Locate your moodle site:

sudo find / -type d -name "moodle"

```
towios@ubuntu-moodle:~$ sudo find / -type d -name "moodle"
/var/www/html/moodle
/var/www/html/moodle/admin/tool/componentlibrary/content/static/moodle
/var/www/html/moodle/admin/tool/componentlibrary/content/moodle
/var/www/html/moodle/theme/boost/scss/moodle
/var/lib/mysql/moodle
find: '/run/user/1000/gvfs': Permission denied
find: '/run/user/1000/doc': Permission denied
```

Create a backup directory to move the current moodle site to:

sudo mkdir /var/www/backup

Move the moodle directory to the backup location and rename it too:

sudo my /var/www/html/moodle /var/www/backup/moodle_backup

Note: In this instance moodle is located within /var/www/html based on the locate command.

4> EXTRACT THE MOODLE DOWNLOAD, RESTORE FILES, & SET PERMISSIONS

Extract the downloaded moodle file to the web server:

(Replace <u>username</u> and <u>file name</u> accordingly) sudo unzip /home/<u>username</u>/Downloads/<u>moodle-latest-403.zip</u> -d /var/www/html/

Restore the config.php from backup to new moodle:

sudo cp /var/www/backup/moodle_backup/config.php /var/www/html/moodle/

(Optional) Restore your theme(s) from backup to new moodle:

sudo cp -pr /var/www/backup/moodle_backup/theme/mytheme /var/www/html/moodle/theme/mytheme

(Optional) Restore your module(s) from backup to new moodle:

sudo cp -pr /var/www/backup/moodle_backup/mod/mymod /var/www/html/moodle/mod/mymod

Set permissions for moodle:

- sudo chown -R root:root /var/www/html/moodle
- sudo chmod -R 755 /var/www/html/moodle

(Optional) Restart web server:

sudo systemctl restart apache2

Note: Make moodle/config.php (and the rest of the source code) readable by your www server. For maximum security the files should not be writeable by your server. This is especially important on a 'production' server open to the public internet.

5> INSTALL THE MOODLE UPGRADE Go to your Moodle site to trigger the upgrade: http://localhost/moodle/admin Confirm the server upgrade: Continue ♠ Administration | The Only × ← → C O localhost/moodle/admin/index.php **Upgrading Moodle database from version** 4.2.2+ (Build: 20230929) (2023042402.12) to 4.3.2+ (Build: 20240202) (2023100902.06) Confirm Your Moodle files have been changed, and you are about to automatically upgrade your server to this 4.3.2+ (Build: 20240202) (2023100902.06) Once you do this you can not go back again. Please note that this process can take a long time. Are you sure you want to upgrade this server to this version? Cancel Continue Server Checks: Continue (Checks server meets requirements _ D X ○ localhost/moodle/admin/index.php?cache=0&confirmupgrade= 50% ☆ රු ≡ **Current release information** Moodle 4.3.2+ (Build: 20240202) Server checks

Other checks


site not https 📳 if this test fails, it indicates a potential problem

(OK)


®

• Plugins Check: Upgrade Moodle database now

(Detects any plugins that need 'attention'. At this stage if any plugins are flagged, e.g if there is an update available - press download next to the offending plugin - this will download the latest plugin, placing it within your Downloads directory.)




• **Upgrading:** Continue (Note this can take some time.)



• New settings: Save changes

(Additional settings added to your moodle site. You can configure these now, or later.)



! THE UPGRADE IS COMPLETE AND YOU ARE RETURNED TO THE NOTIFICATION PAGE!

• Identify the version of Moodle now in use: Select the '?' mark icon for further details

