CAmkES tutorials bug fixes

Page Content

- hello-camkes-0 Tutorial
- Timer Tutorial

hello-camkes-0 Tutorial

When trying to build and run the tutorial from https://docs.sel4.systems/Tutorials/hello-camkes-0.html. with

```
# In build directory
ninja
```

the process gets stuck without an error message.

- **Expected behavior:** after the ninja command it should have successfully built the hello-camkes-0 tutorial
- **Real behavior:** The process gets stuck running the "ninja" command without displaying any error message.
- **Cause:** The exact cause did not become clear during bugfixing. It is possible that specifying the "`--plat`" parameter in the command "`./init --tut hello-world`" (as shown in the example code) could have led to this behavior.
- **Fix:** What helped was to specify the platform with the "`--plat pc99`" directly (even though this should already be the default value).

> This issue seems to be more general as I have faced it in the sel4 threads tutorial. Selecting the pc99 platform seems to fix the problem.
>
> In my case it code stuck on the following step:
>
> ```
> in-container:/host$ ./init --tut threads...in-container:/host$ cd threads_build/in-container:/host
> /threads_build$ ninja...
> [181/189] Generating capDL-tool/parse-capDL
> ```

Timer Tutorial

Unfortunately, the timer tutorial (https://docs.sel4.systems/Tutorials/hello-camkes-timer.html) has a bug:

- **Expected behavior:** after the main thread starts the program should print

  ```
  ------Sleep for X seconds------
  ```

  and with a delay of x seconds a second message

  ```
  After the client: wakeup
  ```

- **Real behavior:** the program prints out the 2 messages without a delay.
- **Cause:**
  - `ttc_start()` starts the timer and it immediately generates an interrupt
  - in the `irq_handle()` we release the semaphore and stop the timer
  - the timer will not generate interrupts anymore and the semaphore is not locked so the delay in the hello sleep will not occur. `hello_sleep()` is executed after the `hello_init()` and `irq_handle()`
- **Fix:**
  - remove the `ttc_start()` function from `hello_init()`
  - move it to `hello_sleep()` after the `ttc_set_timeout()` (we first define the delay and then start the timer)
  - `ttc_stop()` in `irq_handle()` is not necessary because we define the timeout as not periodic in, as the last argument passed to `ttc_set_timeout(ttc_t *ttc, uint64_t ns, bool periodic)` is false. But it will not break the functionality