Fade2.5D

v2.13

Generated by Doxygen 1.9.1

1 Main Page 1

1.1 C++ Delaunay Triangulation and Voronoi library Fade2.5D . . . 1

1.1.1 Using the C++ Constrained Delaunay triangulation library: . . . 1

1.1.2 Compiling and Linking the Library under Windows: . . . 2

1.1.3 Compiling and Linking the Library under Linux and Mac: . . . 2

1.1.4 Directory Contents . . . 3

1.1.5 Troubleshooting . . . 3

1.1.6 Release notes / History . . . 3

2 Module Index 16

2.1 Modules . . . 16

3 Class Index 16

3.1 Class List . . . 16

4 File Index 18

4.1 File List . . . 18

5 Module Documentation 19

5.1 Tools . . . 19

5.1.1 Detailed Description . . . 20

5.1.2 Function Documentation . . . 20

5.2 Version Information . . . 25

5.2.1 Detailed Description . . . 25

5.3 File I/O . . . 25

5.3.1 Detailed Description . . . 26

5.3.2 Function Documentation . . . 26

5.4 Test Data Generators . . . 30

5.4.1 Detailed Description . . . 30

5.4.2 Generate random polygons and other test objects . . . 30

5.4.3 Function Documentation . . . 30

6 Class Documentation 37

6.1 GEOM_FADE25D::Bbox2 Class Reference . . . 37

6.1.1 Constructor & Destructor Documentation . . . 38

6.1.2 Member Function Documentation . . . 39

6.1.3 Friends And Related Function Documentation . . . 42

6.2 GEOM_FADE25D::CAF_Component Class Reference . . . 42

6.2.1 Detailed Description . . . 43

6.2.2 Member Function Documentation . . . 43

6.3 GEOM_FADE25D::Circle2 Class Reference . . . 44

6.3.1 Detailed Description . . . 44

6.3.2 Constructor & Destructor Documentation . . . 44

6.3.3 Member Function Documentation . . . 45

6.4 GEOM_FADE25D::CloudPrepare Class Reference . . . 45
6.4.1 Detailed Description . . . 46
6.4.2 Member Function Documentation . . . 47
6.5 GEOM_FADE25D::Color Class Reference . . . 50
6.5.1 Detailed Description . . . 51
6.5.2 Constructor & Destructor Documentation . . . 51
6.6 GEOM_FADE25D::CompPolygon Struct Reference . . . 52
6.6.1 Detailed Description . . . 52
6.7 GEOM_FADE25D::ConstraintGraph2 Class Reference . . . 52
6.7.1 Detailed Description . . . 53
6.7.2 Member Function Documentation . . . 53
6.8 GEOM_FADE25D::ConstraintSegment2 Class Reference . . . 56
6.8.1 Detailed Description . . . 56
6.8.2 Member Function Documentation . . . 57
6.9 GEOM_FADE25D::CutAndFill Class Reference . . . 57
6.9.1 Detailed Description . . . 58
6.9.2 Constructor & Destructor Documentation . . . 58
6.9.3 Member Function Documentation . . . 59
6.10 GEOM_FADE25D::Edge2 Class Reference . . . 62
6.10.1 Constructor & Destructor Documentation . . . 63
6.10.2 Member Function Documentation . . . 63
6.11 GEOM_FADE25D::EfficientModel Class Reference . . . 64
6.11.1 Detailed Description . . . 65
6.11.2 Member Function Documentation . . . 65
6.12 GEOM_FADE25D::Fade_2D Class Reference . . . 67
6.12.1 Detailed Description . . . 70
6.12.2 Constructor & Destructor Documentation . . . 70
6.12.3 Member Function Documentation . . . 70
6.13 GEOM_FADE25D::FadeExport Struct Reference . . . 91
6.13.1 Detailed Description . . . 92
6.13.2 Member Function Documentation . . . 92
6.14 GEOM_FADE25D::Func_gtEdge2D Struct Reference . . . 93
6.15 GEOM_FADE25D::Func_ltEdge25D Struct Reference . . . 93
6.16 GEOM_FADE25D::Func_ltEdge2D Struct Reference . . . 93
6.17 GEOM_FADE25D::Func_ltPointXYZ Struct Reference . . . 94
6.18 GEOM_FADE25D::IsoContours Class Reference . . . 94
6.18.1 Detailed Description . . . 94
6.18.2 Constructor & Destructor Documentation . . . 94
6.18.3 Member Function Documentation . . . 95
6.19 GEOM_FADE25D::Label Class Reference . . . 95
6.19.1 Detailed Description . . . 96
6.19.2 Constructor & Destructor Documentation . . . 96

6.20 GEOM_FADE25D::MeshGenParams Class Reference . . . 96
6.20.1 Detailed Description . . . 97
6.20.2 Member Function Documentation . . . 97
6.20.3 Member Data Documentation . . . 99
6.21 GEOM_FADE25D::MsgBase Class Reference . . . 101
6.21.1 Detailed Description . . . 101
6.21.2 Member Function Documentation . . . 102
6.22 GEOM_FADE25D::PeelPredicateTS Class Reference . . . 102
6.22.1 Detailed Description . . . 102
6.23 GEOM_FADE25D::Point2 Class Reference . . . 102
6.23.1 Detailed Description . . . 104
6.23.2 Constructor & Destructor Documentation . . . 104
6.23.3 Member Function Documentation . . . 104
6.24 GEOM_FADE25D::PShape Class Reference . . . 108
6.24.1 Detailed Description . . . 108
6.25 GEOM_FADE25D::Segment2 Class Reference . . . 108
6.25.1 Constructor & Destructor Documentation . . . 108
6.25.2 Member Function Documentation . . . 109
6.26 GEOM_FADE25D::SegmentChecker Class Reference . . . 110
6.26.1 Detailed Description . . . 110
6.26.2 Constructor & Destructor Documentation . . . 111
6.26.3 Member Function Documentation . . . 112
6.27 GEOM_FADE25D::Triangle2 Class Reference . . . 118
6.27.1 Detailed Description . . . 119
6.27.2 Member Function Documentation . . . 120
6.28 GEOM_FADE25D::TriangleAroundVertexIterator Class Reference . . . 124
6.28.1 Detailed Description . . . 124
6.28.2 Constructor & Destructor Documentation . . . 125
6.28.3 Member Function Documentation . . . 125
6.29 GEOM_FADE25D::UserPredicateT Class Reference . . . 127
6.29.1 Detailed Description . . . 127
6.30 GEOM_FADE25D::Vector2 Class Reference . . . 127
6.30.1 Detailed Description . . . 128
6.30.2 Constructor & Destructor Documentation . . . 128
6.30.3 Member Function Documentation . . . 128
6.31 GEOM_FADE25D::Visualizer2 Class Reference . . . 128
6.31.1 Detailed Description . . . 130
6.31.2 Constructor & Destructor Documentation . . . 131
6.31.3 Member Function Documentation . . . 131
6.32 GEOM_FADE25D::Visualizer3 Class Reference . . . 135
6.33 GEOM_FADE25D::VtxColor Struct Reference . . . 137
6.34 GEOM_FADE25D::Zone2 Class Reference . . . 137

6.34.1 Detailed Description . . . 139
6.34.2 Member Function Documentation . . . 139
6.34.3 Friends And Related Function Documentation . . . 145

7 File Documentation **146**

7.1 Bbox2.h File Reference . . . 146
7.1.1 Function Documentation . . . 147
7.2 CAF_Component.h File Reference . . . 147
7.2.1 Enumeration Type Documentation . . . 147
7.2.2 Function Documentation . . . 148
7.3 Circle2.h File Reference . . . 148
7.4 CloudPrepare.h File Reference . . . 148
7.4.1 Enumeration Type Documentation . . . 148
7.5 Color.h File Reference . . . 149
7.6 ConstraintGraph2.h File Reference . . . 149
7.7 ConstraintSegment2.h File Reference . . . 149
7.7.1 Enumeration Type Documentation . . . 150
7.8 CutAndFill.h File Reference . . . 150
7.9 Edge2.h File Reference . . . 150
7.10 EfficientModel.h File Reference . . . 151
7.10.1 Enumeration Type Documentation . . . 151
7.11 Fade_2D.h File Reference . . . 151
7.11.1 Detailed Description . . . 152
7.11.2 Function Documentation . . . 152
7.12 FadeExport.h File Reference . . . 152
7.13 freeFunctions.h File Reference . . . 153
7.13.1 Function Documentation . . . 155
7.14 IsoContours.h File Reference . . . 157
7.15 Label.h File Reference . . . 157
7.16 MeshGenParams.h File Reference . . . 157
7.16.1 Function Documentation . . . 158
7.17 MsgBase.h File Reference . . . 158
7.18 Performance.h File Reference . . . 158
7.18.1 Function Documentation . . . 158
7.19 Point2.h File Reference . . . 158
7.19.1 Function Documentation . . . 159
7.20 PShape.h File Reference . . . 160
7.21 Segment2.h File Reference . . . 160
7.22 SegmentChecker.h File Reference . . . 161
7.22.1 Enumeration Type Documentation . . . 161
7.23 testDataGenerators.h File Reference . . . 162
7.24 Triangle2.h File Reference . . . 162

7.24.1 Enumeration Type Documentation . . . 162
7.25 TriangleAroundVertexIterator.h File Reference . . . 164
7.26 UserPredicates.h File Reference . . . 164
7.27 Vector2.h File Reference . . . 164
7.27.1 Function Documentation . . . 165
7.28 Visualizer2.h File Reference . . . 165
7.29 Visualizer3.h File Reference . . . 166
7.30 Zone2.h File Reference . . . 166
7.30.1 Enumeration Type Documentation . . . 166
7.30.2 Function Documentation . . . 167

Index **169**

1 Main Page

1.1 C++ Delaunay Triangulation and Voronoi library Fade2.5D

- Fast C++ Delaunay triangulation library for 2D and 2.5D point clouds, see the benchmark
- Free Student license. Commercial licenses and support are available.
- For Windows (Visual Studio, MinGW), macOS and iOS, Linux (GCC) on PC and Raspberry PI
- Easy to use, a minimal example is:

```
#include <Fade_2D.h>
#include <stdio.h>
using namespace GEOM_FADE2D;
int main()
{
    Fade_2D dt;
    // Create and insert 4 points
    Point2 p0(0.0,0.0);
    Point2 p1(0.0,1.0);
    Point2 p3(2,0.5);
    Point2 p2(0.5,0.5);
    dt.insert(p0);
    dt.insert(p1);
    dt.insert(p2);
    dt.insert(p3);
    // Draw
    dt.show("example.pdf");
    return 0;
}
```

- C++ examples included: - 2D Delaunay triangulations and Voronoi diagrams, - 2.5D triangulations for lifted point clouds, - Practical C++ Meshing examples solving real user tasks.

1.1.1 Using the C++ Constrained Delaunay triangulation library:

- Download.
- Unzip.
- Start to play with the included C++ example source codes: The first example is described here.

Fade comes as two separate libraries:

- Fade2D is a **2D Constrained Delaunay triangulation library** with
  - Polygon support
  - Constraint edges
  - Grid Mesher and Delaunay Mesh Generator
  - Segment Intersection Test Software
- Fade2.5D is a C++ Constrained Delaunay triangulation library **for 2.5D** and it can do **anything that the Fade2D library can do.**. In addition it has a z-coordinate and a rich selection of algorithms made for Digital Elevation Models (DEM) and surfaces like
  - Cut-and-Fill
  - Cookie Cutter
  - Valley-/Ridge-triangulations
  - Mesh smoothing
  - Point cloud simplification.

A collection of 2D and 2.5D example source codes is included in the download. The C++ examples walk through the concepts of the library step by step. You can jump to the topic of your interest and refer back to the basics as needed. The basics of the 2D examples apply to the 2.5D version as well.

1.1.2 Compiling and Linking the Library under Windows:

1. Open one of the Visual Studio example projects (supported: VS2010, VS2012, VS2013, VS2015, VS2017, VS2019, VS2022)
2. Compile the example source code. The executable is written to the Win32 or x64 folder.

When linking the triangulation library with your own software you can use the settings from the provided example solutions or use the table below:

Visual Studio	IDE	Platform Toolset
VS2010	v10	toolset v100 or Windows7.1SDK
VS2012	v11	toolset v110
VS2013	v12	toolset v120
VS2015	v14	toolset v140
VS2017	v15	toolset v141
VS2019	v16	toolset v142
VS2022	v17	toolset v143

1.1.3 Compiling and Linking the Library under Linux and Mac:

1. Edit the Makefile to specify your platform (Apple, Linux distro, or Raspberry Pi) and type 'make' to compile the example source code.
2. Ensure that GMP is installed. On Ubuntu, Debian, Raspbian, you can install it using the following command: $ sudo apt-get install libgmp10 (works on Ubuntu/Debian/Mint/Raspbian, on other systems search for libgmp or gmp)

Work through the provided examples. They are small, well-documented, and are also discussed on the website

1.1.4 Directory Contents

- **include_fade2d** and **include_fade25d**
  Header files of the two libraries.
- **Win32** and **x64**
  This directory contains the DLL's for Windows 32-bit and 64-bit and it is the target directory for the executables of example code compiled with Visual Studio.
- **lib_${DISTRO}_${ARCHITECTURE}**
  The shared library (∗.so) for Linux/Apple developers.
- **examples_2D**
  2D Example source code (∗.cpp files) and Visual Studio projects
- **examples_25D**
  2.5D Example source code (∗.cpp files) and Visual Studio projects
- **doc**
  Library Documentation in ∗.pdf format

1.1.5 Troubleshooting

- A supposed crash is often just an exception that has been thrown for a good reason. Use try/catch blocks to investigate the cause.
- When updating from an earlier version: **UPDATE ALSO THE HEADER FILES.**
- Compare the settings of the example projects with your project settings.
- Avoid mixing multiple Visual Studio versions. Use the correct dll.
- If your problem persists, feel free to `send` a minimal example that reproduces it and it will be fixed as soon as possible.

1.1.6 Release notes / History

1.1.6.1 Version 2.13 (June 18th, 2024) Bug Fixes

- **Index Computation Error:** Resolved an issue in the *FadeExport* struct where triangle neighbors were incorrectly computed.
- **Point Removal for Convex Hull Points:** Fixed a bug where removing a convex hull point could incorrectly flip nearby constraint segments.

New Features

- **New PDF Writer:** The `Visualizer2` class now supports writing both PDF and Postscript files. Simply provide a filename with a .ps or .pdf extension. To ensure robustness from the start, `Visualizer2` utilizes the excellent `PDFGen` code.
- **Function `drape()` :** Improved performance and accuracy for the `drape()` function.

1.1.6.2 Version 2.12 (February 29th, 2024)

Bug Fixes:

- Resolved issue with multithreaded triangulation malfunctioning when fewer than 3 non-degenerate points were inserted initially, leading to failures in subsequent calls.
- Fixed the getUndirectedEdges() function, which erroneously returned directed edges.

New Features:

- Support for .PLY File Format: read/write operations with 64-bit coordinates.
- Enhanced import method: Introducing the new importTriangles_robust() method, designed to import triangles specified as a list of 3 subsequent points per triangle. The improvement over the classic importTriangles() method is, that it works also in scenarios where rounding errors lead to overlapping triangles.
- Multithreading improved

Platform specific:

- iOS build supports arm and x86_64 simulator again
- macOS build supports arm64 and x86_64

1.1.6.3 Version 2.11 (February 27th, 2024)

- internal development and test version

1.1.6.4 Version 2.10, September 23rd, 2023:

- Bugfix in valley-ridge-optimization: OPTMODE_BEST could change the boundary edges of a zone
- Cookie-Cutter: Much better performance when edges are to be protected

1.1.6.5 Version 2.09, July 25th, 2023:

- Numeric improvements
- Bugfix for constraint insertion (very rare endless loop bug)
- Bugfix in CookieCutter
- New untwistPolygon() function to repair selfintersecting polygons
- MinGW64 support
- Better Zone::smoothing() method
- Two memory leaks fixed

1.1.6.6 Version 2.08, May 7th, 2023:

- Support for MinGW64 added
- Zone::smoothing() improved
- TestDataGenerators, createRandomSurfacePoints() improved

1.1.6.7 Version 2.07, April 11th, 2023:

- Experimental support for MinGW
- Grid meshes can be aligned to a certain reference point now
- Segment intersection: Numeric improvements
- Fade_2D::remove(std::vector<Point2*>) added which provides better performance than iterative calls to Fade_2D::remove(Point2*).
- Accuracy of Fade_2D::drape() improved.

1.1.6.8 Version 2.06, April 10th, 2023: INTERNAL TEST VERSION

- Segment intersection: Numeric improvements
- Fade_2D::remove(std::vector<Point2*>) added which provides better performance than calling Fade_2D::remove(Point2*) for a large number of points iteratively.

1.1.6.9 Version 2.05, April 5th, 2023: INTERNAL TEST VERSION

- Experimental support for MinGW
- Pivot point for grid meshing

1.1.6.10 Version 2.04, February 22nd, 2023:

- importTriangles(): Performance improved, multithreading added, progress counter added
- copyFade() function added to copy a Fade instance and its zones.
- native VS2022 version added.

1.1.6.11 Version 2.03, January 9th, 2023:

- Grid meshing is much faster now
- Memory leak fixed, possible numerical problem fixed
- Multithreading improved, see setGlobalNumCPU()
- Performance of Cut&Fill improved

1.1.6.12 Version 2.02, October 3rd, 2022:

- Cut&Fill revised for better reproducibility and robustness. The default value of ignoreThreshold has been reduced to 1e-6 to prevent null-components due to rounding.
- Numeric bug solved. This bug has not shown up for years but it is a critical one and upgrading to version 2.02 is recommended.

1.1.6.13 Version 2.01, September 19th, 2022:

- Reproducibility further improved.
- Note: For reproducibility pass the maximum number of vertices (including those created due to intersections and remeshing) to the Fade_2D constructor e.g., Fade_2D dt(1000000);

1.1.6.14 Version 2.00, September 15th, 2022:

- Fade v2.00 is simply the version number after v1.99. There are no fundamental or breaking changes in the library.
- Reproducibility of results for grid and quality meshing
- Minor fixes

1.1.6.15 Version 1.99, January 25th, 2022:

- Bugfix: In version 1.98 multithreading was not stable. Fixed.
- The function offsetPolygonPoints() accounts for angles of the polygon now.

1.1.6.16 Version 1.98, January 15th, 2022:

- Large coordinates and other numerically difficult settings are now handled more efficiently. It depends on your data whether this gives a dramatic improvement in performance.
- CutAndFill prints warnings to stdout but this is not always desired, so CutAndFill::go() takes a new parameter *bool bWithMessages* now. Use *bWithMessages=false* to disable the messages.
- FadeExport offers the new function FadeExport::lexiSort(): It sorts the points stored in FadeExport lexicographically. Use it for better reproducibility.
- New function FadeExport::getCustomIndex() to retrieve the (optional) custom index of a vertex.
- New function FadeExport::getNormal() to compute the normal vector of a stored triangle.

1.1.6.17 Version 1.97, October 29th, 2021:

- Custom indices via CloudPrepare work now
- Voronoi diagram fixed (it had an endless loop)

1.1.6.18 Version 1.96, October 18th, 2021:

- Bug in CloudPrepare::adaptiveSimplification() fixed and other small bugfixes
- iOS support added (please report your experience)

1.1.6.19 Version 1.95, October 2nd:

- Internal test version, bugfixes, iOS

1.1.6.20 Version 1.94, September 7th, 2021:

- Fixed: When all points are horizontal or all points are vertical then multithreaded insertion failed.

1.1.6.21 Version 1.93, September 1st, 2021:

- Bug in the new Voronoi diagram module solved
- Voronoi diagram improved

1.1.6.22 Version 1.92, August 9th, 2021:

- Multithreading issue finally fixed.

1.1.6.23 Version 1.91, August 8th, 2021:

- Fixed multithreading issue when SegmentChecker is used in multiple threads
- New methods in Fade_2D: getDirectedEdges(), getUndirectedEdges() and getNearestNeighbor()
- Export of Zones to the FadeExport struct

1.1.6.24 Version 1.90, August 8th, 2021:

- Fixed stability issue when SegmentChecker is used in multiple threads
- Fixed rare bug in the Fade_2D::drape() method
- Added pZone2::getComponentPolygons() to retrieve oriented boundary polygons per connected component
- Added the free function getSortedBoundaryPolygons()

1.1.6.25 Version 1.89, June 8th, 2021:

- Voronoi diagram: Numeric problems fixed.
- Visualizer: Scaling problem fixed.
- Circumcenter-computation improved.
- Segment intersection accuracy improved.

1.1.6.26 Version 1.88, June 4th, 2021:

- Voronoi diagram.
- Accuracy of Triangle::getDual() improved with multiple-precision arithmetic.

1.1.6.27 Version 1.87, May 5th., 2021:

- Additional versions of the load() and save() commands to also accept std::ostream and std::istream.
- There is a new version of the peelOffIf() function that removes unwanted border-triangles. It can prevent a zone from breaking apart by deleting triangles. It takes the new predicate "PeelPredicateTS", which allows more precise decisions. The version of peelOffIf() that takes the old "UserPredicateT" remains valid for backwards compatibility.
- When Fade_2D::createConstraint() inserts a constraint segment that intersects an existing one or an existing point, then it needs to be subdivided. By default, the intersection point is then assigned the height of the existing element. But now this function has an additional parameter 'bool bUseHeightOfLatest=false' which can be used to enforce the height of the last inserted segment.

1.1.6.28 Version 1.86, April 28th., 2021:

- New commands Fade_2D::saveTriangulation(), Fade_2D::saveZones(), Zone2::save() and Fade_2D::load() to save and load triangulation data. The new example ex11_save_and_load.cpp demonstrates it.
- New dry-mode parameter for CloudPrepare::uniformSimplifyGrid() and for CloudPrepare::adaptiveSimplify() so that the size of the point cloud that would result from the reduction can be determined.

1.1.6.29 Version 1.85, March 8th., 2021:

- Bugfixes: A multithreading-bug has been solved and strings are now correctly passed to the Visualizer2 class.
- New method Fade_2D::setFastMode(true) to avoid expensive computations. This accelerates triangulation of raster data i.e., points on a regular grid.

1.1.6.30 v1.84, Jan. 7th., 2021:

- **IMPORTANT IF YOU UPGRADE FROM A PREVIOUS VERSION:** To avoid passing std::strings over the DLL boundary, some function parameters have been changed from std::string to const char$*$. You will often not even notice this, but if your code should not compile anymore, then this is the reason. Instead of passing "yourString" please pass it as "yourString.c_str()". This change was unavoidable. Thank you for your understanding!
- New **CloudPrepare** class to simplify point clouds and also to avoid memory-usage-peaks. Have a look at the examples!
- New function **Fade_2D::exportTriangulation()** allows convenient transfer of triangulation data to your own data structures. The function was created with memory consumption in mind, i.e. while the data is exported, it frees memory from the library gradually.
- New function Zone2::smoothing() applies weighted **Laplacian smoothing** to the vertices of a zone.
- New **Valley**/**Ridge optimization**: With Zone2::slopeValleyRidgeOptimization() one can choose between 3 algorithms now to adapt the triangulation better to valleys and ridges. Have a look at the new examples.

- **Example codes** completely rewritten.
- Small bug fixes.

v1.83, Dec. 30th, 2020:

- Internal test release. Significant changes, thus it has not been released.

v1.82, Nov. 15th, 2020:

- Intermediate release to support CentOS/RedHat7.8. Minor improvements here and there.

v1.81, May 17th, 2020:

- Memory Leak in EfficientModel fixed. EfficientModel improved: Pruning the point cloud is much faster now and the new method zSmoothing() has been implemented. It provides minimum-, maximum-, median- and average-smoothing.

v1.80, March 25th, 2020:

- Bug in Cut&Fill solved: A foot point was computed in 3D while it should have been computed in 2D. The difference was in most cases insignificant and thus the problem did not become apparent earlier. Sorry. Fixed.
- Improvement in Cut&Fill: The algorithm checks now if the two input zones do overlap. If not, the CutAndFill↩ ::go() method returns false and the CutAndFill object shall not further be used.
- Example source codes adapted and -std=c++98 removed from their Makefiles
- Documentation improved

1.1.6.31 v1.79, January 20th, 2020:

Internal version. Revision.

1.1.6.32 v1.78, November 15th, 2019:

- Bugfix: Multithreading did not work in Windows due to a CMake configuration error.
- A typo in the function name Fade_2D::measureTriangulationTime() has been corrected.

1.1.6.33 v1.77, October 21st, 2019

- Support for Visual Studio 2019.
- A bug has been fixed: In a rare case a self-intersecting constraint graph could generate an error.
- Improvements: The constraint-insertion-strategies CIS_CONFORMING_DELAUNAY and CIS_↩ CONFORMING_DELAUNAY_SEGMENT_LEVEL are deprecated now.
- The fast and reliable replacement is CIS_CONSTRAINED_DELAUNAY along with the new methods ConstraintGraph::makeDelaunay() and Fade_2D::drape(). See the new example code in examples_↩ 25D/terrain.cpp.

1.1.6.34 v1.75 and 1.76

- Non-public tests.

1.1.6.35 v1.74, March 19th, 2019:

- Cleanup: The (until now experimental) surface reconstruction module has been moved into the separate WOF Point Cloud Meshing library (https://www.geom.at/products/wof-point-cloud-mesher/). This makes the binaries smaller and it improves the maintainability of the code.
- Cleanup: Support for VS2008 has been dropped (if you are a commercial user and still need VS2008 then contact the author please!).

- The build system has been migrated to CMake to reduce the manual work and to guarantee uniform flags for all builds.
- The HoleFiller class that has been developed for the removed surface reconstruction module is retained in the library because it has already users. Its code has been revised in order to provide repeatable results for identical inputs.
- According to a user request the MeshGenParams class (used for advanced Delaunay Meshing) offers now a method to lock certain constraint segments such that they are not splitted while all others can be splitted if required.

1.1.6.36 v1.73, January 14th, 2019:

- While all below mentioned releases after v1.63 were development versions the present v1.73 is again an official release for all.
- The work of the below betas is included
- as well as a bugfix in the getProfile() method of the IsoContours class (this method was new and experimental in v1.63)

1.1.6.37 v1.71 and 1.72, October 24th, 2018:

- (internal) Hole-Filling (Polygon-Triangulation) improved.

1.1.6.38 v1.70, October 17th, 2018:

- (internal) Hole-Filling (Polygon-Triangulation) improved.

1.1.6.39 v1.69, October 15th, 2018:

- (internal) Hole-Filling (Polygon-Triangulation) improved.

1.1.6.40 v1.68, September 14th, 2018:

- (internal) Hole-Filling (Polygon-Triangulation) improved.

1.1.6.41 v1.67, September 4th, 2018:

- (internal) Hole-Filling (Polygon-Triangulation) is now offered via. an API call. Intermediate beta release.

1.1.6.42 v1.66, August 25th, 2018:

- (internal) Bugfix in Cut&Fill: An intersection point could be slightly off its expected range. Solved. Unofficial intermediate code.

1.1.6.43 v1.65, July 29th, 2018:

- (internal) Another bugfix in Cut&Fill. Unofficial intermediate binary.

1.1.6.44 v1.64, July 21st, 2018:

- (internal) Bugfix in the Cut&Fill module: In rare cases Cut&Fill crashed due to unexpected numeric deviation (fixed).
- The importTriangles() function has been reimplemented and is considerably faster now.
- And there is a change that affects only 32-bit users: Binary files written with the writePointsBIN() and writeSegmentsBIN() functions on 32-bit machines were not readable on 64-bit machines. The format on 32-bit machines (read/write) has been adapted to match exactly the one of 64-bit machines. But note that old 32-bit files are not readable anymore. This should affect next to nobody, thus this solution has been chosen.

1.1.6.45 v1.63, June 10th, 2018:

- Cookie-Cutter operation added. 3D Point Cloud Reconstruction added to the API (but is still under development, pls. take it as a preview).
- Raspberry PI support added again.

1.1.6.46 v1.62, June 3rd, 2018:

- 3D Point Cloud Reconstruction considerably improved. Unofficial demo.

1.1.6.47 v1.61, May 1st, 2018:

- 3D Point Cloud Reconstruction: Unofficial demo.

1.1.6.48 v1.60, February 26th, 2018:

- Accurate computation of glancing segment intersections.
- Additional parameter for Advanced Meshing: bool bKeepExistingSteinerPoints=true in MeshGenParams makes all Steiner points from previous refinement calls static, i.e. unremovable during subsequent refinement calls. This way Advanced Meshing can be carried out for several zones of a triangulation such that it does not destroy what has been meshed so far.

1.1.6.49 v1.59, January 14th, 2018:

- Performance upgrade: Multithreading is available now. Large point sets reach a speedup of 4.4 on a hexacore CPU (i7 6800K)

1.1.6.50 v1.58, October 23th, 2017:

- Mesh Generator refactored. Delaunay Meshing is +10x faster now.
- A function to create polygons from boundary edges has been added.

1.1.6.51 v1.57, October 9th, 2017:

- Nonpublic test code.

1.1.6.52 v1.56, September 24th, 2017:

- Bugfix: createConstraint() crashed in a rare case. Solved.
- Functions for binary file I/O added.

1.1.6.53 v1.55, August 12th, 2017:

- Access to internal Cut&Fill datastructures revised.
- Example source codes revised. Support for Visual Studio 2017 added.

1.1.6.54 v1.54beta, August 8th, 2017:

- Access to internal Cut&Fill datastructures. . This is a pre-released beta, code quality is good but final tests and documentation updates required.

1.1.6.55 v1.53, July 15th, 2017:

- Error corrections and performance upgrades in the still quite new Cut&Fill library module.

1.1.6.56 v1.53 beta, June 2nd, 2017:

- The new Cut&Fill library module has been added. Cut&Fill computes the volume between two surfaces.

1.1.6.57 v1.51 beta, May 27th, 2017:

- Non-public test binary

1.1.6.58 v1.50, April 5th, 2017: After three internal betas (that concetrated on refactoring and rare bugs) this is again a stable public release:

- The constraint insertion subsystem has been rewrittten and is faster now.
- Visualization improved.
- Exact orientation tests provided through the API.
- Improved progress bar support. Mesh generator improved.
- Users who upgrade from earlier Fade releases: The Zone2::getArea() and Triangle2::getArea() methods have been replaced by getArea2D() in Fade2D and by getArea2D() AND getArea25D() in Fade2.5D. The reason is that the old getArea() method was easily misunderstood in Fade2.5D (it returned the same result as getArea25D() now). We have decided to remove the old method to avoid confusion and a potential source of error. If necessary, please adapt your code.

1.1.6.59 v1.49, March 2nd, 2017:

- Constraint insertion subsystem improved.
- Mesh generator revised.

1.1.6.60 v1.48, February 15th, 2017:

- Corrections of yesterday's v1.47.

1.1.6.61 v1.47, February 14th, 2017: The focus of this (for now) non-public version is stability:

- Intersecting constraint segments must be subdivided although their exact intersection is not always representable with double precision coordinates. Thus tiny rounding errors are unavoidable and these caused trouble in very unlikely cases.
- The constraint insertion subsystem has now been re-implemented to behave robust also in such cases.

1.1.6.62 v1.46a, January 14th, 2017:

- +++ Raspberry PI is supported now +++ // Apart from RPI support v1.46a is equal to v1.46. Raspberry PI users: Please give feedback, do you have everything you need for RPI development now?

1.1.6.63 v1.46, January 8th, 2017:

- +++ MacOS is supported now +++ //
- A new class EfficientModel takes oversampled 2.5D point clouds and returns a subset that represents the model efficiently. The automatic pruning process runs in a controlled fashion such that a user specified maximum error is kept.
- The Delaunay Mesh Generator is now supported by a Grid Mesher, thus it creates more regular meshes.
- The Delaunay triangulation of specific point sets is not unique, for example when grid points are triangulated (4 points on a common circumcircle). To improve the repeatability and for reasons of visual appearance the new method Zone2::unifyGrid() has been implemented.
- A problem in the point location method Fade_2D::locate() when the query point was exactly on the convex hull of the triangulation has been solved.

1.1.6.64 v1.43, November 20th, 2016:

- Better example source code for the new SegmentChecker class.
- And the SegmentChecker of v1.42 returned false positives, this problem is solved now.

1.1.6.65 v1.42, October 19th, 2016:

- The new tool SegmentChecker takes a bunch of segments and fully automatically identifies intersecting segments. The underlying data structure makes the tool incredibly fast. Intersecting segments can be visualized. Intersections can be computed in 2D and 2.5D (with heights).
- A new module named TestDataGenerators creates random polygons, random segments, points, random numbers and polylines for automated software stress tests. Progress bar support added.

1.1.6.66 v1.41, July 24th, 2016:

- New constraint insertion strategy.
- Minor bug fixes.
- Performance slightly improved.

1.1.6.67 v1.40 beta, June 14th, 2016:

- Non public intermediate test code.
- Bounded zones introduced: Mesh generation algorithms require that zones are bounded by constraint segments. This is certainly the case for the most usual zones with zoneLocation=ZL_INSIDE. But other types of zones may be unbounded and in this case remeshing won't work well, so it was necessary to change the behavior: From now on calling refine() and refineAdvanced() is only allowed with zones whose zone↩ Location is ZL_INSIDE or ZL_BOUNDED. A bounded zone can easily be gained from any other zone using Zone2::convertToBoundedZone(). Also new: Fade_2D::createConstraintGraph(..) has now a third parameter 'bool bOrientedSegments=false'. By default it is false to provide backwards compatibility. This parameter allows you to specify that the provided segments are CCW oriented. This way more complex inside- and outside-zones can be formed.
- Performance of Fade_2D::createConstraint(..) drastically improved.

1.1.6.68 v1.39, May 31st, 2016:

- Non public intermediate beta.

1.1.6.69 v1.37a, March 15th, 2016:

- Small upgrade: The performance of the remove method has been improved.

1.1.6.70 v1.37, March 10th, 2016:

- Interface change in the MeshGenParams class. The class has been introduced two weeks before, so chances are good that the change does not affect you. Previously the class had the methods getMaxTriangle↩ Area(double x,double y) and getMaxEdgeLength(double x,double y) where x and y where the barycenter of a triangle for which the algorithm determines if it must be refined. The change is that x and y have been replaced by the triangle itself to give client code even more control (x and y can still be computed from the triangle).

1.1.6.71 v1.36, February 29th, 2016:

- Experimental method refineExtended(..) replaced by the (now permanent) method refineAdvanced(Mesh↩ GenParams∗ pParams). This method allows much more control over the mesh density.

1.1.6.72 v1.34, February 14th, 2016:

- Vertex management subsystem revised (sometimes Vertex removement did not work as expected). Performance improvement.

1.1.6.73 v1.33 PreRelease, January 17th, 2016: The previous official Fade version is Fade 1.24. It was released 6 months ago. Since then major developments have been made and now a big upgrade follows with v1.↩ 33.14:

- Constraint segments may intersect now and they are automatically subdivided at their intersection points.
- Import of existing triangles is supported and one can cut through static triangulations. This version is well tested. It also runs at two customers sites with no known problems. But due to the large amount of new code we call this one a pre-release. Please report if you find any problems and note that it is also helpful if you report that the library works well in your setting. The DLL names have been adapted to the safer and more convenient pattern

  fade[2D|25D]_$(Platform)_$(PlatformToolset)_$(Configuration).dll

  If you upgrade from an earlier release it is recommended that you remove any previous Fade DLL's to avoid unintended linking to an old binary.

1.1.6.74 v1.31 and 1.32, December 1st, 2015:

- Non public intermediate release, improves the CDT.

1.1.6.75 v1.30, November 18th, 2015:

- Non public intermediate release, improves the refineExtended method.

1.1.6.76 v1.29, October 17th, 2015:

- Non public intermediate release. The method importTriangles() detects invalid input data now and returns NULL to avoid an assertion or even an infinite loop when the input data is not clean. The possibly invalid input elements are written to stdout and a postscript file visualizes where the problem occurs.

1.1.6.77 v1.28, October 10th, 2015:

- Non public intermediate release. Customer specific code revised. Stress tests with random polygons and segments have been made. Heap checking to ensure proper memory handling.

1.1.6.78 v1.27, October 5th, 2015:

- Non public release, improvements of the recently implemented functions, especially of customer specific code Fade_2D::importTriangles() and Fade2D::cutTriangles().

1.1.6.79 v1.26, September 8th, 2015:

- New functions of the last unofficial v1.25 have been revised. Constraint segments may intersect now.

1.1.6.80 v1.25, August 18th, 2015:

- Intermediate pre-release with new features: importTriangles() imports arbitrary triangles into a triangulation, cutTriangles() allows to insert a constraint segment as if it where a knife, getOrientation() provides an exact orientation test. Zone2 objects can now also be made from a set of triangles. Constraint segments can intersect now. These features correspond to a large amount of new code: Please test v1.25 carefully before deploying it in a production environment.

1.1.6.81 v1.24, July 22nd, 2015:

- Public release of v1.23's improvements. And I'm sorry but we had a bug in Fade_2D::getVertexPointers(..). The method may have missed to return a few pointers after a call to refine() or remove(). This bug is fixed now.

1.1.6.82 v1.23, July 9th, 2015:

- Internal test release with the new refineExtended() method for the specific needs of a certain client software.

1.1.6.83 v1.22, May 25th, 2015:

- Code refactored, build system refactored and as a result improved Linux support: CentOS 6.4, Ubuntu 14.04, Ubuntu 15.04 and similar systems.
- Removement of points has been implemented
- Delaunay meshing has been reworked,
- sqDistance() has been replaced by sqDistance2D() and sqDistance25D() because both versions are useful in 2.5D.
- OpenMP has been removed, it was only used under Linux and currently I work on a better way to provide multithreading.

1.1.6.84 v1.21, May 17th, 2015:

- Unofficial intermediate release. Testing new features.

1.1.6.85 v1.20, April 5th, 2015:

- 3D scene Visualization for (up to date) web browsers added. Misleading enumeration values CIS_KEEP↩ _DELAUNAY and CIS_IGNORE_DELAUNAY have been replaced by CIS_CONFORMING_DELAUNAY and CIS_CONSTRAINED_DELAUNAY (the two deprecated names are kept for backward compatibility).
- Bug in the free function center(Point2&,Point2&) solved.
- Major revision of the documentation pages.
- The source codes of the examples has been reengineered and is included in the present documentation pages.

1.1.6.86 v1.19, October 26th, 2014:

- Support for Visual Studio 2013 (VC12) has been added.
- Only minor code changes.

1.1.6.87 v1.18.3, June 9th, 2014:

- Delaunay Mesh Generation has been improved: Better quality, better performance.
- API improved.
- Small bug fixes.

1.1.6.88 v1.16.1, February 10th, 2014:

- Small update: In rare cases it was possible that subdivided ConstraintSegments caused problems in combination with zone growing. This is fixed now.

1.1.6.89 v1.16, February 3rd, 2014:

- Constrained Delaunay triangulation improved,
- Delaunay meshing improved,
- aspect ratio meshing (experimental) added.
- Minor bug fixes.
- Added support for Visual Studio 2012.

1.1.6.90 v1.14, November 2013 and v1.15, December 2013:

- Non-public intermediate releases (betas with experimental features).

1.1.6.91 v1.13, August 4th, 2013:

- Mesh generation (Delaunay Meshing) has been improved and two bugfixes have been made in the new IsoContours class: A message can be suppressed now and a numeric problem has been fixed.

1.1.6.92 v1.12, June 30th, 2013:

- Starting with v1.12 the download consists of two separate libraries: The familiar full version of the 2D flavor as well as a 2.5D evaluation version. Two very fast new methods have been added to the 2.5D edition: One computes iso-contours, the other computes the height of a point with arbitrary (x,y) coordinates.
- Delaunay mesh generation has been improved.
- Support for VS2008, 32-bit and 64-bit, has been added.
- The performance has been improved.

1.1.6.93 v1.11, June 14th, 2013:

- Non-public intermediate release with VS2008 support and a first version of the iso-contour feature.

1.1.6.94 v1.10, March 30th, 2013:

- Delaunay Refinement (already included as preview in the previous release) has been improved and is officially released now. Parts of the algorithm can use up to 8 CPUs under Linux if explicitly switched on using Fade2↩ D::enableMultithreading().
- There is a new insert method in the API which uses arrays.

1.1.6.95 v1.03, Nov. 4th, 2012:

- A critical bug has been fixed, please switch to v1.03.
- Performance upgrade: A first step towards multithreading has been made in the Linux version.
- In order to facilitate the installation for users without administrator privileges the installers have been replaced by a simple zipped directory that contains everything.
- Meshing through Delaunay Refinement is scheduled for the next release but it is pre-released as an experimental feature in the current v1.03.

1.1.6.96 v1.02, 9/2012:

- An additional debug library for Windows has been added and
- the directory structure has been reorganized.

1.1.6.97 v1.01, 9/2012:

- This is a stable public release. Since v0.9 we have introduced insertion of constraint edges and the zone concept. Moreover the API is under a namespace now. Boost types have been removed from the API to avoid this additional dependency. New demo software has been written and the library is now also available for 64-bit Windows.

2 Module Index

2.1 Modules

Here is a list of all modules:

Tools 19

Version Information 25

File I/O 25

Test Data Generators 30

3 Class Index

3.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

GEOM_FADE25D::Bbox2
Bbox2 is an axis aligned 2D bounding box 37

GEOM_FADE25D::CAF_Component
CAF_Component stands for CUT AND FILL COMPONENT. It represents a connected area of the surface 42

GEOM_FADE25D::Circle2
Circle for visualization 44

GEOM_FADE25D::CloudPrepare
CloudPrepare simplifies overdense point clouds and helps to avoid memory-usage-peaks during data transfer 45

GEOM_FADE25D::Color
Color for visualization 50

GEOM_FADE25D::CompPolygon
Connected component with boundary- and hole polygons 52

GEOM_FADE25D::ConstraintGraph2
ConstraintGraph2 is a set of Constraint Edges (ConstraintSegment2) 52

GEOM_FADE25D::ConstraintSegment2
A ConstraintSegment2 represents a Constraint Edge 56

GEOM_FADE25D::CutAndFill
CutAndFill computes the volume(s) between two overlapping surfaces 57

GEOM_FADE25D::Edge2
Edge2 is a directed edge 62

GEOM_FADE25D::EfficientModel
EfficientModel (DEPRECATED in favor of the new CloudPrepare class) 64

GEOM_FADE25D::Fade_2D
Fade_2D is the Delaunay triangulation class 67

GEOM_FADE25D::FadeExport
FadeExport is a simple struct to export triangulation data 91

GEOM_FADE25D::Func_gtEdge2D
Functor to sort edges by 2d length (descending) 93

GEOM_FADE25D::Func_ltEdge25D
Functor to sort edges by 2.5d length (ascending) 93

GEOM_FADE25D::Func_ltEdge2D
Functor to sort edges by 2d length (ascending) 93

GEOM_FADE25D::Func_ltPointXYZ
Functor to sort points lexicographically 94

GEOM_FADE25D::IsoContours
IsoContours uses a fast datastructure to compute intersections of horizontal planes with a given list of triangles 94

GEOM_FADE25D::Label
Label is a Text-Label for Visualization 95

GEOM_FADE25D::MeshGenParams
Parameters for the mesh generator 96

GEOM_FADE25D::MsgBase
MsgBase, a base class for message subscriber classes 101

GEOM_FADE25D::PeelPredicateTS
User-defined peel predicate 102

GEOM_FADE25D::Point2
Point 102

GEOM_FADE25D::PShape
Polygonal Shape for Visualization 108

GEOM_FADE25D::Segment2
Segment 108

GEOM_FADE25D::SegmentChecker
SegmentChecker identifies intersecting line segments 110

GEOM_FADE25D::Triangle2
Triangle 118

GEOM_FADE25D::TriangleAroundVertexIterator
Iterator for all triangles around a given vertex 124

GEOM_FADE25D::UserPredicateT
User-defined predicate (deprecated) 127

GEOM_FADE25D::Vector2
Vector 127

GEOM_FADE25D::Visualizer2
Visualizer2 is a PDF- and Postscript writer 128

GEOM_FADE25D::Visualizer3
Visualizer3 is a 3D scene writer for the Geomview viewer 135

GEOM_FADE25D::VtxColor 137

GEOM_FADE25D::Zone2
Zone2 is a certain defined area of a triangulation 137

4 File Index

4.1 File List

Here is a list of all documented files with brief descriptions:

Bbox2.h 146

CAF_Component.h 147

Circle2.h 148

CloudPrepare.h 148

Color.h 149

ConstraintGraph2.h 149

ConstraintSegment2.h 149

CutAndFill.h 150

Edge2.h 150

EfficientModel.h 151

Fade_2D.h 151

FadeExport.h 152

freeFunctions.h 153

IsoContours.h 157

Label.h 157

MeshGenParams.h 157

MsgBase.h 158

Performance.h 158

Point2.h 158

PShape.h 160

Segment2.h 160

SegmentChecker.h 161

testDataGenerators.h 162

Triangle2.h 162

TriangleAroundVertexIterator.h 164

UserPredicates.h 164

Vector2.h 164

Visualizer2.h 165

Visualizer3.h 166

Zone2.h 166

5 Module Documentation

5.1 Tools

Functions

- void GEOM_FADE25D::edgesToPolygons (const std::vector< Edge2 > &vEdgesIn, std::vector< std::vector< Edge2 > > &vvPolygonsOut, std::vector< Edge2 > &vRemainingOut)

  Create polygons from a set of edges.
- bool GEOM_FADE25D::fillHole (const std::vector< Point2 > &vMeshCorners, const std::vector< Segment2 > &vPolygonSegments, bool bWithRefine, bool bVerbose, std::vector< Point2 > &vCornersOut)

  Fill a hole in a 3D mesh with triangles (deprecated)
- bool GEOM_FADE25D::fillHole (const std::vector< std::pair< Segment2, Vector2 > > &vPolygonSegments, bool bWithRefine, bool bVerbose, std::vector< Point2 > &vCornersOut)

  Fill a hole in a 3D mesh with triangles (deprecated)
- bool GEOM_FADE25D::fillHole (Mesh3 *pMesh, const std::vector< Edge2 > &vPolygonEdges, bool bWithRefine, bool bVerbose, std::vector< Point2 > &vCornersOut)

  Fill a hole in a 3D mesh with triangles (deprecated)
- double GEOM_FADE25D::getArea25D (const Point2 *p0, const Point2 *p1, const Point2 *p2)

  Get 2.5D area of a triangle.
- double GEOM_FADE25D::getArea2D (const Point2 *p0, const Point2 *p1, const Point2 *p2)

  Get 2D area of a triangle.
- void GEOM_FADE25D::getBorders (const std::vector< Triangle2 * > &vT, std::vector< Segment2 > &vBorderSegmentsOut)

  Get Borders.
- void GEOM_FADE25D::getConnectedComponents (const std::vector< Triangle2 * > &vT, std::vector< std::vector< Triangle2 * > > &vvT)

  Get connected components.
- void GEOM_FADE25D::getDirectedEdges (const std::vector< Triangle2 * > &vT, std::vector< Edge2 > &vDirectedEdgesOut)

  Get directed edges The directed edges of `vT` are returned in `vDirectedEdgesOut`. Directed means that each edge (a,b) with two adjacent triangles in vT is returned twice, as edge(a,b) and edge(b,a).
- Vector2 GEOM_FADE25D::getNormalVector (const Point2 &p0, const Point2 &p1, const Point2 &p2, bool &bOK)

  Get normal vector.
- Orientation2 GEOM_FADE25D::getOrientation2 (const Point2 *p0, const Point2 *p1, const Point2 *p2)

  Get the orientation of three points.
- Orientation2 GEOM_FADE25D::getOrientation2_mt (const Point2 *p0, const Point2 *p1, const Point2 *p2)

  Get Orientation2 (MT)
- void GEOM_FADE25D::getUndirectedEdges (const std::vector< Triangle2 * > &vT, std::vector< Edge2 > &vUndirectedEdgesOut)

  Get undirected edges.
- bool GEOM_FADE25D::isSimplePolygon (std::vector< Segment2 > &vSegments)

isSimplePolygon

- void GEOM_FADE25D::pointsToPolyline (std::vector< Point2 > &vInPoints, bool bClose, std::vector< Segment2 > &vOutSegments)

  Points-to-Polyline.
- bool GEOM_FADE25D::sortRing (std::vector< Segment2 > &vRing)

  Sort a vector of Segments.
- bool GEOM_FADE25D::sortRingCCW (std::vector< Segment2 > &vRing)

  Sort a vector of Segments.

5.1.1 Detailed Description

5.1.2 Function Documentation

5.1.2.1 edgesToPolygons()

```
void GEOM_FADE25D::edgesToPolygons (
        const std::vector< Edge2 > & vEdgesIn,
        std::vector< std::vector< Edge2 > > & vvPolygonsOut,
        std::vector< Edge2 > & vRemainingOut )
```

A number of methods in Fade returns an unorganized set of edges that delimit a certain area. But sometimes it is more beneficial to have these edges organized as a set of one or more polygons. This is the purpose of the present method.

Parameters

in	*vEdgesIn*	is a vector of oriented edges
out	*vvPolygonsOut*	contains one vector<Edge2> for each polygon found in the input data.
out	*vRemainingOut*	is used to return unusable remaining edges

The present function adds one vector<Edge2> to `vvPolygonsOut` for each polygon found in `vEdgesIn`. Each such polygon starts with the leftmost vertex (and when two or more vertices share the smallest x-coordiante then the one of them with the smallest y-coordinate is chosen). Edges that do not form a closed polygon are returned in `vRemainingOut`.

Note

An Edge2 object represents an edge of a triangle. Triangle corners are always counterclockwise (CCW) oriented. Thus outer polygons are CCW-oriented while hole-polygons are CW-oriented, see the figure.




Figure 1 Polygons created by edgesToPolygons

5.1.2.2 fillHole() [1/3]

```
bool GEOM_FADE25D::fillHole (
        const std::vector< Point2 > & vMeshCorners,
        const std::vector< Segment2 > & vPolygonSegments,
        bool bWithRefine,
        bool bVerbose,
        std::vector< Point2 > & vCornersOut )
```

This function was experimental and is now deprecated because 3D point cloud meshing has been moved to the WOF library.

Parameters

in	*vMeshCorners*	specifies the input mesh, 3 points per triangle in counterclockwise order.
in	*vPolygonSegments*	are the edges of the *closed* polygon to be triangulated.
in	*bWithRefine*	specifies if additional vertices shall be created (bWithRefine=true is experimental, don't use currently)
in	*bVerbose*	specifies if warnings shall be printed to stdout
out	*vCornersOut*	contains the created fill triangles, 3 corners per triangle, counterclockwise oriented.

Note

This function is deprecated because all related functionality has been moved to the WOF project.

5.1.2.3 fillHole() [2/3] bool GEOM_FADE25D::fillHole (

```
const std::vector< std::pair< Segment2, Vector2 > > & vPolygonSegments,
bool bWithRefine,
bool bVerbose,
std::vector< Point2 > & vCornersOut )
```

This function was experimental and is now deprecated because 3D point cloud meshing has been moved to the WOF library.

Parameters

in	*vPolygonSegments*	contains the segments of a closed, simple input polygon along with normal vectors. The segments are counterclockwise oriented and ordered with respect to the surface to be created. Check twice, the orientation is very important. The normal vectors point in the direction of the thought surface at the segment i.e., if a hole is filled, the normal vector of an adjecent triangle is taken but if a T-joint is filled the normal vector should be the average normal of the two triangles at the edge.
in	*bWithRefine*	specifies if additional vertices shall be created. (bWithRefine=true is experimental, don't use currently)
in	*bVerbose*	specifies if warnings shall be printed to stdout
out	*vCornersOut*	contains the created fill triangles, 3 corners per triangle, counterclockwise oriented.

Note

This function is deprecated because all related functionality has been moved to the WOF project.

5.1.2.4 fillHole() [3/3] bool GEOM_FADE25D::fillHole (

```
Mesh3 * pMesh,
const std::vector< Edge2 > & vPolygonEdges,
bool bWithRefine,
bool bVerbose,
std::vector< Point2 > & vCornersOut )
```

This function was experimental and is now deprecated because 3D point cloud meshing has been moved to the WOF library.

Parameters

in	*pMesh*	
in	*vPolygonEdges*	are edges of the polygon to be triangulated. They must form a closed polygon in the mesh.
in	*bWithRefine*	specifies if additional vertices shall be created (Note: bWithRefine=true is experimental, don't use currently)
in	*bVerbose*	specifies if warnings shall be printed to stdout
out	*vCornersOut*	contains the created fill triangles, 3 corners per triangle, counterclockwise oriented.

Note

This function is deprecated because all related functionality has been moved to the WOF project.

5.1.2.5 getArea25D() double GEOM_FADE25D::getArea25D (

```
const Point2 * p0,
```

```
const Point2 * p1,
const Point2 * p2 )
```

Returns the area of the triangle defined by the three input points p0, p1, p2.

Parameters

in	*p0,p1,p2*	are the corners of the triangle

5.1.2.6 getArea2D()

```
double GEOM_FADE25D::getArea2D (
const Point2 * p0,
const Point2 * p1,
const Point2 * p2 )
```

Returns the 2D area of the triangle defined by the three input points p0, p1, p2.

Note

The 2D area is returned i.e., the z-coordinate is ignored.

See also

getArea25D()

Parameters

in	*p0,p1,p2*	are the corners of the triangle

5.1.2.7 getBorders()

```
void GEOM_FADE25D::getBorders (
const std::vector< Triangle2 * > & vT,
std::vector< Segment2 > & vBorderSegmentsOut )
```

Computes the border of the triangles in vT. The border consists of all edges having only one adjacent triangle in vT.

Parameters

in	*vT*	are the input triangles
out	*vBorderSegmentsOut*	is used to return all border segments

5.1.2.8 getConnectedComponents()

```
void GEOM_FADE25D::getConnectedComponents (
const std::vector< Triangle2 * > & vT,
std::vector< std::vector< Triangle2 * > > & vvT )
```

This function partitions the triangles of vT into connected components i.e., connected sets of triangles. A connection between two triangles exists when they share a common edge.

Parameters

in	*vT*	Input triangles
out	*vvT*	Output components

5.1.2.9 getNormalVector()

```
Vector2 GEOM_FADE25D::getNormalVector (
        const Point2 & p0,
        const Point2 & p1,
        const Point2 & p2,
        bool & bOK )
```

Returns the normalized normal vector of the triangle defined by the three input points p0, p1, p2.

Parameters

in	*p0,p1,p2*	When these points are counterclockwise (CCW) oriented then the resulting normal vector points towards the viewer.
out	*bOK*	returns true for valid results. When the plane defined by p0, p1, p2 is degenerate, bOK returns false.

5.1.2.10 getOrientation2()

```
Orientation2 GEOM_FADE25D::getOrientation2 (
        const Point2 * p0,
        const Point2 * p1,
        const Point2 * p2 )
```

This function returns the *exact* orientation of the points p0, p1, p2 Possible values are
ORIENTATION2_COLLINEAR if p0, p1, p2 are located on a line,
ORIENTATION2_CCW if p0, p1, p2 are counterclockwise oriented
ORIENTATION2_CW if p0, p1, p2 are clockwise oriented
Not thread-safe but a bit faster than the thread-safe version

5.1.2.11 getOrientation2_mt()

```
Orientation2 GEOM_FADE25D::getOrientation2_mt (
        const Point2 * p0,
        const Point2 * p1,
        const Point2 * p2 )
```

See also

getOrientation2(const Point2* p0,const Point2* p1,const Point2* p2)

This version is thread-safe.

5.1.2.12 getUndirectedEdges()

```
void GEOM_FADE25D::getUndirectedEdges (
        const std::vector< Triangle2 * > & vT,
        std::vector< Edge2 > & vUndirectedEdgesOut )
```

The undirected edges of vT are returned vUndirectedEdgesOut.

5.1.2.13 isSimplePolygon()

```
bool GEOM_FADE25D::isSimplePolygon (
        std::vector< Segment2 > & vSegments )
```

Parameters

in	*vSegments*	specifies segments to be checked. Degenerate segments (0-length) are ignored.

Returns

true if vSegments contains a closed polygon without selfintersections. False otherwise.

5.1.2.14 pointsToPolyline()

```
void GEOM_FADE25D::pointsToPolyline (
        std::vector< Point2 > & vInPoints,
```

```
        bool bClose,
        std::vector< Segment2 > & vOutSegments )
```

Turns a vector of points (p0,p1,p2,...pm,pn) into a vector of segments ((p0,p1),(p1,p2),...,(pm,pn)). In case that bClose is true an additional segment (pn,p0) is constructed. Degenerate segments are ignored. Selfintersections of the polyline are not checked.

Parameters

in	*vInPoints*	
in	*bClose*	specifies whether a closing segment shall be constructed
out	*vOutSegments*	is where the output segments are stored

5.1.2.15 sortRing() `bool GEOM_FADE25D::sortRing (`

```
        std::vector< Segment2 > & vRing )
```

The segments in vRing are reoriented and sorted such that subsequent segments join at the endpoints.

5.1.2.16 sortRingCCW() `bool GEOM_FADE25D::sortRingCCW (`

```
        std::vector< Segment2 > & vRing )
```

The segments in vRing are reoriented and sorted such that the resulting polygon is counterclockwise oriented and subsequent segments join at the endpoints.

5.2 Version Information

Functions

- const char * GEOM_FADE25D::getFade2DVersion ()

  Get the Fade2D version string.
- int GEOM_FADE25D::getMajorVersionNumber ()

  Get the major version number.
- int GEOM_FADE25D::getMinorVersionNumber ()

  Get the minor version number.
- int GEOM_FADE25D::getRevisionNumber ()

  Get the revision version number.
- bool GEOM_FADE25D::isRelease ()

  Check if a RELEASE or a DEBUG version is used.

5.2.1 Detailed Description

5.3 File I/O

Functions

- bool GEOM_FADE25D::readPointsBIN (const char *filename, std::vector< Point2 > &vPointsIn, bool b↩ WithHeader=true)

  Read points from a binary file.
- bool GEOM_FADE25D::readPointsPLY (const char *filename, bool bUniquePoints, std::vector< Point2 > &vPoints, std::vector< VtxColor > *pVertexColors=NULL)

  *Read points from a *.PLY file.*
- bool GEOM_FADE25D::readPointsPLY (std::istream &is, bool bUniquePoints, std::vector< Point2 > &v↩ Points, std::vector< VtxColor > *pVertexColors=NULL)

  *Read points from a *.PLY file.*
- bool GEOM_FADE25D::readSegmentsBIN (const char *filename, std::vector< Segment2 > &vSegments↩ Out)

  Read segments from a binary file.

- bool GEOM_FADE25D::readXY (const char *filename, std::vector< Point2 > &vPointsOut)

  Read (x y) points.
- bool GEOM_FADE25D::readXYZ (const char *filename, std::vector< Point2 > &vPointsOut)

  Read (x y z) points.
- bool GEOM_FADE25D::writePointsASCII (const char *filename, const std::vector< Point2 * > &vPointsIn)

  Write points to an ASCII file.
- bool GEOM_FADE25D::writePointsASCII (const char *filename, const std::vector< Point2 > &vPointsIn)

  Write points to an ASCII file.
- bool GEOM_FADE25D::writePointsBIN (const char *filename, std::vector< Point2 * > &vPoints)

  Write points to a binary file.
- bool GEOM_FADE25D::writePointsBIN (const char *filename, std::vector< Point2 > &vPoints)

  Write points to a binary file.
- bool GEOM_FADE25D::writePointsPLY (const char *filename, std::vector< Point2 * > &vPoints, bool b↩ ASCII)

  *Write points to a *.PLY file.*
- bool GEOM_FADE25D::writePointsPLY (std::ostream &os, std::vector< Point2 * > &vPoints, bool bASCII)

  *Write points to a *.PLY file.*
- bool GEOM_FADE25D::writeSegmentsBIN (const char *filename, std::vector< Segment2 > &vSegmentsIn)

  Write segments to a binary file.

5.3.1 Detailed Description

5.3.2 Function Documentation

5.3.2.1 readPointsBIN()

```
bool GEOM_FADE25D::readPointsBIN (
        const char * filename,
        std::vector< Point2 > & vPointsIn,
        bool bWithHeader = true )
```

Reads points from a binary file.

Parameters

filename	is the input file
vPointsIn	is used to return the points
bWithHeader	specifies if the file contains a header (like the ones written by writePointsBIN()) or if the file contains just a sequence of double precision coordinates - use false in this case.

See also

writePointsBIN()

5.3.2.2 readPointsPLY() [1/2]

```
bool GEOM_FADE25D::readPointsPLY (
        const char * filename,
        bool bUniquePoints,
        std::vector< Point2 > & vPoints,
        std::vector< VtxColor > * pVertexColors = NULL )
```

Parameters

vPoints	[out] returns the read points
filename	is the input filename

Parameters

bUniquePoints	specifies whether to read a unique point set OR point triples (3 points per triangle)
pVertexColors	points to an optional color output vector. Default: NULL

Note

: If pVertexColors!=NULL, then colors from the ∗.PLY file are stored in ∗pVertexColors. Additionally, indices to these colors are then stored in the points. These indices can be retrieved with Point2::getCustomIndex() Function available for platforms with C++11.

5.3.2.3 readPointsPLY() [2/2]

```
bool GEOM_FADE25D::readPointsPLY (
        std::istream & is,
        bool bUniquePoints,
        std::vector< Point2 > & vPoints,
        std::vector< VtxColor > * pVertexColors = NULL )
```

Parameters

vPoints	[out] returns the read points
is	is the input stream
bUniquePoints	specifies whether to read a unique point set OR point triples (3 points per triangle)
pVertexColors	points to an optional color output vector. Default: NULL

Note

: If pVertexColors!=NULL, then colors from the ∗.PLY file are stored in ∗pVertexColors. Additionally, indices to these colors are then stored in the points. These indices can be retrieved with Point2::getCustomIndex() Function available for platforms with C++11.

5.3.2.4 readSegmentsBIN()

```
bool GEOM_FADE25D::readSegmentsBIN (
        const char * filename,
        std::vector< Segment2 > & vSegmentsOut )
```

Reads segments from a binary file of type 21 or 31

See also

writeSegmentsBIN()

5.3.2.5 readXY()

```
bool GEOM_FADE25D::readXY (
        const char * filename,
        std::vector< Point2 > & vPointsOut )
```

Reads points from an ASCII file. Expected file format: Two coordinates (x y) per line, whitespace separated. The z coordinate is set to 0.

5.3.2.6 readXYZ()

```
bool GEOM_FADE25D::readXYZ (
        const char * filename,
        std::vector< Point2 > & vPointsOut )
```

Reads points from an ASCII file. Expected file format: Three coordinates (x y z) per line, whitespace separated.

5.3.2.7 writePointsASCII() [1/2]

```
bool GEOM_FADE25D::writePointsASCII (
        const char * filename,
        const std::vector< Point2 * > & vPointsIn )
```

Writes points to an ASCII file, three coordinates (x y z) per line, whitespace separated.

Note

Data exchange through ASCII files is easy and convenient but floating point coordinates are not necessarily exact when represented as decimal numbers. If the tiny rounding errors can't be accepted in your setting you are advised to write binary files, (use writePointsBIN())

5.3.2.8 writePointsASCII() [2/2]

```
bool GEOM_FADE25D::writePointsASCII (
        const char * filename,
        const std::vector< Point2 > & vPointsIn )
```

Write points to an ASCII file

See also

readPointsASCII()

5.3.2.9 writePointsBIN() [1/2]

```
bool GEOM_FADE25D::writePointsBIN (
        const char * filename,
        std::vector< Point2 * > & vPoints )
```

File format:
int filetype (30)
size_t numPoints (8 bytes)
double x0
double y0
double z0
...
double xn
double yn
double zn

5.3.2.10 writePointsBIN() [2/2]

```
bool GEOM_FADE25D::writePointsBIN (
        const char * filename,
        std::vector< Point2 > & vPoints )
```

File format:
int filetype (30)
size_t numPoints (8 bytes)
double x0
double y0
double z0
...
double xn
double yn
double zn

5.3.2.11 writePointsPLY() [1/2]

```
bool GEOM_FADE25D::writePointsPLY (
        const char * filename,
        std::vector< Point2 * > & vPoints,
        bool bASCII )
```

Parameters

vPoints	[in] are the points to be written
bASCII	specifies whether to write an ASCII- (true) or binary (false) *.ply file
filename	is the output filename

Note

Coordinates are rounded to 32-bit floating point numbers. Function available for platforms with C++11.

5.3.2.12 writePointsPLY() [2/2]

```
bool GEOM_FADE25D::writePointsPLY (
    std::ostream & os,
    std::vector< Point2 * > & vPoints,
    bool bASCII )
```

Parameters

vPoints	[in] are the points to be written
bASCII	specifies whether to write an ASCII- (true) or binary (false) *.ply file
os	is the output stream

Note

Coordinates are rounded to 32-bit floating point numbers. Function available for platforms with C++11.

5.3.2.13 writeSegmentsBIN()

```
bool GEOM_FADE25D::writeSegmentsBIN (
    const char * filename,
    std::vector< Segment2 > & vSegmentsIn )
```

Binary file format:
int filetype (31)
size_t numSegments (`vSegmentsIn.size()`)
double x0_source
double y0_source
double z0_source
double x0_target
double y0_target
double z0_target
...
double xn_source
double yn_source
double zn_source
double xn_target
double yn_target
double zn_target

Note

Since version 1.64 the binary file format written by 32-bit machines is identical with the file format of x64 machines i.e., the numSegments value is always 8 bytes, not 4. This change affects only 32-bit programs.

See also

readSegmentsBIN()

5.4 Test Data Generators

Functions

- void GEOM_FADE25D::generateCircle (int numPoints, double x, double y, double z, double radiusX, double radiusY, std::vector< Point2 > &vCirclePointsOut)

  Generate a circle.
- void GEOM_FADE25D::generateRandomNumbers (size_t num, double min, double max, std::vector< double > &vRandomNumbersOut, unsigned int seed=0)

  Generate random numbers.
- void GEOM_FADE25D::generateRandomPoints (size_t numRandomPoints, double min, double max, std::vector< Point2 > &vRandomPointsOut, unsigned int seed=0)

  Generate random points.
- void GEOM_FADE25D::generateRandomPoints3D (size_t numRandomPoints, double min, double max, std::vector< Point2 > &vRandomPointsOut, unsigned int seed=0)

  Generate random points with height.
- void GEOM_FADE25D::generateRandomPolygon (size_t numSegments, double min, double max, std::vector< Segment2 > &vPolygonOut, unsigned int seed=0)

  Generate a random simple polygon.
- void GEOM_FADE25D::generateRandomSegments (size_t numSegments, double min, double max, double maxLen, std::vector< Segment2 > &vSegmentsOut, unsigned int seed)

  Generate random line segments.
- void GEOM_FADE25D::generateRandomSurfacePoints (size_t numX, size_t numY, size_t numCenters, double xmin, double ymin, double zmin, double xmax, double ymax, double zmax, std::vector< Point2 > &vSurfacePointsOut, unsigned int seed, bool bGrid=true)

  Generate a random surface.
- void GEOM_FADE25D::generateSineSegments (int numSegments, int numPeriods, double xOffset, double yOffset, double xFactor, double yFactor, bool bSwapXY, std::vector< Segment2 > &vSineSegmentsOut)

  Generate segments from a sine function.
- void **GEOM_FADE25D::shear** (std::vector< Point2 > &vPointsInOut, double shearX, double shearY)

5.4.1 Detailed Description

5.4.2 Generate random polygons and other test objects

Theory, careful programming and automated software stress tests. Neither of them can replace the other one. Testing with random data helps to discover errors early. Fade provides random object generators for your automated software stress tests:

- Random simple polygons
- Random segments
- Random point clouds
- Random numbers.
- Polylines from sine functions

If you discover an error in your software you must be able to reproduce the input data that has triggered your bug. For this reason the random object generators take a seed value to initialize the internal random number generators. A certain seed value always leads to the same sequence of objects. Only when the special seed value 0 is used then the random number generators are initialized from the system time.

5.4.3 Function Documentation

5.4.3.1 generateCircle()

```
void GEOM_FADE25D::generateCircle (
        int numPoints,
        double x,
        double y,
        double z,
        double radiusX,
        double radiusY,
        std::vector< Point2 > & vCirclePointsOut )
```

Returns points on a circle centered at the given coordinates

5.4.3.2 generateRandomNumbers()

```
void GEOM_FADE25D::generateRandomNumbers (
        size_t num,
        double min,
        double max,
        std::vector< double > & vRandomNumbersOut,
        unsigned int seed = 0 )
```

Parameters

	num	Number of random numbers to be generated
	min	Lower bound
	max	Upper bound
out	*vRandomNumbersOut*	is the output vector
	seed	initializes the random number generator RNG (default: 0...mapped to a random seed, other values: constant initialization)

Note

Reproducable random numbers are often desirable when software is tested with random geometric constructions. Thus each seed value different from *0* leads to its own, reproducible, output sequence. In contrast the `seed` value *0* is mapped to random initialization of the RNG. In this case the RNG will produce a different output sequence each time it is called.

5.4.3.3 generateRandomPoints()

```
void GEOM_FADE25D::generateRandomPoints (
        size_t numRandomPoints,
        double min,
        double max,
        std::vector< Point2 > & vRandomPointsOut,
        unsigned int seed = 0 )
```

Parameters

	numRandomPoints	Number of points to be generated
	min	Lower bound (x,y)
	max	Upper bound (x,y)
out	*vRandomPointsOut*	is the output vector
	seed	initializes the random number generator RNG (default: 0...mapped to a random seed, other values: constant initialization)




Figure 2 Point generator

5.4.3.4 generateRandomPoints3D()

```
void GEOM_FADE25D::generateRandomPoints3D (
        size_t numRandomPoints,
        double min,
        double max,
        std::vector< Point2 > & vRandomPointsOut,
        unsigned int seed = 0 )
```

Parameters

	numRandomPoints	Number of points to be generated
	min	Lower bound (x,y)
	max	Upper bound (x,y)
out	*vRandomPointsOut*	is the output vector
	seed	initializes the random number generator RNG (default: 0...mapped to a random seed, other values: constant initialization)




Figure 3 Point generator

5.4.3.5 generateRandomPolygon()

```
void GEOM_FADE25D::generateRandomPolygon (
        size_t numSegments,
        double min,
        double max,
        std::vector< Segment2 > & vPolygonOut,
        unsigned int seed = 0 )
```

Parameters

	numSegments	Number of segments to be generated
	min	Lower bound (x,y)
	max	Upper bound (x,y)
out	*vPolygonOut*	is the output vector
	seed	initializes the random number generator RNG (default: 0...mapped to a random seed, other values: constant initialization)




Figure 4 Polygon generator: Random simple polygon

5.4.3.6 generateRandomSegments()

```
void GEOM_FADE25D::generateRandomSegments (
        size_t numSegments,
        double min,
        double max,
        double maxLen,
        std::vector< Segment2 > & vSegmentsOut,
        unsigned int seed )
```

Parameters

	numSegments	Number of segments to be generated
	min	Lower bound (x,y)
	max	Upper bound (x,y)
	maxLen	Maximal segment length
out	*vSegmentsOut*	is the output vector
	seed	initializes the random number generator RNG (default: 0...mapped to a random seed, other values: constant initialization)



Figure 5 Segment generator: Random line segments

5.4.3.7 generateRandomSurfacePoints()

```
void GEOM_FADE25D::generateRandomSurfacePoints (
        size_t numX,
        size_t numY,
        size_t numCenters,
        double xmin,
        double ymin,
        double zmin,
        double xmax,
        double ymax,
        double zmax,
        std::vector< Point2 > & vSurfacePointsOut,
        unsigned int seed,
        bool bGrid = true )
```

Parameters

	numX,numY	specifies the grid size and must be >1. numX∗numY points are created
	numCenters	defines the number of extreme points (must be >0)
	xmin,ymin,zmin,xmax,ymax,zmax	specifies the geometric bounds
out	*vSurfacePointsOut*	is the output vector
	seed	initializes the random number generator RNG
	bGrid	specifies whether the created points shall be exactly on a grid or slightly randomized (default: 0...mapped to a random seed, other values: constant initialization)

5.4.3.8 generateSineSegments()

```
void GEOM_FADE25D::generateSineSegments (
        int numSegments,
        int numPeriods,
        double xOffset,
        double yOffset,
        double xFactor,
        double yFactor,
        bool bSwapXY,
        std::vector< Segment2 > & vSineSegmentsOut )
```

Parameters

	numSegments	Number of segments to be generated
	numPeriods	Number of periods of the sine function
	xOffset	Offset of the output x-coordinates
	yOffset	Offset of the output y-coordinates
	xFactor	Factor to scale the sine function in x direction
	yFactor	Factor to scale the sine function in y direction
	bSwapXY	Swap the x and y coordinate of the function
out	*vSineSegmentsOut*	is the output vector




Figure 6 Polyline generator: Polylines from sine functions

6 Class Documentation

6.1 GEOM_FADE25D::Bbox2 Class Reference

Bbox2 is an axis aligned 2D bounding box.
`#include <Bbox2.h>`

Public Member Functions

- Bbox2 (GeomTest *pGeomTest_=NULL)
  Constructor.
- bool add (const Bbox2 &other)
  Add another bounding box.
- bool add (const Point2 &p)
  Add a point.
- bool add (size_t numPoints, double *coordinates)
  Add points.
- bool add (std::vector< Point2 * >::const_iterator start_it, std::vector< Point2 * >::const_iterator end_it)
  Add points.
- bool add (std::vector< Point2 >::const_iterator start_it, std::vector< Point2 >::const_iterator end_it)
  Add points.
- Point2 computeCenter () const
  Compute the 2D midpoint.
- bool doIntersect (const Bbox2 &other) const
  Check intersection.
- void doubleTheBox ()
  Double the box.
- void enlargeRanges (double factor, bool bUseMaxRange, double minRange)
  Enlarge the x|y-ranges of a bounding box.
- double get_maxX () const
  Get maxX.
- double get_maxY () const
  Get maxY.
- double get_minX () const
  Get minX.
- double get_minY () const
  Get minY.
- void getBoundary (std::vector< Segment2 > &vBoundary) const
  Get boundary.
- void getBounds (double &minX_, double &maxX_, double &minY_, double &maxY_) const
  Get bounds.
- void getCorners (std::vector< Point2 > &vBoxCorners) const
  Get corners.
- double getMaxCoord () const
  Get maximum coordinate.
- Point2 getMaxPoint () const
  Get the max point.
- double getMaxRange () const
  Get max range.
- double getMinCoord () const
  Get minimum coordinate.
- Point2 getMinPoint () const

Get the min point.

- void getOffsetCorners (double offset, std::vector< Point2 > &vBoxCorners) const

  Get offset corners.
- double getRangeX () const

  Get x-range.
- double getRangeY () const

  Get y-range.
- void inflateIfDegenerate (double val)

  Inflate if Degenerate.
- bool isInBox (const Point2 &p) const

  Point-in-Box Test.
- bool isValid () const

  Check if the bounds are valid.
- Bbox2 operator+ (const Bbox2 &b)

  Add a bounding box.
- void reset ()

  Reset the bounds.
- void setMaxX (double val)

  Set maxX.
- void setMaxY (double val)

  Set maxY.
- void setMinX (double val)

  Set minX.
- void setMinY (double val)

  Set minY.

Protected Member Functions

- void **treatPointForInvalidBox** (const Point2 &p)
- void **treatPointForValidBox** (const Point2 &p)
- bool **updateMaxAbs** ()

Protected Attributes

- bool **bValid**
- double **maxAbsCoord**
- double **maxX**
- double **maxY**
- double **minX**
- double **minY**
- GeomTest * **pGeomTest**

Friends

- std::ostream & operator<< (std::ostream &stream, const Bbox2 &pC)

  Print the box.

6.1.1 Constructor & Destructor Documentation

6.1.1.1 Bbox2() `GEOM_FADE25D::Bbox2::Bbox2 (`

`GeomTest * pGeomTest_ = NULL ) [inline], [explicit]`

Minimum bounds are initialized to DBL_MAX. Maximum bounds are initialized to -DBL_MAX. Box is not valid yet

6.1.2 Member Function Documentation

6.1.2.1 add() [1/5] bool GEOM_FADE25D::Bbox2::add (const Bbox2 & *other*) [inline]

Extends the 2D bounding box if required.

Returns

true if the bounding box changes, false otherwise

6.1.2.2 add() [2/5] bool GEOM_FADE25D::Bbox2::add (const Point2 & *p*) [inline]

Extends the 2D bounding box if required.

Returns

true if the bounding box changes, false otherwise

6.1.2.3 add() [3/5] bool GEOM_FADE25D::Bbox2::add (size_t *numPoints*, double * *coordinates*) [inline]

Extends the 2D bounding box if required.

Returns

true if the bounding box changes, false otherwise

6.1.2.4 add() [4/5] bool GEOM_FADE25D::Bbox2::add (std::vector< Point2 * >::const_iterator *start_it*, std::vector< Point2 * >::const_iterator *end_it*) [inline]

Extends the 2D bounding box if required.

Returns

true if the bounding box changes, false otherwise

6.1.2.5 add() [5/5] bool GEOM_FADE25D::Bbox2::add (std::vector< Point2 >::const_iterator *start_it*, std::vector< Point2 >::const_iterator *end_it*) [inline]

Extends the 2D bounding box if required.

Returns

true if the bounding box changes, false otherwise

6.1.2.6 doIntersect() bool GEOM_FADE25D::Bbox2::doIntersect (const Bbox2 & *other*) const

Two valid bounding boxes intersect if they share at least one point in the XY plane.

6.1.2.7 doubleTheBox() void GEOM_FADE25D::Bbox2::doubleTheBox ( )

Changes the bounds such that the box grows in each direction by half the previous range

6.1.2.8 enlargeRanges() `void GEOM_FADE25D::Bbox2::enlargeRanges (`

```
double factor,
bool bUseMaxRange,
double minRange )
```

This function updates `minX`, `minY`, `maxX` and `maxY` symmetrically to enlarge the `x-` and `y-ranges` of the bounding box.

Parameters

factor	is the factor by which the existing ranges `rangeX` and `rangeY` shall grow.
bUseMaxRange	specifies if a square bounding box with side length $factor * max(rangeX, rangeY)$ shall be made.
minRange	is a lower bound on the new ranges and it can be used to avoid a degenerate box when the pre-existing box was degenerate.

6.1.2.9 get_maxX() `double GEOM_FADE25D::Bbox2::get_maxX ( ) const [inline]`

Returns

maxX

6.1.2.10 get_maxY() `double GEOM_FADE25D::Bbox2::get_maxY ( ) const [inline]`

Returns

maxY

6.1.2.11 get_minX() `double GEOM_FADE25D::Bbox2::get_minX ( ) const [inline]`

Returns

minX

6.1.2.12 get_minY() `double GEOM_FADE25D::Bbox2::get_minY ( ) const [inline]`

Returns

minY

6.1.2.13 getBoundary() `void GEOM_FADE25D::Bbox2::getBoundary (`

```
std::vector< Segment2 > & vBoundary ) const
```

Convenience function: Returns 4 border segments

6.1.2.14 getCorners() `void GEOM_FADE25D::Bbox2::getCorners (`

```
std::vector< Point2 > & vBoxCorners ) const
```

Convenience function: Returns the 4 corners of the box

6.1.2.15 getMaxCoord() `double GEOM_FADE25D::Bbox2::getMaxCoord ( ) const [inline]`

Returns

the largest coordinate value, i.e. max(maxX,maxY)

6.1.2.16 getMaxPoint() `Point2 GEOM_FADE25D::Bbox2::getMaxPoint ( ) const [inline]`

Returns

the 2D corner point with the maximum coordinates, the z-coordinate is set to 0

6.1.2.17 getMaxRange() `double GEOM_FADE25D::Bbox2::getMaxRange ( ) const [inline]`

Returns

the largest range, i.e. max(getRangeX(),getRangeY())

6.1.2.18 getMinCoord() `double GEOM_FADE25D::Bbox2::getMinCoord ( ) const [inline]`

Returns

the smallest coordinate value, i.e. min(minX,minY)

6.1.2.19 getMinPoint() `Point2 GEOM_FADE25D::Bbox2::getMinPoint ( ) const [inline]`

Returns

the corner point with the minimum coordinates, the z-coordinate is set to 0

6.1.2.20 getOffsetCorners()

```
void GEOM_FADE25D::Bbox2::getOffsetCorners (
        double offset,
        std::vector< Point2 > & vBoxCorners ) const
```

Convenience function: Returns the 4 corners of an enlarged box. The box es enlarged by `offset` in each direction

6.1.2.21 getRangeX() `double GEOM_FADE25D::Bbox2::getRangeX ( ) const [inline]`

Returns

maxX-minX

6.1.2.22 getRangeY() `double GEOM_FADE25D::Bbox2::getRangeY ( ) const [inline]`

Returns

maxY-minY

6.1.2.23 inflateIfDegenerate()

```
void GEOM_FADE25D::Bbox2::inflateIfDegenerate (
        double val ) [inline]
```

When only one point has been added to Bbox2 or when all points have the same x- and/or y- coordinates then Bbox2 is degenerate. This is a valid state but sometimes undesireable. The present method inflates the Bbox2 by adding /p val to maxX and/or maxY.

6.1.2.24 isInBox()

```
bool GEOM_FADE25D::Bbox2::isInBox (
        const Point2 & p ) const
```

Returns

true if minX <= p.x() <=maxX and minY <= p.y() <=maxY or false otherwise.

6.1.2.25 isValid() `bool GEOM_FADE25D::Bbox2::isValid ( ) const [inline]`

The bounds are valid when at least one point has been added or when set-methods have been used to set minX<=maxX and minY<=maxY

6.1.2.26 operator+() `Bbox2 GEOM_FADE25D::Bbox2::operator+ ( const Bbox2 & b )`

Extends the 2D bounding box if required.

Returns

the resulting bounding box

6.1.2.27 reset() `void GEOM_FADE25D::Bbox2::reset ( ) [inline]`

Resets the bounding box to default values

6.1.3 Friends And Related Function Documentation

6.1.3.1 operator<< `std::ostream& operator<< ( std::ostream & stream, const Bbox2 & pC ) [friend]`

Prints the box coordinates to `stream`

The documentation for this class was generated from the following file:

- Bbox2.h

6.2 GEOM_FADE25D::CAF_Component Class Reference

CAF_Component stands for CUT AND FILL COMPONENT. It represents a connected area of the surface.

`#include <CAF_Component.h>`

Public Member Functions

- **CAF_Component** (std::vector< Triangle2 * > &vT_, std::map< Point2 *, std::pair< double, double > > &mVtx2BeforeAfter_, int label_)
- void getBorder (std::vector< Segment2 > &vBorderSegments) const

  Get border.
- CAFTYP getCAFType () const

  Get Cut&Fill-Type.
- int getLabel () const

  Get label.
- void getTriangles (std::vector< Triangle2 * > &vTrianglesOut) const

  Get Triangles.
- double getVolume () const

  Get the volume.

Protected Member Functions

- void **init** (std::map< Point2 *, std::pair< double, double > > &mVtx2BeforeAfter)
- void **setVolume** (std::vector< Point2 > *pvBeforeT, std::vector< Point2 > *pvAfterT, std::vector< Point2 > *pvWallT)
- void **showGeomview** (const char *name, std::vector< Point2 > *pvBeforeT, std::vector< Point2 > *pv↩ AfterT, std::vector< Point2 > *pvWallT) const

Protected Attributes

- CAFTYP **caftype**
- int **label**
- std::vector< Triangle2 * > * **pVT**
- double **volume**

6.2.1 Detailed Description

A CAF_Component object represents a connected part of the surface such that:

- the first surface is below the second one (CAFTYP=CT_FILL) or
- the first surface is above the second one (CAFTYP=CT_CUT) or
- the first surface corresponds to the second one (CAFTYP=CT_NULL)

6.2.2 Member Function Documentation

6.2.2.1 getBorder() `void GEOM_FADE25D::CAF_Component::getBorder ( std::vector< Segment2 > & vBorderSegments ) const`

Returns

border segments of the present component in no particular order

6.2.2.2 getCAFType() `CAFTYP GEOM_FADE25D::CAF_Component::getCAFType ( ) const`

Returns

CT_CUT, CT_FILL or CT_NULL

- CT_CUT means that earth must be digged off to turn the first surface into the second one,
- CT_FILL means that earth must be added.
- CT_NULL is returned when the first surface corresponds to the second one.

6.2.2.3 getLabel() `int GEOM_FADE25D::CAF_Component::getLabel ( ) const`

Returns

the component label

Components are consecutively numbered.

6.2.2.4 getTriangles() `void GEOM_FADE25D::CAF_Component::getTriangles ( std::vector< Triangle2 * > & vTrianglesOut ) const`

Returns

the triangles of the present component. The z-coordinates of their corners correspond to the height differences between the two input surfaces.

Parameters

out	*vTrianglesOut*	is used to return the triangles

6.2.2.5 getVolume() `double GEOM_FADE25D::CAF_Component::getVolume ( ) const`

Returns

the volume of the present component.

Note

The volume is an absolute value. Use getCAFType() to determine if it is a CUT, FILL or ZERO volume.

Warning

The computations are unitless but you must make sure that the x, y, and z-coordinate are given in the same unit.

The documentation for this class was generated from the following file:

- CAF_Component.h

6.3 GEOM_FADE25D::Circle2 Class Reference

Circle for visualization.
`#include <Circle2.h>`

Public Member Functions

- Circle2 (const Point2 &center_, double sqRadius_)
  Constructor.
- Circle2 (double x, double y, double sqRadius_)
  Constructor.
- Point2 getCenter ()
  Get the center of the circle.
- double getRadius ()
  Get the radius of the circle.
- double getSqRadius ()
  Get the squared radius of the circle.

Protected Attributes

- Point2 **center**
- double **sqRadius**

Friends

- std::ostream & **operator**<< (std::ostream &stream, Circle2 b)

6.3.1 Detailed Description

See also

Visualizer2

6.3.2 Constructor & Destructor Documentation

6.3.2.1 Circle2() [1/2] `GEOM_FADE25D::Circle2::Circle2 (`

```
double x,
double y,
double sqRadius_ )
```

Parameters

x	is x-coordinate of the center
y	is y-coordinate of the center
*sq↩ Radius_*	is the squared radius of the circle

Warning

The method expects the *squared* radius

6.3.2.2 Circle2() [2/2] GEOM_FADE25D::Circle2::Circle2 (const Point2 & *center_*, double *sqRadius_*)

Parameters

*center_*	center of the circle
*sq↩ Radius_*	squared radius of the circle

Warning

The method expects the *squared* radius

6.3.3 Member Function Documentation

6.3.3.1 getCenter() Point2 GEOM_FADE25D::Circle2::getCenter ( )

Returns

a Point2 which represents the center

6.3.3.2 getRadius() double GEOM_FADE25D::Circle2::getRadius ( )

Returns

the radius

6.3.3.3 getSqRadius() double GEOM_FADE25D::Circle2::getSqRadius ( )

Returns

the squared radius

The documentation for this class was generated from the following file:

- Circle2.h

6.4 GEOM_FADE25D::CloudPrepare Class Reference

CloudPrepare simplifies overdense point clouds and helps to avoid memory-usage-peaks during data transfer.
`#include <CloudPrepare.h>`

Public Member Functions

- size_t adaptiveSimplify (double maxDiffZ, SumStrategy sms, ConvexHullStrategy chs, bool bDryRun=false)

  Simplify the Point Cloud according to a tolerance z-value.
- void add (const std::vector< Point2 > &vPoints)

  Add points to the CloudPrepare object (vector-version)
- void add (double x, double y, double z, int customIndex=-1)

  Add a point to the CloudPrepare object.
- void add (size_t numPoints, double *aCoordinates)

  Add points to the CloudPrepare object (array-version)
- void clear ()

  Clear all stored data.
- bool computeConvexHull (bool bAllPoints, std::vector< Point2 > &vConvexHull)

  Compute the 2.5D Convex Hull.
- void getBounds (double &minX, double &minY, double &minZ, double &maxX, double &maxY, double &maxZ)

  Get the min/max bounds.
- size_t getNumPoints () const

  Get the number of points.
- void getPoints (std::vector< Point2 > &vPointsOut) const

  Get the simplified point cloud.
- double getRangeX ()
- double getRangeY ()
- double getRangeZ ()
- size_t uniformSimplifyGrid (double gridLength, SumStrategy sms, ConvexHullStrategy chs, bool bDry↩ Run=false)

  Simplify the point cloud according to grid resolution.
- size_t uniformSimplifyNum (int approxNumPoints, SumStrategy sms, ConvexHullStrategy chs)

  Simplify the Point Cloud to a specific target size.

6.4.1 Detailed Description

This class has two applications:

1. **Simplification of over-dense point clouds** from areal and photogrammetry surveys. The reduction is either grid-based or z-adaptive with a tolerance threshold for the height error. Four strategies can be selected for grouping similar points: MIN, MAX, MEDIAN and AVG. MIN corresponds to simple ground filtering, since it favors ground measurement points over those on vegetation. MEDIAN stabilizes the point cloud because it removes outliers while AVG is well suited to reduce noise in the scan.

2. **Avoding memory usage peaks** when triangulating a large point cloud: Usually you have all vertices in the data structures of your own software and when you then call Fade_2D::insert(), triangles are created immediately and only after that you have the possibility to remove the points from your own data structures. This means for a short time the vertices are duplicated in memory, and this creates an unnecessary memory peak. The solution is to give the points to the CloudPrepare class in advance (one-by-one or all at once) and to delete them from your own data structures while not a single triangle exists yet. Only then call Fade_2D↩ ::insert(&CloudPrepare).This avoids duplicating memory usage for the vertices.

Have a look at the `Examples`.

Note

This class replaces the EfficientModel class. It is much more memory-efficient and it is extremely fast.




Figure 7 Point Cloud Reduction: Left original, right reduced

6.4.2 Member Function Documentation

6.4.2.1 adaptiveSimplify()

```
size_t GEOM_FADE25D::CloudPrepare::adaptiveSimplify (
        double maxDiffZ,
        SumStrategy sms,
        ConvexHullStrategy chs,
        bool bDryRun = false )
```

This method simplifies the point cloud height-adaptively. This means that adjoining points with similar z-values (within the given tolerance `maxDiffZ`) are combined into one.

Parameters

maxDiffZ	[in] is the maximum height (z-coordinate) difference of points, so that these points are combined to one.
sms	[in] is the strategy used to summarize similar points into one. Possible values are SMS_MINIMUM, SMS_MAXIMUM, SMS_MEDIAN and SMS_AVERAGE.
chs	[in] is the ConvexHullStrategy: Use CHS_MAXHULL to keep all points of the convex hull unchanged. If only convex points but not collinear points of the convex hull are to be considered as convex hull points, then use CHS_MINHULL. If convex hull points should be treated like all other points, then use CHS_NOHULL.
bDryRun	is used to avoid point cloud simplification. This is used to determine the number of points that would result from simplification with certain parameters. By default bDryRun=false.

Returns

the resulting number of points

6.4.2.2 add() [1/3]

```
void GEOM_FADE25D::CloudPrepare::add (
        const std::vector< Point2 > & vPoints )
```

Parameters

vPoints	[in] are the input points

6.4.2.3 add() [2/3]

```
void GEOM_FADE25D::CloudPrepare::add (
        double x,
        double y,
        double z,
        int customIndex = -1 )
```

Parameters

	x,y,z	[in] are the coordinates
in	*customIndex*	is an optional index that you can use to relate the point to your own data structures.

Note

If you call Point2::getCustomIndex() on this point at a later time, then exactly this index will be returned.

6.4.2.4 add() [3/3]

```
void GEOM_FADE25D::CloudPrepare::add (
        size_t numPoints,
        double * aCoordinates )
```

Parameters

numPoints	[in] specifies the number of input points
aCoordinates	[in] an array that holds 3∗numPoints coordinates (x0,y0,z0,x1,y1,z1,...,xn,yn,zn)

6.4.2.5 computeConvexHull()

```
bool GEOM_FADE25D::CloudPrepare::computeConvexHull (
        bool bAllPoints,
        std::vector< Point2 > & vConvexHull )
```

Parameters

bAllPoints	If this parameter is *true*, then all convex hull points are returned. Otherwise, those points are omitted which lie on the convex hull but whose absence does not shrink the convex hull
vConvexHull	[out] is used to return the convex hull points

6.4.2.6 getBounds()

```
void GEOM_FADE25D::CloudPrepare::getBounds (
        double & minX,
        double & minY,
        double & minZ,
        double & maxX,
        double & maxY,
        double & maxZ )
```

Parameters

minX,minY,minZ,maxX,maxY,maxZ	[out]

6.4.2.7 getNumPoints()

```
size_t GEOM_FADE25D::CloudPrepare::getNumPoints ( ) const
```

Returns

the number of points

6.4.2.8 getPoints()

```
void GEOM_FADE25D::CloudPrepare::getPoints (
        std::vector< Point2 > & vPointsOut ) const
```

Parameters

vPointsOut	[out] is used to return the points

Note

The points of the CloudPrepare object can be inserted directly with Fade_2D::insert(CloudPrepare). This is more memory efficient than getting the points out first only to pass them to insert().

See also

Fade_2D::void insert(CloudPrepare* pCloudPrepare,bool bClear=true)

6.4.2.9 getRangeX()

```
double GEOM_FADE25D::CloudPrepare::getRangeX ( )
```

Returns

the x-Range

6.4.2.10 getRangeY()

```
double GEOM_FADE25D::CloudPrepare::getRangeY ( )
```

Returns

the y-Range

6.4.2.11 getRangeZ()

```
double GEOM_FADE25D::CloudPrepare::getRangeZ ( )
```

Returns

the z-Range

6.4.2.12 uniformSimplifyGrid()

```
size_t GEOM_FADE25D::CloudPrepare::uniformSimplifyGrid (
        double gridLength,
        SumStrategy sms,
        ConvexHullStrategy chs,
        bool bDryRun = false )
```

This method uses a thought grid in the xy plane and combines the points of each cell into a single point.

Parameters

gridLength	[in] determines the horizontal and vertical cell spacing in the grid.
sms	[in] is the SumStrategy used to combine similar points into one. Possible values are SMS_MINIMUM, SMS_MAXIMUM, SMS_MEDIAN and SMS_AVERAGE.
chs	[in] is the ConvexHullStrategy: Points of the convex hull can be kept unchanged. Use CHS_MAXHULL for this purpose. If only convex points but not collinear points of the convex hull are to be considered as convex hull points, then use CHS_MINHULL. If convex hull points should be treated like all other points, then use CHS_NOHULL.
bDryRun	is used to avoid point cloud simplification. This is used to determine the number of points that would result from simplification with certain parameters. By default bDryRun=false.

Returns

the resulting number of points

6.4.2.13 uniformSimplifyNum()

```
size_t GEOM_FADE25D::CloudPrepare::uniformSimplifyNum (
        int approxNumPoints,
        SumStrategy sms,
        ConvexHullStrategy chs )
```

This method uses a thought grid in the xy plane and combines the points of each cell into a single point. The resolution of the grid is automatically determined such that the point cloud is reduced to approximately the desired number of points.

Parameters

approxNumPoints	[in] is the desired number of remaining points. The algorithm will reduce the point cloud to approximately that number of points.
sms	[in] is the SumStrategy used to combine similar points into one. Possible values are SMS_MINIMUM, SMS_MAXIMUM, SMS_MEDIAN and SMS_AVERAGE.
chs	[in] is the ConvexHullStrategy: Points of the convex hull can be kept unchanged. Use CHS_MAXHULL for this purpose. If only convex points but not collinear points of the convex hull are to be considered as convex hull points, then use CHS_MINHULL. If convex hull points should be treated like all other points, then use CHS_NOHULL.

Returns

the resulting number of points

The documentation for this class was generated from the following file:

- CloudPrepare.h

6.5 GEOM_FADE25D::Color Class Reference

Color for visualization.

`#include <Color.h>`

Public Member Functions

- Color (Colorname c, float width_=0.001, bool bFill_=false)
- Color (double r_, double g_, double b_, double width_, bool bFill_=false)
- bool **operator!=** (const Color &other) const
- bool **operator<** (const Color &other) const
- bool **operator==** (const Color &other) const

Static Public Member Functions

- static Colorname **getNextColorName** ()

Public Attributes

- float b

  Blue.
- bool bFill

  Fill the shape or not.
- float g

  Green.

- float r

  Red.
- float width

  Linewidth.

Friends

- std::ostream & **operator**<< (std::ostream &stream, const Color &c)

6.5.1 Detailed Description

See also

Visualizer2

6.5.2 Constructor & Destructor Documentation

6.5.2.1 Color() [1/2] GEOM_FADE25D::Color::Color (

```
double r_,
double g_,
double b_,
double width_,
bool bFill_ = false )
```

Parameters

*r_*	red
*g_*	green
*b_*	blue
*width_*	linewidth
*bFill_*	fill (default: *false*) has two meanings: Objects that have an area, like Triangle2, Circle2 and VoroCell2, are filled with the specified rgb-color while line segments with `bFill=true` will be drawn with x-marks at their endpoints.

6.5.2.2 Color() [2/2] GEOM_FADE25D::Color::Color (

```
Colorname c,
float width_ = 0.001,
bool bFill_ = false ) [explicit]
```

For convenience predefined colors can be used.

Parameters

c	is a predefined color name
*width_*	linewidth (default: *0.001*)
*bFill_*	fill (default: *false*)

Note

bFill_=true has two meanings: Objects that can be filled (Triangle2, Circle2) are filled with the rgb-color but line segments get x-marks at their endpoints.

The documentation for this class was generated from the following file:

- Color.h

6.6 GEOM_FADE25D::CompPolygon Struct Reference

Connected component with boundary- and hole polygons.
`#include <Zone2.h>`

Public Member Functions

- **CompPolygon** (const CompPolygon &other)
- CompPolygon & **operator=** (const CompPolygon &other)

Public Attributes

- std::vector< Triangle2 * > * pvCC

  Connected component of triangles (connection along edges, not just vertices)
- std::vector< Edge2 > * pvOuterPolygon

  Ordered outer polygon.
- std::vector< std::vector< Edge2 > > * pvvHolePolygons

  Ordered hole polygons.

6.6.1 Detailed Description

The CompPolygon struct holds a connected component of triangles. Thereby two triangles count as connected if they share a common edge. It also holds an ordered vector of polygon edges and ordered vectors of hole edges.

Remarks

An edge is represented by a triangle and an opposite index. Its orientation is always counterclockwise (CCW) around the triangle. Thus outer polygon edges are counterclockwise while hole polygons (if any) are clockwise (CW) oriented.

The documentation for this struct was generated from the following file:

- Zone2.h

6.7 GEOM_FADE25D::ConstraintGraph2 Class Reference

ConstraintGraph2 is a set of Constraint Edges (ConstraintSegment2)
`#include <ConstraintGraph2.h>`

Public Member Functions

- void getChildConstraintSegments (std::vector< ConstraintSegment2 * > &vConstraintSegments_) const

  Get child ConstraintSegment2 objects.
- void getDirectChildren (ConstraintSegment2 *pParent, ConstraintSegment2 *&pChild0, ConstraintSegment2 *&pChild1)

  Get direct children.
- Dt2 * getDt2 ()
- ConstraintInsertionStrategy getInsertionStrategy () const

  Get the constraint insertion strategy.
- void getOriginalConstraintSegments (std::vector< ConstraintSegment2 * > &vConstraintSegments_) const

  Get the original ConstraintSegment2 objects.
- void getPolygonVertices (std::vector< Point2 * > &vVertices_)

  Get the vertices of the constraint segments.
- bool isConstraint (ConstraintSegment2 *pCSeg) const

Check if a ConstraintSegment2 is a member.

- bool isConstraint (Point2 *p0, Point2 *p1) const

  Check if an edge is a constraint segment.
- bool isOriented () const

  Are the segments of the constraint graph oriented?
- bool isPolygon () const

  Does the constraint graph form a closed polygon?
- bool isReverse (ConstraintSegment2 *pCSeg) const
- bool makeDelaunay (double minLength)
- void show (const char *name)

  Visualization.
- void show (Visualizer2 *pVis, const Color &color)

  Visualization.

Protected Attributes

- bool **bIsOriented**
- bool **bIsPolygon**
- ConstraintInsertionStrategy **cis**
- std::map< ConstraintSegment2 *, bool, func_ltDerefPtr< ConstraintSegment2 * > > **mCSegReverse**
- std::map< Point2 *, size_t > **mSplitPointNum**
- Dt2 * **pDt2**
- GeomTest * **pGeomPredicates**
- std::vector< ConstraintSegment2 * > **vCSegParents**

6.7.1 Detailed Description

See also

Fade_2D::createConstraint()




Figure 8 Constraint Delaunay triangulation

6.7.2 Member Function Documentation

6.7.2.1 getChildConstraintSegments()

```
void GEOM_FADE25D::ConstraintGraph2::getChildConstraint↩
Segments (
            std::vector< ConstraintSegment2 * > & vConstraintSegments_ ) const
```

Returns the current constraint segments, i.e., the original ones or, if splitted, their child segments.

6.7.2.2 getDirectChildren()

```
void GEOM_FADE25D::ConstraintGraph2::getDirectChildren (
        ConstraintSegment2 * pParent,
        ConstraintSegment2 *& pChild0,
        ConstraintSegment2 *& pChild1 )
```

Parameters

in	*pParent*	is a ConstraintSegment that may have been splitted
out	*pChild0,pChild1*	are the direct child segments of `pParent`. They can be alive or dead (splitted).

The children are returned in the correct order of the present ConstraintGraph2.

6.7.2.3 getDt2()

```
Dt2* GEOM_FADE25D::ConstraintGraph2::getDt2 ( )
```

Returns

the Delaunay class it belongs to

6.7.2.4 getInsertionStrategy()

```
ConstraintInsertionStrategy GEOM_FADE25D::ConstraintGraph2::getInsertionStrategy ( ) const
```

Returns

CIS_CONFORMING_DELAUNAY, CIS_CONFORMING_DELAUNAY_SEGMENT_LEVEL or CIS_CONSTRAINED_DELAUNAY

6.7.2.5 getOriginalConstraintSegments()

```
void GEOM_FADE25D::ConstraintGraph2::getOriginalConstraintSegments (
        std::vector< ConstraintSegment2 * > & vConstraintSegments_ ) const
```

Get the original, ConstraintSegment2 objects. They are not subdivided but may be dead and have child segments (which may also be dead and have child segments...)

6.7.2.6 getPolygonVertices()

```
void GEOM_FADE25D::ConstraintGraph2::getPolygonVertices (
        std::vector< Point2 * > & vVertices_ )
```

Use this method to retrieve the vertices of the present ConstraintGraph2. If it forms ONE closed polygon, then the vertices are ordered and oriented in counterclockwise direction, e.g. (a,b,b,c,c,d,d,a). Otherwise they are returned in original order. Be aware that the order is only maintained if the ConstraintGraph2 has been created with Fade_2D::createConstraint(..,..,`bOrientedSegments=true`).

Note

The segments of the present ConstraintGraph2 may have been splitted. In this case the split points are also contained in the result. If, in the above example, the ConstraintSegment2(a,b) has been subdivided at vertex x then the result is (a,x,x,b,b,c,c,d,d,a).

See also

Zone2::getBorderEdges() and edgesToPolygons()

6.7.2.7 isConstraint() [1/2]

```
bool GEOM_FADE25D::ConstraintGraph2::isConstraint (
        ConstraintSegment2 * pCSeg ) const
```

The present ConstraintGraph2 has been created using a set of edges and this method checks if the ConstraintSegment2 `pCSeg` is one of them. Original edges that have been splitted are not alive anymore and are no members. But their child segments are members.

6.7.2.8 isConstraint() [2/2] bool GEOM_FADE25D::ConstraintGraph2::isConstraint (Point2 * p0, Point2 * p1) const

Checks if the edge (p0,p1) is a constraint segment of the present ConstraintGraph2 object. The order of p0 and p1 does not matter.

6.7.2.9 isOriented() bool GEOM_FADE25D::ConstraintGraph2::isOriented ( ) const

Returns

true if the constraint graph has been created with bOrientedSegments=true or if automatic reorientation was possible which is the case for simple polygons.

6.7.2.10 isPolygon() bool GEOM_FADE25D::ConstraintGraph2::isPolygon ( ) const

Returns

true when the present ConstraintGraph forms a closed polygon.

Note

This method won't check if it is a simple polygon (one without self-intersections).

6.7.2.11 isReverse() bool GEOM_FADE25D::ConstraintGraph2::isReverse (ConstraintSegment2 * *pCSeg*) const

Get the orientation of a ConstraintSegment2
A ConstraintSegment2 `pCSeg` is unoriented because it may participate (with different orientations) in more than just one ConstraintGraph2 and thus the vertices returned by pCSeg->getSrc() and pCSeg->getTrg() do not carry any orientation information. However, the orientation of `pCSeg` is stored in the ConstraintGraph2 objects where `pCSeg` is a member and this method returns if the source and target vertex must be exchanged to match the present graph's direction.

6.7.2.12 makeDelaunay() bool GEOM_FADE25D::ConstraintGraph2::makeDelaunay (double *minLength*)

Improve the triangle quality (make Delaunay)
Constraint segments can make a triangulation locally non-delaunay i.e., the empty-circumcircle property is not maintained for all triangles. `makeDelaunay()` subdivides the constraint segments so that they appear naturally as part of the Delaunay triangulation. Use this function to create visually more appealing triangles with better aspect ratios.

Note

This optimization considers the projection of the triangles to the xy plane.

Parameters

in	*minLength*	specifies a lower bound. Constraint segments smaller than `minLength` are not subdivided. This parameter avoids excessive subdivision in narrow settings.

Returns

TRUE when all required somedevisions have been carried out or FALSE when `minLength` has avoided further subdivision.

The documentation for this class was generated from the following file:

- ConstraintGraph2.h

6.8 GEOM_FADE25D::ConstraintSegment2 Class Reference

A ConstraintSegment2 represents a Constraint Edge.
`#include <ConstraintSegment2.h>`

Public Member Functions

- void getChildrenAndSplitPoint (ConstraintSegment2 *&pCSeg0, ConstraintSegment2 *&pCSeg1, Point2 *&pSplitPoint)

  Get the children and the split point Retrieve the two direct children of the current ConstraintSegment2 as well as the split point.
- void getChildrenRec (std::vector< ConstraintSegment2 * > &vChildConstraintSegments)

  Get all children Recursively retrieve all children of the current ConstraintSegment2.
- ConstraintInsertionStrategy getCIS () const

  Get the Constraint Insertion Strategy (CIS)
- int **getLabel** () const
- std::string **getLabelString** () const
- Point2 * getSrc () const

  Get the first endpoint.
- Point2 * getTrg () const

  Get the second endpoint.
- Point2 * insertAndSplit (const Point2 &splitPoint)

  Split a constraint segment.
- bool isAlive () const

  Check if the present ConstraintSegment2 is alive.
- bool operator< (const ConstraintSegment2 &pOther) const

  operator<(..) Compares the vertex pointers of the endpoints, not the length
- bool split_combinatorialOnly (Point2 *pSplit)

  Split a constraint segment.

Public Attributes

- int **label**

Static Public Attributes

- static int **runningLabel**

Protected Attributes

- bool **bAlive**
- ConstraintInsertionStrategy **cis**
- Point2 * **p0**
- Point2 * **p1**
- std::vector< ConstraintSegment2 * > **vChildren**

Friends

- class **ConstraintGraph2**
- class **ConstraintMgr**
- std::ostream & **operator**<< (std::ostream &stream, const ConstraintSegment2 &cSeg)

6.8.1 Detailed Description

A ConstraintSegment2 can belong to more than one ConstraintGraph2 object, thus it is unoriented. But the ConstraintGraph knows the orientation of its ConstraintSegment2's.

6.8.2 Member Function Documentation

6.8.2.1 getCIS() `ConstraintInsertionStrategy GEOM_FADE25D::ConstraintSegment2::getCIS ( ) const`

Returns

the constraint insertion strategy (CIS) of the present object

6.8.2.2 getSrc() `Point2* GEOM_FADE25D::ConstraintSegment2::getSrc ( ) const`

Returns

the first vertex

6.8.2.3 getTrg() `Point2* GEOM_FADE25D::ConstraintSegment2::getTrg ( ) const`

Returns

the second vertex

6.8.2.4 insertAndSplit() `Point2* GEOM_FADE25D::ConstraintSegment2::insertAndSplit ( const Point2 & splitPoint )`

Splits the ConstraintSegment2 (which must be alive) at `splitPoint`.
It may be impossible to represent a point *exactly* on a line segment using floatingpoint arithmetic. Therefore it is highly recommended to split a ConstraintSegment2 object not just be inserting points into the triangulation but using the present method. It does not require that `splitPoint` is exactly on the segment.

Note

A splitted ConstraintSegment2 is dead and it has two child segments (which may also be dead and have children). The class is organized as a binary tree.

6.8.2.5 isAlive() `bool GEOM_FADE25D::ConstraintSegment2::isAlive ( ) const`

Returns

TRUE when the object is alive, FALSE otherwise

6.8.2.6 split_combinatorialOnly() `bool GEOM_FADE25D::ConstraintSegment2::split_combinatorialOnly ( Point2 * pSplit )`

internal use only (unless you do something very unusual)
The documentation for this class was generated from the following file:

- ConstraintSegment2.h

6.9 GEOM_FADE25D::CutAndFill Class Reference

CutAndFill computes the volume(s) between two overlapping surfaces.
`#include <CutAndFill.h>`

Public Member Functions

- CutAndFill (Zone2 *pZoneBefore, Zone2 *pZoneAfter, double ignoreThreshold=1e-6)

  Constructor.
- CAF_Component * getComponent (size_t ith) const

  Get component `ith`.
- bool getDiffZone (Zone2 *&pDiffZone, std::map< Point2 *, std::pair< double, double > > &mVtx2Before↩ After)

  Get the difference zone.
- size_t getNumberOfComponents () const

  Get the number of components.
- bool go (bool bWithMessages=true)

  Start the computation.
- void show (Visualizer2 *pVis) const

  Draw a postscript visualization.
- void subscribe (MsgType msgType, MsgBase *pMsg)

  Register a progress bar object.
- void unsubscribe (MsgType msgType, MsgBase *pMsg)

  Unregister a progress bar object.

6.9.1 Detailed Description




Figure 9 Overlapping input surfaces for Cut-And-Fill: RED=before, GREEN=after. The surfaces do not need to match exactly, the overlapping area is used

Given two overlapping surfaces with different elevations, CutAndFill partitions the surfaces into connected components and computes the volume that must be removed or added to turn one surface into the other.

See also

https://www.geom.at/cut-and-fill/

6.9.2 Constructor & Destructor Documentation

6.9.2.1 CutAndFill()

```
GEOM_FADE25D::CutAndFill::CutAndFill (
        Zone2 * pZoneBefore,
        Zone2 * pZoneAfter,
        double ignoreThreshold = 1e-6 )
```

Parameters

pZoneBefore	represents the surface before the earthworks
pZoneAfter	is the surface afterwards
ignoreThreshold	(default: 1e-6) can be used to ignore insignificant height differences

6.9.3 Member Function Documentation

6.9.3.1 getComponent()

```
CAF_Component* GEOM_FADE25D::CutAndFill::getComponent (
        size_t ith ) const
```

Returns

the `ith` CAF_Component.

6.9.3.2 getDiffZone()

```
bool GEOM_FADE25D::CutAndFill::getDiffZone (
        Zone2 *& pDiffZone,
        std::map< Point2 *, std::pair< double, double > > & mVtx2BeforeAfter )
```

This method gives access to the internal data structures, namely to a Zone2 object whose vertices have z-values that correspond to the height differences between the two input meshes (SurfaceBefore minus SurfaceAfter). And a map is returned that contains for each vertex the height in the first and in the second input mesh.

Returns

true in case of success, false otherwise.

Note

This method may set pDiffZone=NULL and return false when the two input surfaces do not share a common area. In this case the previous call to CutAndFill::go() has already returned false.

6.9.3.3 getNumberOfComponents()

```
size_t GEOM_FADE25D::CutAndFill::getNumberOfComponents ( ) const
```

Returns

the number of components.

A CAF_Component object represents a connected part of the surface such that

- the first surface is below the second one (Type CT_FILL)
- the first surface is above the second one (Type CT_CUT)
- the first surface corresponds to the second one (Type CT_NULL)

6.9.3.4 go()

```
bool GEOM_FADE25D::CutAndFill::go (
        bool bWithMessages = true )
```

Parameters

bWithMessages	is used to allow or suppress any warnings.

Returns

true in case of success, false otherwise.

Note

When an input zone is empty or when the two input zones do not overlap then there is no common area on which the algorithm could operate. In this case the present method returns false.

6.9.3.5 show()

```
void GEOM_FADE25D::CutAndFill::show (
        Visualizer2 * pVis ) const
```

For a quick overview a postscript visualization can be created.




Figure 10 Cut&Fill-Result: YELLOW area CUT, CYAN area: FILL

6.9.3.6 subscribe()

```
void GEOM_FADE25D::CutAndFill::subscribe (
        MsgType msgType,
        MsgBase * pMsg )
```

A user defined message receiver object (for example your own progress-bar class) can be registered to get progress updates. This step is optional.

Parameters

msgType	is the message type. For progress information the type is always MSG_PROGRESS
pMsg	is a user defined progress bar which derives from Fade's MsgBase.

6.9.3.7 unsubscribe()

```
void GEOM_FADE25D::CutAndFill::unsubscribe (
        MsgType msgType,
        MsgBase * pMsg )
```

Parameters

msgType	is the message type. For progress information the type is always MSG_PROGRESS
pMsg	is a user defined class which derives from Fade's MsgBase

The documentation for this class was generated from the following file:

- CutAndFill.h

6.10 GEOM_FADE25D::Edge2 Class Reference

Edge2 is a directed edge.

`#include <Edge2.h>`

Public Member Functions

- **Edge2** (const Edge2 &e_)
- Edge2 (Triangle2 *pT, int oppIdx_)

  Constructor.
- int getIndex () const
- double getLength25D () const
- double getLength2D () const
- void getPoints (Point2 *&p1, Point2 *&p2) const

  Get the endpoints.
- Point2 * getSrc () const

  Get the source point.
- Point2 * getTrg () const

  Get the target point.
- Triangle2 * getTriangle () const
- void getTriangles (Triangle2 *&pT0, Triangle2 *&pT1, int &idx0, int &idx1) const
- bool operator!= (const Edge2 &e) const

  operator!=()
- bool operator< (const Edge2 &e) const

  operator<()
- Edge2 & **operator=** (const Edge2 &other)
- bool operator== (const Edge2 &e) const

  operator==()

Protected Attributes

- int **oppIdx**
- Triangle2 * **pT**

Friends

- std::ostream & **operator**<< (std::ostream &stream, const Edge2 &e)

6.10.1 Constructor & Destructor Documentation

6.10.1.1 Edge2() `GEOM_FADE25D::Edge2::Edge2 (`

```
Triangle2 * pT,
int oppIdx_ )
```

Parameters

pT	is the triangle from which the edge is constructed
*oppIdx_*	is intra-triangle-index of the opposite vertex (of the edge) in pT

The orientation of the constructed Edge2 is counterclockwise (CCW) with respect to `pT`. Example: Edge2(pT,0) creates an edge from pT->getCorner(1) to pT->getCorner(2).

6.10.2 Member Function Documentation

6.10.2.1 getIndex() `int GEOM_FADE25D::Edge2::getIndex ( ) const`

Get the opposite index

Returns

the intra-triangle-index of the opposite vertex

6.10.2.2 getLength25D() `double GEOM_FADE25D::Edge2::getLength25D ( ) const`

Get the 2.5D length

Returns

the 2.5D length of the edge

6.10.2.3 getLength2D() `double GEOM_FADE25D::Edge2::getLength2D ( ) const`

Get the 2D length

Returns

the 2D length of the edge, the z-coordinate is ignored

6.10.2.4 getPoints() `void GEOM_FADE25D::Edge2::getPoints (`

```
Point2 *& p1,
Point2 *& p2 ) const
```

returns the source point of the edge as `p1` and the target point as `p2`

6.10.2.5 getSrc() `Point2* GEOM_FADE25D::Edge2::getSrc ( ) const`

Returns

the source point of the edge, i.e. pT->getCorner((oppIdx+1)%3)

6.10.2.6 getTrg() `Point2* GEOM_FADE25D::Edge2::getTrg ( ) const`

Returns

the target point of the edge, i.e. pT->getCorner((oppIdx+2)%3)

6.10.2.7 getTriangle() `Triangle2* GEOM_FADE25D::Edge2::getTriangle ( ) const`

Get the triangle

Returns

the triangle whose directed edge the present edge is

6.10.2.8 getTriangles()

```
void GEOM_FADE25D::Edge2::getTriangles (
        Triangle2 *& pT0,
        Triangle2 *& pT1,
        int & idx0,
        int & idx1 ) const
```

Get the triangles

Returns

the two adjacent triangles of the present edge along with their intra-triangle-indices

Parameters

pT0	is used to return the triangle whose directed edge the present edge is
idx0	is the opposite intra-triangle-index in pT0 of the present edge
pT1	is the other adjacent triangle at the present edge (or NULL)
idx1	is the intra-triangle index of the present edge in pT1 (or -1)

6.10.2.9 operator"!=()

```
bool GEOM_FADE25D::Edge2::operator!= (
        const Edge2 & e ) const  [inline]
```

operator!=() returns true if the compared edges are different. Be aware that edges are directed and therefore two adjacent triangles do not share the same Edge2.

6.10.2.10 operator<()

```
bool GEOM_FADE25D::Edge2::operator< (
        const Edge2 & e ) const  [inline]
```

operator<() does NOT compare edge lengths but the associated triangle pointers and intra-triangle indices. This is useful when edges are used in STL containers.

6.10.2.11 operator==()

```
bool GEOM_FADE25D::Edge2::operator== (
        const Edge2 & e ) const  [inline]
```

operator==() compares oriented edges, i.e., it returns only true when the two edges have been made from the same triangle and the same intra-triangle-index i.e., an edge with two adjacent triangles has two Edge2 objects, one in each direction.

The documentation for this class was generated from the following file:

- Edge2.h

6.11 GEOM_FADE25D::EfficientModel Class Reference

EfficientModel (DEPRECATED in favor of the new CloudPrepare class)

`#include <EfficientModel.h>`

Public Member Functions

- **EfficientModel** (const std::vector< Point2 > &vPoints)
- void extract (double maxError, std::vector< Point2 > &vEfficientPointsOut)

  Extract a subset of points.
- void zSmoothing (int numIterations, double maxDifferencePerIteration, SmoothingStrategy sms)

  Smoothing.

Protected Member Functions

- void **go** ()
- int **insertKeepError** (double factor, double err, std::vector< Point2 * > &vIn, std::vector< Point2 * > &v↩ NeedlessBigError, std::vector< Point2 * > &vNeedlessSmallError)
- void **insertMinHull** ()
- void **part1_extractFC** ()
- void **part2_setWeights** ()
- void **show** (const char *name)
- void **solveCand** (Candidate *pCand, double maxErr)
- void **sortVtx** (std::vector< Point2 * > &vVtx)

6.11.1 Detailed Description

Note

This class is deprecated but is kept for backward compatibility with existing software. Please use the new CloudPrepare class which is much faster and also more memory efficient.

6.11.2 Member Function Documentation

6.11.2.1 extract()

```
void GEOM_FADE25D::EfficientModel::extract (
        double maxError,
        std::vector< Point2 > & vEfficientPointsOut )
```

This method extracts a subset of the original point cloud that represents the model more efficiently. Thereby the original and the simplified model cover the same area.

Parameters

	maxError	is the maximum height difference between the original points and the simplified model.
out	*vEfficientPointsOut*	is used to return a subset of the original points that represents the model more efficiently.

Note

When `maxError` is tiny i.e., below the noise level of the point cloud, then processing can take quite some time. Consider using the zSmoothing() method before.

6.11.2.2 zSmoothing()

```
void GEOM_FADE25D::EfficientModel::zSmoothing (
        int numIterations,
        double maxDifferencePerIteration,
        SmoothingStrategy sms )
```

This method should be used before extract(). It adapts the z-values according to the chosen SmoothingStrategy `sms`.

Parameters

numIterations	Number of iterations
maxDifferencePerIteration	is the maximum change of any z-value
sms	is one of SMST_MINIMUM, SMST_MAXIMUM, SMST_MEDIAN, SMST_AVERAGE

The documentation for this class was generated from the following file:

- EfficientModel.h

6.12 GEOM_FADE25D::Fade_2D Class Reference

Fade_2D is the Delaunay triangulation class.
`#include <Fade_2D.h>`

Public Member Functions

- Fade_2D (Fade_2D &other, std::vector< Zone2 * > vZoneIn=std::vector< Zone2 * >(), std::vector< Zone2 * > vZoneOut=std::vector< Zone2 * >())

  Copy constructor, copy also zones.
- Fade_2D (unsigned numExpectedVertices=3)

  Constructor of the triangulation class.
- ~Fade_2D ()

  Destructor.
- void applyConstraintsAndZones ()

  Apply conforming constraints and zones (deprecated!)
- bool checkValidity (bool bCheckEmptyCircleProperty, const char *msg) const

  Checks if a triangulation is valid.
- Bbox2 computeBoundingBox () const

  Compute the axis-aligned bounding box of the points.
- ConstraintGraph2 * createConstraint (std::vector< Segment2 > &vSegments, ConstraintInsertionStrategy cis, bool bOrientedSegments=false, bool bUseHeightOfLatest=false)

  Add constraint edges (edges, polyline, polygon) .
- Zone2 * createZone (const std::vector< ConstraintGraph2 * > &vConstraintGraphs, ZoneLocation zoneLoc, const Point2 &startPoint, bool bVerbose=true)

  Create a zone limited by multiple ConstraintGraph2 objects by growing from a start point.
- Zone2 * createZone (ConstraintGraph2 *pConstraintGraph, ZoneLocation zoneLoc, bool bVerbose=true)

  Create a zone.
- Zone2 * createZone (ConstraintGraph2 *pConstraintGraph, ZoneLocation zoneLoc, const Point2 &startPoint, bool bVerbose=true)

  Create a zone limited by a ConstraintGraph by growing from a start point.
- Zone2 * createZone (std::vector< Triangle2 * > &vTriangles, bool bVerbose=true)

  Create a zone defined by a vector of triangles.
- Zone2 * createZone_cookieCutter (std::vector< Segment2 > &vSegments, bool bProtectEdges, ConstraintGraph2 *&pProtectedEdgesCG, ConstraintGraph2 *&pBoundaryCG)

  Cookie Cutter The Cookie Cutter cuts out a part of a triangulation and returns it as a Zone2 object.
- void cutTriangles (const Point2 &knifeStart, const Point2 &knifeEnd, bool bTurnEdgesIntoConstraints)

  Cut through a triangulation.
- void cutTriangles (std::vector< Segment2 > &vSegments, bool bTurnEdgesIntoConstraints)

  Cut through a triangulation.
- void deleteZone (Zone2 *pZone)

  Delete a Zone2 object.
- bool drape (std::vector< Segment2 > &vSegmentsIn, std::vector< Segment2 > &vSegmentsOut, double zTolerance, double offTolerance=0.0) const

Drape segments along a surface.

- void exportTriangulation (FadeExport &fadeExport, bool bWithCustomIndices, bool bClear)

  Export triangulation data from Fade.

- Triangle2 * getAdjacentTriangle (Point2 *p0, Point2 *p1) const

  Get adjacent triangle.

- void getAliveAndDeadConstraintSegments (std::vector< ConstraintSegment2 * > &vAllConstraintSegments) const

  Get all (alive and dead) constraint segments.

- void getAliveConstraintSegments (std::vector< ConstraintSegment2 * > &vAliveConstraintSegments) const

  Get active (alive) constraint segments.

- ConstraintSegment2 * getConstraintSegment (Point2 *p0, Point2 *p1) const

  Retrieve a ConstraintSegment2.

- void getConvexHull (bool bAllVertices, std::vector< Point2 * > &vConvexHullPointsOut)

  Compute the convex hull.

- void getDirectedEdges (std::vector< Edge2 > &vDirectedEdgesOut) const

  Get directed edges Edges are counterclockwise oriented around their triangle. The present method returns directed edges. That means each edge(a,b) is returend twice, as edge(a,b) and as edge(b,a).

- bool getHeight (double x, double y, double &heightOut, Triangle2 *pApproxT=NULL, double tolerance=0) const

  Compute the height of a certain point.

- void getIncidentTriangles (Point2 *pVtx, std::vector< Triangle2 * > &vIncidentT) const

  Get incident triangles.

- void getIncidentVertices (Point2 *pVtx, std::vector< Point2 * > &vIncidentVertices) const

  Get incident vertices.

- Point2 * getNearestNeighbor (const Point2 &p)

  Get nearest neighbor.

- Orientation2 getOrientation (const Point2 &p0, const Point2 &p1, const Point2 &p2)

  Compute the orientation of 3 points.

- Zone2 * getPeeledZone (double angleThreshold, bool bAvoidSplit)

  Get a peeled zone The getPeeledZone() function returns a zone that includes all triangles of `dt` except for the almost vertical ones typically found at the boundary of a 2.5D triangulation. More precisely, this function iteratively identifies and removes boundary triangles whose normal vector encloses a larger angle with the vector (0,0,1) than `angleThreshold` degrees. If no triangles remain, the method returns NULL.

- void getTrianglePointers (std::vector< Triangle2 * > &vAllTriangles) const

  Get pointers to all triangles.

- void getUndirectedEdges (std::vector< Edge2 > &vUndirectedEdgesOut) const

  Get undirected edges.

- Point2 * getVertexPointer (const Point2 &p)

  Get pointer.

- void getVertexPointers (std::vector< Point2 * > &vAllPoints) const

  Get pointers to all vertices.

- Voronoi2 * getVoronoiDiagram ()

  Get the Voronoi diagram.

- bool hasArea () const

  Check if the triangulation contains triangles (which is the case if at least 3 non-collinear points exist in the triangulation.

- Zone2 * importTriangles (std::vector< Point2 > &vPoints, bool bReorientIfNeeded, bool bCreateExtendedBoundingBox)

  Import Triangles.

- Zone2 * importTriangles_robust (std::vector< Point2 > &vPoints)

  Import Triangles - Robust (Error-tolerant version)

- Zone2 * importTrianglesFromPly (const char *filename)

  *Import Triangles from *.PLY.*

- Zone2 * importTrianglesFromPly (std::istream &is)

  *Import Triangles from *.PLY.*
- void insert (CloudPrepare *pCloudPrepare, bool bClear=true)

  Insert points from a CloudPrepare object.
- Point2 * insert (const Point2 &p)

  Insert a single point.
- void insert (const std::vector< Point2 > &vInputPoints)

  Insert a vector of points.
- void insert (const std::vector< Point2 > &vInputPoints, std::vector< Point2 * > &vHandles)

  Insert points from a std::vector and store pointers in vHandles.
- void insert (int numPoints, double *aCoordinates, Point2 **aHandles)

  Insert points from an array.
- bool isConstraint (Point2 *p0, Point2 *p1) const

  Check if an edge is a constraint edge.
- bool isConstraint (Point2 *pVtx) const

  Check if a vertex is a constraint vertex.
- bool isConstraint (Triangle2 *pT, int ith) const

  Check if an edge is a constraint edge.
- bool load (const char *filename, std::vector< Zone2 * > &vZones)

  Load a triangulation.
- bool load (std::istream &stream, std::vector< Zone2 * > &vZones)

  Load a triangulation.
- Triangle2 * locate (const Point2 &p)

  Locate a triangle which contains p.
- double measureTriangulationTime (const std::vector< Point2 > &vPoints)

  Measure the Delaunay triangulation time.
- size_t numberOfPoints () const

  Number of points.
- size_t numberOfTriangles () const

  Number of triangles.
- void printLicense () const

  Prints license information.
- void refine (Zone2 *pZone, double minAngleDegree, double minEdgeLength, double maxEdgeLength, bool bAllowConstraintSplitting)

  Delaunay refinement.
- void refineAdvanced (MeshGenParams *pParameters)

  Delaunay refinement and grid meshing.
- void remove (Point2 *pVertex)

  Remove a single vertex.
- void remove (std::vector< Point2 * > &vPoints)

  Remove vertices.
- void reset ()

  Reset.
- bool saveTriangulation (const char *filename, std::vector< Zone2 * > &vSaveZones)

  Save a triangulation.
- bool saveTriangulation (std::ostream &stream, std::vector< Zone2 * > &vSaveZones)

  Save a triangulation.
- bool saveZones (const char *filename, std::vector< Zone2 * > &vSaveZones)

  Save zones.
- bool saveZones (std::ostream &stream, std::vector< Zone2 * > &vSaveZones)

  Save zones.

- void setFastMode (bool bFast)

  Set fast mode.
- int setNumCPU (int numCPU)

  Set the number CPU cores for multithreading (deprecated)
- void show (const char *postscriptFilename, bool bWithConstraints=true) const

  Draws the triangulation as postscript file.
- void show (Visualizer2 *pVis, bool bWithConstraints=true) const

  Draws the triangulation as postscript file using an existing Visualizer2 object.
- void showGeomview (const char *filename, const char *color="1 1 1 0.5") const

  Draws the triangulation in 3D.
- void showGeomview (Visualizer3 *pVis, const char *color="1 1 1 0.5") const

  Draws the triangulation in 3D.
- void statistics (const char *s) const

  Statistics.
- void subscribe (MsgType msgType, MsgBase *pMsg)

  Register a message receiver.
- void unsubscribe (MsgType msgType, MsgBase *pMsg)

  Unregister a message receiver.
- void writeObj (const char *filename) const

  *Write the current triangulation to an *.obj file.*
- void writeObj (const char *filename, Zone2 *pZone) const

  *Write a zone to an *.obj file.*
- bool writePly (const char *filename, bool bASCII=false) const

  *Write the current triangulation to a *.ply file.*
- bool writePly (std::ostream &os, bool bASCII=false) const

  *Write the current triangulation to a *.ply file.*
- void writeWebScene (const char *path) const

  *Write the current triangulation to an *.obj file.*
- void writeWebScene (const char *path, Zone2 *pZone) const

  *Write a zone to an *.obj file.*

6.12.1 Detailed Description

Fade_2D represents a Delaunay triangulation in 2D or 2.5D (depends on the used namespace)

6.12.2 Constructor & Destructor Documentation

6.12.2.1 Fade_2D() `GEOM_FADE25D::Fade_2D::Fade_2D ( unsigned numExpectedVertices = 3 ) [explicit]`

Parameters

numExpectedVertices	specifies the number of points that will be inserted. This is a default parameter that does not need to be specified.

6.12.3 Member Function Documentation

6.12.3.1 applyConstraintsAndZones() `void GEOM_FADE25D::Fade_2D::applyConstraintsAndZones ( )`

This method establishes conforming constraint segments and zones which depend on them. For technical reasons conforming constraint segments are not immediately established but inserted at the end of the triangulation process. This step must be triggered manually i.e., it is up to the user to call applyConstraintsAndZones() before the resulting triangulation is used. If afterwards the triangulation is changed in any way, applyConstraintsAndZones() must be called again.

Note

The present function applyConstraintsAndZones() as well as the two constraint insertion strategies CIS↩ _CONFORMING_DELAUNAY and CIS_CONFORMING_DELAUNAY_SEGMENT_LEVEL are deprecated. These are only kept for backwards compatibilty. The replacement is CIS_CONSTRAINED_DELAUNAY along with the methods Fade_2D::drape() and/or ConstraintGraph2::makeDelaunay(). See the example code in examples_25D/terrain.cpp

6.12.3.2 checkValidity()

```
bool GEOM_FADE25D::Fade_2D::checkValidity (
    bool bCheckEmptyCircleProperty,
    const char * msg ) const
```

Checks the validity of the data structure.

Parameters

bCheckEmptyCircleProperty	specifies if (slow!) multiprecision arithmetic shall be used to recheck the empty circle property
msg	is a debug string that will be shown in terminal output so that you know which checkValidity call currently runs.

This method is thought for development purposes. Don't call it method unless you assume that something is wrong with the code.

6.12.3.3 computeBoundingBox()

```
Bbox2 GEOM_FADE25D::Fade_2D::computeBoundingBox ( ) const
```

If no points have been inserted yet, then the returned Bbox2 object is invalid and its member function *Bbox2::isValid()* returns false.

6.12.3.4 createConstraint()

```
ConstraintGraph2* GEOM_FADE25D::Fade_2D::createConstraint (
    std::vector< Segment2 > & vSegments,
    ConstraintInsertionStrategy cis,
    bool bOrientedSegments = false,
    bool bUseHeightOfLatest = false )
```

Parameters

vSegments	are segments which shall appear as edges of the triangulation. The segments may be automatically reordered and reoriented, see `bOrientedSegments` below.
cis	is the Constraint-Insertion-Strategy. Use always CIS_CONSTRAINED_DELAUNAY. This mode inserts the constraint segments at their original level (no projection onto the surface) and without subdivision unless existing vertices or existing constraint segments are crossed. When subdivision (e.g., to achieve better triangle shapes) is desired then use ConstraintGraph2::makeDelaunay() after insertion. When the segments shall be adapted to the elevation of the existing surface then use Fade_2D::drape(). See the example code in `examples_25D/terrain.cpp`
bOrientedSegments	specifies whether the segments in vSegments are oriented (*oriented, not ordered!*). If later a zone is to be made with the returned ConstraintGraph2 object this is only possible if the value is true (then it is assumed that all segments are counterclockwise oriented) or if the ConstraintGraph2 represents exactly one closed polygon. The value affects also the order of the returned vertices when later ConstraintGraph2::getPolygonVertices() is called. This is a default parameter and it defaults to false.

Parameters

bUseHeightOfLatest	specifies that the height z of the last inserted segment is to be used. This is used in conflict case only, e.g. if the endpoint of an inserted segment already exists with a different height, or if an existing constraint segment is cut. By default, the height of the existing elements is used for the intersection point.

Returns

a pointer to the new ConstraintGraph2 object




Figure 11 Delaunay triangulation without constraints




Figure 12 Constraint Delaunay triangulation




Figure 13 Conforming Delaunay triangulation through the ConstraintGraph::makeDelaunay() method

6.12.3.5 createZone() [1/4]

```
Zone2* GEOM_FADE25D::Fade_2D::createZone (
        const std::vector< ConstraintGraph2 * > & vConstraintGraphs,
        ZoneLocation zoneLoc,
        const Point2 & startPoint,
        bool bVerbose = true )
```

A Zone2 object is an area of the traingulation, see createZone

Parameters

vConstraintGraphs	is a vector of ConstraintGraph objects
zoneLoc	must be ZL_GROW
startPoint	is the point from which the area is grown until the borders specified in vConstraintGraphs are reached
bVerbose	is by default true and causes a warning if NULL is returned.

Returns

a pointer to the new Zone2 object (or NULL if zoneLoc!=ZL_GROW or no triangles exist)

6.12.3.6 createZone() [2/4]

```
Zone2* GEOM_FADE25D::Fade_2D::createZone (
        ConstraintGraph2 * pConstraintGraph,
        ZoneLocation zoneLoc,
        bool bVerbose = true )
```

A Zone2 object is an area of a triangulation, possibly bounded by a ConstraintGraph.

Parameters

zoneLoc	is ZL_INSIDE, ZL_OUTSIDE or ZL_GLOBAL.
pConstraintGraph	points to a formerly created ConstraintGraph2 object (which must be oriented and contain a *simple* polygon) or is NULL in case of zoneLoc==ZL_GLOBAL.
bVerbose	is by default true and causes a warning if NULL is returned.

Returns

a pointer to the new Zone2 object or NULL if no triangles exist or pConstraintGraph->isOriented() returns false.



Figure 14 Zones in a triangulation

6.12.3.7 createZone() [3/4]

```
Zone2* GEOM_FADE25D::Fade_2D::createZone (
        ConstraintGraph2 * pConstraintGraph,
        ZoneLocation zoneLoc,
        const Point2 & startPoint,
        bool bVerbose = true )
```

A Zone2 object is an area of the traingulation, see createZone

Parameters

pConstraintGraph	is a constraint whose edges specify the area's border

Parameters

zoneLoc	must be ZL_GROW
startPoint	is the point from which the area is grown until the borders specified in pConstraint are reached
bVerbose	is by default true and causes a warning if NULL is returned.

Returns

a pointer to the new Zone2 object (or NULL if zoneLoc!=ZL_GROW or no triangles exist)

6.12.3.8 createZone() [4/4]

```
Zone2* GEOM_FADE25D::Fade_2D::createZone (
        std::vector< Triangle2 * > & vTriangles,
        bool bVerbose = true )
```

A Zone2 object is an area of the traingulation, see createZone

Parameters

vTriangles	
bVerbose	is by default true and causes a warning if NULL is returned.

Returns

a pointer to the new Zone2 object (or NULL if vTriangles is empty)

6.12.3.9 createZone_cookieCutter()

```
Zone2* GEOM_FADE25D::Fade_2D::createZone_cookieCutter (
        std::vector< Segment2 > & vSegments,
        bool bProtectEdges,
        ConstraintGraph2 *& pProtectedEdgesCG,
        ConstraintGraph2 *& pBoundaryCG )
```

Parameters

in	*vSegments*	specifies the input polygon
in	*bProtectEdges*	specifies if existing edges shall be locked by turning them into constraint segments
out	*pProtectedEdgesCG*	is used to return the ConstraintGraph2* of edges that have been protected
out	*pBoundaryCG*	is used to return the ConstraintGraph2* of the boundary

Returns

a Zone2 object consisting of all triangles inside the polygon or NULL when the operation has failed due to unmet preconditions.

Properties: The input polygon (vSegments) is not required to have specific height values; the z-coordinates are calculated automatically. The input polygon must be simple, meaning it must not intersect itself, and each vertex must belong to exactly two segments. Alternatively, the polygon may self-intersect at vertices, but in that case, all segments must be oriented counterclockwise. The input polygon is automatically trimmed when it lies outside the convex hull of the triangulation. Inserting intersection points would normally cause existing edges in the triangulation to flip, but this can be avoided by setting bProtectEdges=true. In this case, certain edges of the triangulation will become constraint edges.

6.12.3.10 cutTriangles() [1/2]

```
void GEOM_FADE25D::Fade_2D::cutTriangles (
```

```
const Point2 & knifeStart,
const Point2 & knifeEnd,
bool bTurnEdgesIntoConstraints )
```

Parameters

knifeStart	is one point of the knife segment
knifeEnd	is the second point of the knife segment
bTurnEdgesIntoConstraints	turns all 3 edges of each intersected triangle into constraint segments.

This method inserts a constraint edge *knife*(*knifeStart*,*knifeEnd*). If existing edges *E* are intersected by *knife*, then *knife* is subdivided at the intersection points *P*.
In any case *knife* will exist (in a possibly subdivided form) in the result. But a consequence of the insertion of the points *P* is that the edges *E* and even edges which are not intersected by *knife* may be flipped. Use bTurnEdges↩ IntoConstraints=true to avoid that.

Note

The intersection point of two line segments may not be exactly representable in double precision floating point arithmetic and thus tiny rounding errors may occur. As a consequence two very close intersection points may be rounded to the same coordinates.

When more than one knife segment is inserted then the method void cutTriangles(std::vector<Segment2>& vSegments,bool bTu should be used. The reason is that each individual cut operation changes the triangulation and thus iterative calls to the present version of the method can lead to a different result.

6.12.3.11 cutTriangles() [2/2]

```
void GEOM_FADE25D::Fade_2D::cutTriangles (
std::vector< Segment2 > & vSegments,
bool bTurnEdgesIntoConstraints )
```

Parameters

vSegments	are the knife segments
bTurnEdgesIntoConstraints	specifies if intersected edges shall automatically be turned into constraints

Same method as void cutTriangles(const Point2& knifeStart,const Point2& knifeEnd,bool bTurnEdgesIntoConstraints) but it takes a vector of segments instead of a single segment. This is the recommended method to cut through a triangulation when more than one knife segment exists.

6.12.3.12 deleteZone()

```
void GEOM_FADE25D::Fade_2D::deleteZone (
Zone2 * pZone )
```

Zone2 objects are automatically destroyed with their Fade_2D objects. In addition this method provides the possibility to eliminate Zone2 objects earlier.

Note

Zones are designed transparently: When two zones Z1 and Z2 are combined to a new one Z3 (for example through a boolean operation) then Z1,Z2,Z3 form a tree such that changes in the leaf nodes Z1 and Z2 can propagate up to the root node Z3. For this reason Z1 and Z2 must be alive as long as Z3 is used.

6.12.3.13 drape()

```
bool GEOM_FADE25D::Fade_2D::drape (
std::vector< Segment2 > & vSegmentsIn,
std::vector< Segment2 > & vSegmentsOut,
```

```
        double zTolerance,
        double offTolerance = 0.0 ) const
```

Projects the segments from `vSegmentsIn` onto the triangulation. Thereby the segments are subdivided where they intersect edges of the triangulation. Segment parts outside the triangulation are cut off and ignored. Degenerate input segments are also ignored.
The heights (z-values) of the result segments are adapted to the surface.

Parameters

in	*zTolerance*	is used to avoid excessive subdivision of segments. Use some positive value to define the acceptable geometric error or use `zTolerance=-1.0` to split the segments at all intersections with triangulation-edges.
in	*vSegmentsIn*	Input segments
out	*vSegmentsOut*	Output segments
in	*offTolerance*	is used to prevent truncation of segments that are slightly outside the convex hull which might be the case if your input segments are subject to tiny rounding errors.

Returns

TRUE if all input segments are inside the convex hull of the triangulation. Otherwise FALSE is returned and the result is still valid but it contains only the segment parts inside the convex hull.

Note

The tiny rounding errors that occur when segment intersections are computed are largely theoretical. But be aware that subdivided segments are not always perfectly collinear. This can't be avoided because the exact split point is sometimes not even representable using floating point coordinates.




Figure 15 Drape: Input segments (blue) are draped (red) onto a TIN. Left with tolerance 1.0, right without tolerance

-

Note

Draping segments onto a TIN does not insert them. Use Fade_2D::createConstraint() for that purpose.

6.12.3.14 exportTriangulation()

```
void GEOM_FADE25D::Fade_2D::exportTriangulation (
        FadeExport & fadeExport,
        bool bWithCustomIndices,
        bool bClear )
```

Parameters

fadeExport	is a struct that will hold the requested triangulation data
bWithCustomIndices	determines whether the custom indices of the points are also stored
bClear	determines whether the Fade instance is cleared **during** the export operation to save memory

Note

When bClear is true then all memory of the Fade object is deleted i.e., all existing pointers to its objects become invalid.

6.12.3.15 getAdjacentTriangle()

```
Triangle2* GEOM_FADE25D::Fade_2D::getAdjacentTriangle (
    Point2 * p0,
    Point2 * p1 ) const
```

Returns

the triangle that has the edge (p0,p1) or NULL if no such edge is present

Note

Recall the counter-clockwise enumeration of vertices in a triangle. If (p0,p1) is used, the unique triangle with the CCW oriented edge (p0,p1) is returned, using (p1,p0) one gets the other adjacent triangle.

6.12.3.16 getConstraintSegment()

```
ConstraintSegment2* GEOM_FADE25D::Fade_2D::getConstraint↩
Segment (
    Point2 * p0,
    Point2 * p1 ) const
```

Returns

a pointer to the ConstraintSegment2 between p0 and p1 or NULL if the segment is not a constraint edge (or dead because it has been splitted)

6.12.3.17 getConvexHull()

```
void GEOM_FADE25D::Fade_2D::getConvexHull (
    bool bAllVertices,
    std::vector< Point2 * > & vConvexHullPointsOut )
```

Parameters

	bAllVertices	determines if all convex hull points are returned or if collinear ones shall be removed.
out	*vConvexHullPointsOut*	is used to return the convex hull vertices in counterclockwise order. The start vertex is the leftmost vertex. If more than one leftmost vertex exists, the bottommost of them is the start vertex.

6.12.3.18 getHeight()

```
bool GEOM_FADE25D::Fade_2D::getHeight (
    double x,
    double y,
    double & heightOut,
    Triangle2 * pApproxT = NULL,
    double tolerance = 0 ) const
```

Computes the height (z) at the coordinates x and y, assigns it to heightOut and returns true if successful.

Parameters

in	*x,y*	are the input coordinates
out	*heightOut*	is the computed height

Parameters

in	*pApproxT*	can be set to a nearby triangle. If unknown, use NULL.
in	*tolerance*	is by default 0, see below

Note

pApproxT is an optional parameter to speed up the search in case that you know a nearby triangle. But point location if very fast anyway and if you are not sure, using NULL is probably faster.

Due to rounding errors your query point may lie slightly outside the convex hull of the triangulation and in such a case the present method would correctly return false. But you can use the optional `tolerance` parameter (default: 0): If your query point is not farther outside the convex hull than `tolerance` then the height of the closest point of the convex hull is returned.

6.12.3.19 getIncidentTriangles()

```
void GEOM_FADE25D::Fade_2D::getIncidentTriangles (
    Point2 * pVtx,
    std::vector< Triangle2 * > & vIncidentT ) const
```

Stores pointers to all triangles around pVtx into vIncidentT

6.12.3.20 getIncidentVertices()

```
void GEOM_FADE25D::Fade_2D::getIncidentVertices (
    Point2 * pVtx,
    std::vector< Point2 * > & vIncidentVertices ) const
```

Stores pointers to all vertices around pVtx into vIncidentVertices

6.12.3.21 getNearestNeighbor()

```
Point2* GEOM_FADE25D::Fade_2D::getNearestNeighbor (
    const Point2 & p )
```

This method returns the closest vertex of `p`.

Parameters

in	*p*	is the query point

Returns

a pointer to the closest vertex

6.12.3.22 getOrientation()

```
Orientation2 GEOM_FADE25D::Fade_2D::getOrientation (
    const Point2 & p0,
    const Point2 & p1,
    const Point2 & p2 )
```

Returns

ORIENTATION2_COLLINEAR, ORIENTATION2_CW (clockwise) or ORENTATION2_CCW (counterclockwise)

6.12.3.23 getPeeledZone()

```
Zone2* GEOM_FADE25D::Fade_2D::getPeeledZone (
    double angleThreshold,
    bool bAvoidSplit )
```

Parameters

in	*angleThreshold*	is the maximum angle between the normal vector of any kept triangle and the vector (0,0,1). Use for example 89.9 degrees.
in	*bAvoidSplit*	prevents the zone from breaking apart i.e., if bAvoidSplit=true and removing a triangle would split the zone in two independent connected components then the triangle is not removed.

Returns

the peeled Zone2* or NULL if no triangles remain.

See also

Zone2::peelOffIf()

6.12.3.24 getTrianglePointers()

```
void GEOM_FADE25D::Fade_2D::getTrianglePointers (
    std::vector< Triangle2 * > & vAllTriangles ) const
```

This command fetches the existing triangles

Parameters

out	*vAllTriangles*	is used to return the triangles

Note

that the lifetime of data from the Fade2D datastructures does exceed the lifetime of the Fade2D object.

6.12.3.25 getUndirectedEdges()

```
void GEOM_FADE25D::Fade_2D::getUndirectedEdges (
    std::vector< Edge2 > & vUndirectedEdgesOut ) const
```

Parameters

vUndirectedEdgesOut	is used to return a unique set of undirected edges.

6.12.3.26 getVertexPointer()

```
Point2* GEOM_FADE25D::Fade_2D::getVertexPointer (
    const Point2 & p )
```

Parameters

p	is the query point

Returns

the vertex pointer of or NULL if is not a vertex of the triangulation

6.12.3.27 getVertexPointers()

```
void GEOM_FADE25D::Fade_2D::getVertexPointers (
    std::vector< Point2 * > & vAllPoints ) const
```

Parameters

vAllPoints	is an empty vector of Point2 pointers.

Stores pointers to all vertices of the triangulation in vAllPoints. The order in which the points are stored is *not* necessarily the insertion order. For geometrically identical points which have been inserted multiple times, only one pointer exists. Thus vAllPoints.size() can be smaller than the number of inserted points.

6.12.3.28 getVoronoiDiagram() `Voronoi2* GEOM_FADE25D::Fade_2D::getVoronoiDiagram ( )`

Returns

a dual Voronoi diagram that changes dynamically when the triangulation changes.

6.12.3.29 hasArea() `bool GEOM_FADE25D::Fade_2D::hasArea ( ) const`

As long as all inserted points are collinear the triangulation does not contain triangles. This is clearly the case as long as less than three input points are present but it may also be the case when 3 or more points have been inserted when all these points are collinear. These points are then in a pending state, i.e. they will be triangulated as soon as the first non-collinear point is inserted.




Figure 16 Triangles are generated as soon as the first non-collinear point is inserted.

Returns

true if at least one triangle exists
false otherwise

6.12.3.30 importTriangles() `Zone2* GEOM_FADE25D::Fade_2D::importTriangles (`

```
std::vector< Point2 > & vPoints,
bool bReorientIfNeeded,
bool bCreateExtendedBoundingBox )
```

This method imports triangles into an empty Fade object.

Warning

Using this older version of the method is only recommended if you definitely know that your input triangulation is 100% correct. If there is any chance that the input points have been rounded (e.g., due to conversion from 64 to 32 bit precision or simply because they have been parsed from an ASCII file), then please use the robust version importTriangles_robust() instead.

Parameters

vPoints	Contains the input triangulation (3 subsequent points per triangle).
bReorientIfNeeded	specifies whether the orientations of the point triples shall be checked and corrected. If you know that the point triples are certainly oriented in counterclockwise order, then the orientation test can be skipped.
bCreateExtendedBoundingBox	can be used to insert the 4 corners of an extended bounding box as dummy points. This is convenient in some cases. Use false if you are unsure.

Returns

a pointer to a Zone2 object or NULL if the input data is invalid.

6.12.3.31 importTriangles_robust()

```
Zone2* GEOM_FADE25D::Fade_2D::importTriangles_robust (
    std::vector< Point2 > & vPoints )
```

This method imports triangles into an empty Fade object. In contrast to the classic importTriangles() method, this robust version works also in presence of errors in the input data, and corrects overlapping triangles automatically. This robust version is very fast, and due to the additional checks, it is also very safe. Thus, it is highly recommended to use it always rather than the classic importTriangles() method.

Parameters

vPoints	contains the input triangulation (3 subsequent points per triangle).

Returns

a pointer to a Zone2 object or NULL if the input data is invalid.

Note

A Delaunay triangulation is always **convex**, and thus additional fill-triangles are created, if necessary, to complete the convex hull. Consequently, when you later call Fade_2D::getTrianglePointers(), you will also receive the **additional triangles**. If you are only interested in the triangles that you have imported, use the Zone2* returned by the present command, and call Zone2::getTriangles() instead.

6.12.3.32 importTrianglesFromPly() [1/2]

```
Zone2* GEOM_FADE25D::Fade_2D::importTrianglesFromPly (
    const char * filename )
```

This method imports triangles from a *.PLY file into an empty Fade object. This method is robust i.e., it works also in presence of errors in the input data, and corrects overlapping triangles automatically.

Parameters

filename	contains the input *.PLY file (ASCII or binary)

Returns

a pointer to a Zone2 object or NULL if the input data is invalid.

Note

Method available for platforms with C++11

6.12.3.33 importTrianglesFromPly() [2/2]

```
Zone2* GEOM_FADE25D::Fade_2D::importTrianglesFromPly (
    std::istream & is )
```

This method imports triangles from a *.PLY file into an empty Fade object. This method is robust i.e., it works also in presence of errors in the input data, and corrects overlapping triangles automatically.

Parameters

is	is the input *.PLY file (ASCII or binary)

Returns

a pointer to a Zone2 object or NULL if the input data is invalid.

Note

Method available for platforms with C++11

6.12.3.34 insert() [1/5]

```
void GEOM_FADE25D::Fade_2D::insert (
    CloudPrepare * pCloudPrepare,
    bool bClear = true )
```

Parameters

in	*pCloudPrepare*	is a CloudPrepare object that contains a point cloud
in	*bClear*	determines whether pCloudPrepare shall be cleared during the operation in order to save memory. Always use bClear=true unless you plan to use pCloudPrepare also for other triangulations.

Note

There's a difference in peak memory conversion compared to the other insert() methods: You can pre-give the vertices to the CloudPrepare object and delete them from your own software's data structures while not a single triangle has been created yet. Only after that you call this insert() function with the CloudPrepare object and the vertices are triangulated.

6.12.3.35 insert() [2/5]

```
Point2* GEOM_FADE25D::Fade_2D::insert (
    const Point2 & p )
```

Parameters

p	is the point to be inserted.

Returns

a pointer to the point in the triangulation

The triangulation keeps a copy of *p*. The return value is a pointer to this copy. If duplicate points are inserted, the triangulation does not create new copies but returns a pointer to the copy of the very first insertion.

Note

This method offers a very good performance but it is still faster if all points are passed at once, if possible.

6.12.3.36 insert() [3/5]

```
void GEOM_FADE25D::Fade_2D::insert (
    const std::vector< Point2 > & vInputPoints )
```

Parameters

vInputPoints	contains the points to be inserted.

Note

Use Fade_2D::setNumCPU() to activate multithreading

6.12.3.37 insert() [4/5]

```
void GEOM_FADE25D::Fade_2D::insert (
    const std::vector< Point2 > & vInputPoints,
    std::vector< Point2 * > & vHandles )
```

Parameters

vInputPoints	contains the points to be inserted.
vHandles	(empty) is used by Fade to return Point2 pointers

Internally, the triangulation keeps copies of the inserted points which are returned in *vHandles* (in the same order). If duplicate points are contained in vInputPoints then only one copy will be made and a pointer to this unique copy will be stored in vHandles for every occurance.

Note

Use Fade_2D::setNumCPU() to activate multithreading

6.12.3.38 insert() [5/5]

```
void GEOM_FADE25D::Fade_2D::insert (
    int numPoints,
    double * aCoordinates,
    Point2 ** aHandles )
```

Parameters

numPoints	is the number of points to be inserted
aCoordinates	is an array of *3n* double values, e.g. {x0,y0,z0,x1,y1,z1,...,xn,yn,zn}
aHandles	is an array with size *n* where pointers to the inserted points will be stored

Note

Use Fade_2D::setNumCPU() to activate multithreading

6.12.3.39 isConstraint() [1/3]

```
bool GEOM_FADE25D::Fade_2D::isConstraint (
    Point2 * p0,
    Point2 * p1 ) const
```

Returns whether the edge (p0,p1) is a constraint edge.

6.12.3.40 isConstraint() [2/3]

```
bool GEOM_FADE25D::Fade_2D::isConstraint (
    Point2 * pVtx ) const
```

Returns whether the vertex `pVtx` belongs to a constraint edge.

6.12.3.41 isConstraint() [3/3]

```
bool GEOM_FADE25D::Fade_2D::isConstraint (
    Triangle2 * pT,
    int ith ) const
```

Returns whether the edge in triangle *pT* which is opposite to the *ith* vertex is a constraint edge.

6.12.3.42 load() [1/2]

```
bool GEOM_FADE25D::Fade_2D::load (
    const char * filename,
    std::vector< Zone2 * > & vZones )
```

Loads a triangulation together with any custom indices, constraint-edges and zones from a binary file

Parameters

in	*filename*	is the name of the input file
out	*vZones*	is used to return Zone2∗ pointers if any. The order of the pointers is the same as at the time of storage

Returns

whether the operation was successful

6.12.3.43 load() [2/2]

```
bool GEOM_FADE25D::Fade_2D::load (
    std::istream & stream,
    std::vector< Zone2 * > & vZones )
```

Loads a triangulation together with any custom indices, constraint-edges and zones from a stream

Parameters

	stream	is an input stream
out	*vZones*	is used to return Zone2∗ pointers if any. The order of the pointers is the same as at the time of storage

Returns

whether the operation was successful

6.12.3.44 locate()

```
Triangle2* GEOM_FADE25D::Fade_2D::locate (
    const Point2 & p )
```




Figure 17 Point location

The Fade_2D class can be used as a data structure for point location. This method returns a pointer to a triangle which contains *p*.

Parameters

in	*p*	is the query point

Returns

a pointer to a Triangle2 object (or NULL if hasArea()==false or if *p* is outside the triangulation)

6.12.3.45 measureTriangulationTime()

```
double GEOM_FADE25D::Fade_2D::measureTriangulationTime (
    const std::vector< Point2 > & vPoints )
```

This method evaluates the performance of single- and multithreaded point insertion into a Delaunay triangulation.

Parameters

in	*vPoints*	are the points to be inserted

Returns

the total wall-time for point insertion in seconds

Note

The method cleans up the triangulation (objects, memory) on exit. Thus the time measured outside this method may be slightly larger than the returned time that is exactly the time needed to triangulate the input points.

Use Fade_2D::setNumCPU() to activate multithreading

6.12.3.46 numberOfPoints()

```
size_t GEOM_FADE25D::Fade_2D::numberOfPoints ( ) const
```

Returns

the number of points in the triangulation

Note

Due to possibly duplicate input points the number of points is not stored somewhere but freshly computed in O(n) time. This is fast but you are adviced to avoid calling this method over-frequently in a loop. Duplicate point insertions count only once.

6.12.3.47 numberOfTriangles()

```
size_t GEOM_FADE25D::Fade_2D::numberOfTriangles ( ) const
```

Returns

the number of triangles in the triangulation (or 0 as long as hasArea() is false).

6.12.3.48 refine()

```
void GEOM_FADE25D::Fade_2D::refine (
    Zone2 * pZone,
    double minAngleDegree,
    double minEdgeLength,
    double maxEdgeLength,
    bool bAllowConstraintSplitting )
```

Creates a mesh inside the area given by a Zone2 object.

Parameters

pZone	is the zone whose triangles are refined. Allowed zoneLocation values are ZL_INSIDE and ZL_BOUNDED.

Parameters

minAngleDegree	(up to 30) is the minimum interior triangle angle
minEdgeLength	is a lower threshold on the edge length. Triangles with smaller edges are not refined.
maxEdgeLength	is an upper threshold on the edge length. Triangles with larger edges are always refined.
bAllowConstraintSplitting	specifies if constraint edges may be splitted

Note

The behavior of the present method had to be changed in Fade v1.39: Only ZL_INSIDE and ZL_↩ BOUNDED zones are accepted. But you can easily convert other types of zones to ZL_BOUNDED using Zone2::convertToBoundedZone().

6.12.3.49 refineAdvanced() `void GEOM_FADE25D::Fade_2D::refineAdvanced (`

`MeshGenParams * pParameters )`

This method calls an advanced Delaunay mesh generator and grid mesher. The parameters are encapsulated in the MeshGenParams class. This class provides default parameters that can be used as is. Alternatively client code can derive from MeshGenParams and overwrite the methods and parameters to gain full control over the mesh generation process.

6.12.3.50 remove() [1/2] `void GEOM_FADE25D::Fade_2D::remove (`

`Point2 * pVertex )`

Parameters

pVertex	shall be removed.

Note

`pVertex` must not be a vertex of a ConstraintGraph2 or ConstraintSegment2 object. If this is the case, the vertex is not removed and a warning is issued.

6.12.3.51 remove() [2/2] `void GEOM_FADE25D::Fade_2D::remove (`

`std::vector< Point2 * > & vPoints )`

Parameters

vPoints	are the points to be removed

Note

`vPoints` must not be vertices of any ConstraintGraph2 or ConstraintSegment2 object. In this case the vertex is not removed.

6.12.3.52 reset() `void GEOM_FADE25D::Fade_2D::reset ( )`

Resets the triangulation and makes it re-usable.

6.12.3.53 saveTriangulation() [1/2]

```
bool GEOM_FADE25D::Fade_2D::saveTriangulation (
    const char * filename,
    std::vector< Zone2 * > & vSaveZones )
```

The saveTriangulation() command saves all triangles of the present triangulation to a binary file. Thereby it retains constraint edges and custom vertex indices, if any. If Zone2∗ pointers are specified, these zones will be saved also and their order will be retained.

Parameters

in	*filename*	is the name of the output file
in	*vSaveZones*	is used specify zones that shall additionally be saved

See also

If you just want to store zones, use Zone2::save() or Fade_2D::saveTriangulation(). Use Fade_2D::load() to reload data from such files.

Returns

whether the operation was successful

6.12.3.54 saveTriangulation() [2/2]

```
bool GEOM_FADE25D::Fade_2D::saveTriangulation (
    std::ostream & stream,
    std::vector< Zone2 * > & vSaveZones )
```

The saveTriangulation() command saves all triangles of the present triangulation to a stream. Thereby it retains constraint edges and custom vertex indices, if any. If Zone2∗ pointers are specified, these zones will be saved also and their order will be retained.

Parameters

	stream	is the output stream
out	*vSaveZones*	is used specify zones that shall additionally be saved

See also

If you just want to store zones, use Zone2::save() or Fade_2D::saveTriangulation(). Use Fade_2D::load() to reload data from such files.

Returns

whether the operation was successful

6.12.3.55 saveZones() [1/2]

```
bool GEOM_FADE25D::Fade_2D::saveZones (
    const char * filename,
    std::vector< Zone2 * > & vSaveZones )
```

The saveZones() command saves the triangles of the zones in `vSaveZones` to a binary file. Thereby it keeps the order of the zones and it retains any constraint edges and custom indices in the domain.

Note

A Delaunay triangulation is convex without holes and this may not hold for the zones to be saved. Thus extra triangles may be saved to fill concavities. These extra-triangles will belong to the Fade_2D instance but not to any Zone2 when reloaded later.

Parameters

in	*filename*	is the name of the output file
out	*vSaveZones*	(non-empty) specifies the zones to be saved

Returns

whether the operation was successful

See also

The saveTriangulation() command can be used to store all triangles of a triangulation plus any specified zones. The Zone2::save() command is used to store just one zone. Use Fade_2D::load() to reload data from such files.

6.12.3.56 saveZones() [2/2]

```
bool GEOM_FADE25D::Fade_2D::saveZones (
    std::ostream & stream,
    std::vector< Zone2 * > & vSaveZones )
```

The saveZones() command saves the triangles of the zones in `vSaveZones` to stream. Thereby it keeps the order of the zones and it retains any constraint edges and custom indices in the domain.

Note

A Delaunay triangulation is convex without holes and this may not hold for the zones to be saved. Thus extra triangles may be saved to fill concavities. These extra-triangles will belong to the Fade_2D instance but not to any Zone2 when reloaded later.

Parameters

	stream	is the name of output stream
out	*vSaveZones*	(non-empty) specifies the zones to be saved

Returns

whether the operation was successful

See also

The saveTriangulation() command can be used to store all triangles of a triangulation plus any specified zones. The Zone2::save() command is used to store just one zone. Use Fade_2D::load() to reload data from such files.

6.12.3.57 setFastMode()

```
void GEOM_FADE25D::Fade_2D::setFastMode (
    bool bFast )
```

By default, numerically perfect calculations are performed to compute a 100% perfect Delaunay triangulation. However, the quality difference to using double precision arithmetic is hardly noticeable. It is often rather relevant in scientific applications while practical applications may want to skip the computationally expensive calculations. Depending on the position of the input points, the effect of FastMode can be zero or a quite considerable acceleration.

Parameters

bFast	use true to avoid using multiple precision arithmetic in favor of better performance.

6.12.3.58 setNumCPU() `int GEOM_FADE25D::Fade_2D::setNumCPU ( int numCPU )`

Warning

This method is deprecated in favor of the free function int setGlobalNumCPU(). It is kept for backwards compatibility and it internally forwards the call to setGlobalNumCPU().

6.12.3.59 show() [1/2] `void GEOM_FADE25D::Fade_2D::show ( const char * postscriptFilename, bool bWithConstraints = true ) const`

show() is a convenience function for quick outputs with a default look. It is also possible to use the Visualizer2 class directly to draw arbitrary circles, line segments, vertices and labels with custom colors.

Parameters

postscriptFilename	is the output name, i.e. "myFile.ps"
bWithConstraints	specifies if constraint segments shall be shown (default: true)

6.12.3.60 show() [2/2] `void GEOM_FADE25D::Fade_2D::show ( Visualizer2 * pVis, bool bWithConstraints = true ) const`

This overload of the show() method allows to add further geometric primitives to the Visualizer2 object before it is finally written.

Parameters

pVis	is the pointer of a Visualizer2 object that may already contain geometric primitives or that may later be used to draw further elements
bWithConstraints	specifies if constraint segments shall be shown (default: true)

Note

When the last elements have been drawn, the postscript file must be finalized with Visualizer2::writeFile().

6.12.3.61 showGeomview() [1/2] `void GEOM_FADE25D::Fade_2D::showGeomview ( const char * filename, const char * color = "1 1 1 0.5" ) const`

Parameters

filename	is the output filename
color	is by default white (red:1,green:1,blue:1,alpha:0.5)

Note

The free viewer Geomview can be used to view such files

6.12.3.62 showGeomview() [2/2]

```
void GEOM_FADE25D::Fade_2D::showGeomview (
    Visualizer3 * pVis,
    const char * color = "1 1 1 0.5" ) const
```

Parameters

pVis	points to a Visualizer3 object
color	is by default white (red:1,green:1,blue:1,alpha:0.5)

Note

The free viewer Geomview can be used to view such files

6.12.3.63 statistics()

```
void GEOM_FADE25D::Fade_2D::statistics (
    const char * s ) const
```

Prints mesh statistics to stdout.

6.12.3.64 subscribe()

```
void GEOM_FADE25D::Fade_2D::subscribe (
    MsgType msgType,
    MsgBase * pMsg )
```

Parameters

msgType	is the type of message the subscriber shall receive, e.g. MSG_PROGRESS or MSG_WARNING
pMsg	is a pointer to a custom class derived from MsgBase

6.12.3.65 unsubscribe()

```
void GEOM_FADE25D::Fade_2D::unsubscribe (
    MsgType msgType,
    MsgBase * pMsg )
```

Parameters

msgType	is the type of message the subscriber shall not receive anymore
pMsg	is a pointer to a custom class derived from MsgBase

6.12.3.66 writeObj() [1/2]

```
void GEOM_FADE25D::Fade_2D::writeObj (
    const char * filename ) const
```

Parameters

filename	is the output filename

6.12.3.67 writeObj() [2/2]

```
void GEOM_FADE25D::Fade_2D::writeObj (
    const char * filename,
    Zone2 * pZone ) const
```

Visualizes a certain Zone2 object of the present triangulation. The *.obj format represents a 3D scene.

6.12.3.68 writePly() [1/2] bool GEOM_FADE25D::Fade_2D::writePly (

```
const char * filename,
bool bASCII = false ) const
```

Parameters

filename	is the output filename
bASCII	specifies whether to write the ∗.ply in ASCII or binary format

Note

Method available for platforms with C++11

6.12.3.69 writePly() [2/2] bool GEOM_FADE25D::Fade_2D::writePly (

```
std::ostream & os,
bool bASCII = false ) const
```

Parameters

os	is the output file
bASCII	specifies whether to write the ∗.ply in ASCII or binary format

Note

Method available for platforms with C++11

6.12.3.70 writeWebScene() [1/2] void GEOM_FADE25D::Fade_2D::writeWebScene (

```
const char * path ) const
```

Made for terrain visualizations in 2.5D but will work also for 2D.

6.12.3.71 writeWebScene() [2/2] void GEOM_FADE25D::Fade_2D::writeWebScene (

```
const char * path,
Zone2 * pZone ) const
```

Made for terrain visualizations in 2.5D but will work also for 2D.
The documentation for this class was generated from the following file:

- Fade_2D.h

6.13 GEOM_FADE25D::FadeExport Struct Reference

FadeExport is a simple struct to export triangulation data.
`#include <FadeExport.h>`

Public Member Functions

- **FadeExport** (const FadeExport &other)
- void **copy** (const FadeExport &other)
- void extractTriangleNeighborships (std::vector< std::pair< int, int > > &vNeigs) const

  Determine index-pairs of adjacent triangles.
- void getCoordinates (int vtxIdx, double &x, double &y, double &z) const

  Get the coorinates for a certain vertex index.
- void getCornerIndices (int triIdx, int &vtxIdx0, int &vtxIdx1, int &vtxIdx2) const

  Get the corner indices of a certain triangle.

- int getCustomIndex (int vtxIdx) const

  Get the custom vertex index.
- void getNormal (int triIdx, double &x, double &y, double &z) const

  Get the normal vector of a triangle.
- void lexiSort ()

  Sort the points lexicographically.
- FadeExport & **operator=** (const FadeExport &other)
- bool **operator==** (const FadeExport &other) const
- void print () const

  Print data for demonstration purposes.
- void reset ()

  Reset the object.
- bool writeObj (const char *filename) const

  *Write an *.obj file (supported by virtually any 3D viewer)*

Public Attributes

- double * aCoords

  *Cartesian coordinates (dim*numPoints)*
- int * aCustomIndices

  Custom indices of the points (only when exported)
- int * aTriangles

  *3 counterclockwise oriented vertex-indices per triangle (3*numTriangles)*
- int dim

  Dimension.
- int numCustomIndices

  number of custom indices (same as numPoints when exported, otherwise 0)
- int numPoints

  number of points
- int numTriangles

  number of triangles

6.13.1 Detailed Description

This data structure is there to get data out of Fade easily and memory efficiently. **The source code of this class is deliberately included in the header file** so that users can take over the code to their individual project.
Have a look at the Examples.

6.13.2 Member Function Documentation

6.13.2.1 getCoordinates()

```
void GEOM_FADE25D::FadeExport::getCoordinates (
        int vtxIdx,
        double & x,
        double & y,
        double & z ) const  [inline]
```

Parameters

vtxIdx	[in] vertex index
x,y,z	[out] coordinates

6.13.2.2 getCornerIndices()

```
void GEOM_FADE25D::FadeExport::getCornerIndices (
        int triIdx,
        int & vtxIdx0,
        int & vtxIdx1,
        int & vtxIdx2 ) const  [inline]
```

Parameters

trildx	[in] triangle index
vtxIdx0,vtxIdx1,vtxIdx2	[out] corner indices

6.13.2.3 getCustomIndex()

```
int GEOM_FADE25D::FadeExport::getCustomIndex (
        int vtxIdx ) const  [inline]
```

Returns

the (optional) custom index of the vertex with the index `vtxIdx` or -1 if the vertex indices have not been exported.

6.13.2.4 lexiSort()

```
void GEOM_FADE25D::FadeExport::lexiSort ( )
```

This method sorts the data lexicographically for reproducibility.

6.13.2.5 reset()

```
void GEOM_FADE25D::FadeExport::reset ( )  [inline]
```

This method deletes all contained data

The documentation for this struct was generated from the following file:

- FadeExport.h

6.14 GEOM_FADE25D::Func_gtEdge2D Struct Reference

Functor to sort edges by 2d length (descending)

`#include <Edge2.h>`

Public Member Functions

- bool **operator()** (const Edge2 &e0, const Edge2 &e1) const

The documentation for this struct was generated from the following file:

- Edge2.h

6.15 GEOM_FADE25D::Func_ltEdge25D Struct Reference

Functor to sort edges by 2.5d length (ascending)

`#include <Edge2.h>`

Public Member Functions

- bool **operator()** (const Edge2 &e0, const Edge2 &e1) const

The documentation for this struct was generated from the following file:

- Edge2.h

6.16 GEOM_FADE25D::Func_ltEdge2D Struct Reference

Functor to sort edges by 2d length (ascending)

`#include <Edge2.h>`

Public Member Functions

- bool **operator()** (const Edge2 &e0, const Edge2 &e1) const

The documentation for this struct was generated from the following file:

- Edge2.h

6.17 GEOM_FADE25D::Func_ltPointXYZ Struct Reference

Functor to sort points lexicographically.
`#include <Point2.h>`

Public Member Functions

- bool **operator()** (const Point2 &p0, const Point2 &p1) const

The documentation for this struct was generated from the following file:

- Point2.h

6.18 GEOM_FADE25D::IsoContours Class Reference

IsoContours uses a fast datastructure to compute intersections of horizontal planes with a given list of triangles.
`#include <IsoContours.h>`

Public Member Functions

- IsoContours (std::vector< Point2 > &vCorners, const Vector2 &dirVec)
- **IsoContours** (std::vector< Triangle2 * > &vTriangles)
- bool getContours (double height, std::vector< std::vector< Segment2 > > &vvContours, bool bVerbose, bool bAutoPerturbate=true)
- double getMaxHeight ()
- double getMinHeight ()
- void getProfile (const Point2 &p, std::vector< Segment2 > &vSegmentsOut)

Protected Member Functions

- **IsoContours** (const IsoContours &other)
- IsoContours & **operator=** (const IsoContours &other)

Protected Attributes

- std::vector< Triangle2 * > **vTriangles**

6.18.1 Detailed Description

See also

http://www.geom.at/terrain-triangulation/

6.18.2 Constructor & Destructor Documentation

6.18.2.1 IsoContours() `GEOM_FADE25D::IsoContours::IsoContours ( std::vector< Point2 > & vCorners, const Vector2 & dirVec )`

Experimental feature
IsoContours can be used to create profiles (slices).

Parameters

vCorners	contains 3∗n points to specify n triangles, i.e. it is a corners-list where 3 subsequent points define a triangle.
dirVec	specifies the slice direction to compute profiles

6.18.3 Member Function Documentation

6.18.3.1 getContours()

```
bool GEOM_FADE25D::IsoContours::getContours (
        double height,
        std::vector< std::vector< Segment2 > > & vvContours,
        bool bVerbose,
        bool bAutoPerturbate = true )
```

Get Contours
Computes the intersection of a horizontal plane at a certain height with all triangles and returns a vector of assembled polygons and polylines. The method works only for `height` values that do not occur as heights of any of the vertices. It returns false in such as case except `bAutoPerturbate=true`. In this case a tiny offset is automatically added to `height`.

Note

Polylines that end in the middle of a terrain can not exist and if you see such lines in the output then these are not only individual line segments but extremely narrow polygons - enforced by your geometric setting. You can numerically inspect those lines to verify that.

6.18.3.2 getMaxHeight()

```
double GEOM_FADE25D::IsoContours::getMaxHeight ( )
```

The the maximum height
Returns the largest z-coordinate

6.18.3.3 getMinHeight()

```
double GEOM_FADE25D::IsoContours::getMinHeight ( )
```

Get the minimum height
Returns the smallest z coordinate

6.18.3.4 getProfile()

```
void GEOM_FADE25D::IsoContours::getProfile (
        const Point2 & p,
        std::vector< Segment2 > & vSegmentsOut )
```

Get Profile
This is a new method to compute profiles i.e., to produce slices orthogonal to a direction specified in the constructor IsoContours(std::vector<Point2>& vCorners,const Vector2& dirVec)
The documentation for this class was generated from the following file:

- IsoContours.h

6.19 GEOM_FADE25D::Label Class Reference

Label is a Text-Label for Visualization.
`#include <Label.h>`

Public Member Functions

- **Label** (const Label &other)
- Label (const Point2 &p_, const char ∗s_, bool bWithMark_=true, int fontSize_=8)

  Constructs a Text-Label.
- const char ∗ **getCS** () const
- Label & **operator=** (const Label &other)

Public Attributes

- bool **bWithMark**
- int **fontSize**
- Point2 **p**
- LDat * **pDat**

6.19.1 Detailed Description

See also

Visualizer2 where Label objects are used for visualizations

6.19.2 Constructor & Destructor Documentation

6.19.2.1 Label()

```
GEOM_FADE25D::Label::Label (
        const Point2 & p_,
        const char * s_,
        bool bWithMark_ = true,
        int fontSize_ = 8 )
```

Parameters

*p_*	is the point where the label appears
*s_*	is the text to be shown
*bWith↩ Mark_*	switches between text-only and text-with-mark
*fontSize_*	

The documentation for this class was generated from the following file:

- Label.h

6.20 GEOM_FADE25D::MeshGenParams Class Reference

Parameters for the mesh generator.
`#include <MeshGenParams.h>`

Public Member Functions

- **MeshGenParams** (Zone2 *pZone_)
- void addLockedConstraint (ConstraintSegment2 *pConstraintSegment)

  Constraint Segments that shall not be splitted.
- virtual double getMaxEdgeLength (Triangle2 *pT)

  getMaxEdgeLength(Triangle2 pT)*
- virtual double getMaxTriangleArea (Triangle2 *pT)

  getMaxTriangleArea(Triangle2 pT)*

Public Attributes

- bool bAllowConstraintSplitting

  bAllowConstraintSplitting
- bool bGridMeshingLQ

  Low quality but high performance grid meshing.
- bool bKeepExistingSteinerPoints

  Steiner points from previous refinements.

- bool bReproducibleResults

  Reproducible results.
- double capAspectLimit

  capAspectLimit
- int command

  Command.
- double gridLength

  gridLength
- Point2 gridPoint

  Grid Point.
- Vector2 gridVector

  gridVector
- double growFactor

  growFactor
- double growFactorMinArea

  growFactorMinArea
- double maxEdgeLength

  Maximum edge length.
- double maxHeightError

  maxHeightError
- double maxTriangleArea

  maxTriangleArea
- double minAngleDegree

  Minimum interior triangle angle.
- double minEdgeLength

  Minimum edge length.
- Fade_2D * pHeightGuideTriangulation

  pHeightGuideTriangulation
- Zone2 * pZone

  Zone to be meshed.

6.20.1 Detailed Description

This class serves as container for mesh generator parameters. Client code can provide a class which derives from MeshGenParams and which provides custom implementations of the getMaxTriangleArea(Triangle* pT) method or the getMaxEdgeLength(Triangle* pT) method in order to gain control over the local density of the generated mesh. The meshing algorithm calls these functions to decide if a certain triangle must be refined.

See also

http://www.geom.at/advanced-mesh-generation/

6.20.2 Member Function Documentation

6.20.2.1 addLockedConstraint() `void GEOM_FADE25D::MeshGenParams::addLockedConstraint ( ConstraintSegment2 * pConstraintSegment )`

In case that some ConstraintSegment2 can be splitted and others must not be splitted use `bAllowConstraintSplitting=true` and add the ones that must not be splitted.

6.20.2.2 getMaxEdgeLength() `virtual double GEOM_FADE25D::MeshGenParams::getMaxEdgeLength ( Triangle2 * pT ) [inline], [virtual]`

Parameters

pT	is a triangle for which the meshing algorithm checks if it must be refined.

The default implementation of the present class returns the value maxEdgeLength (which is DBL_MAX if not changed by the user). This method can be overridden by the client software in order to control the local mesh density.




Figure 18 User Controlled Mesh Density, Edge Length

6.20.2.3 getMaxTriangleArea()

`virtual double GEOM_FADE25D::MeshGenParams::getMaxTriangleArea ( Triangle2 * pT ) [inline], [virtual]`

Parameters

pT	is a triangle for which the meshing algorithm checks if it must be refined.

The default implementation of the present class returns the value maxTriangleArea (which is the default value DBL_MAX if not changed by the user). This method can be overridden by the client software in order to control the local mesh density.




Figure 19 User Controlled Mesh Density, Area

6.20.3 Member Data Documentation

6.20.3.1 bAllowConstraintSplitting `bool GEOM_FADE25D::MeshGenParams::bAllowConstraintSplitting`

Defines if constraint segments can be splitted. Default: yes

6.20.3.2 bGridMeshingLQ `bool GEOM_FADE25D::MeshGenParams::bGridMeshingLQ`

By default bGridMeshingLQ=false in order to create high quality triangles everywhere. By using `bGridMeshingLQ=true` you can save time but a few bad shaped triangles may remain. This option works only together with grid-meshing.

6.20.3.3 bKeepExistingSteinerPoints `bool GEOM_FADE25D::MeshGenParams::bKeepExistingSteinerPoints`

A previous call to refine() or refineAdvanced() may have created Steiner points. These may be partially or entirely removed during a later refinement call, even (!) if this later refinement takes place in a different zone. It depends on your application if this behavior is desired or not. Usually you want to preserve the points, thus the default value of /p bKeepExistingSteinerPoints is true.

6.20.3.4 bReproducibleResults `bool GEOM_FADE25D::MeshGenParams::bReproducibleResults`

By default the algorithm generates reproducible triangulations. If not required you can disable that with `bReproducibleResults=false` to save time.

Note

Reproducible results are created *inside* `pZone`. If you need reproducable results outside also then create a global zone and call unifyGrid(0) once.

6.20.3.5 capAspectLimit `double GEOM_FADE25D::MeshGenParams::capAspectLimit`

Limits the quotient edgeLength / height. Default value: 10.0

6.20.3.6 command `int GEOM_FADE25D::MeshGenParams::command`

A command for development, not for public use. Will vanish soon.

6.20.3.7 gridLength `double GEOM_FADE25D::MeshGenParams::gridLength`

Set gridLength > 0 to mesh large enough areas with grid points. Border areas and narrow stripes where a grid does not fit are automatically meshed using classic Delaunay methods. By default gridLength=0 (off).

Note

The length of the diagonals in the grid is sqrt(2)∗gridLength and the algorithm may automatically adapt the gridLength a bit such that the grid fits better into the shape.




Figure 20 Grid Meshing axis aligned

6.20.3.8 gridPoint `Point2 GEOM_FADE25D::MeshGenParams::gridPoint`

An optional point through which the grid-mesh must pass

6.20.3.9 gridVector `Vector2 GEOM_FADE25D::MeshGenParams::gridVector`

When grid-meshing is used the grid is aligned to the `gridVector`. By default `gridVector` is axis aligned.




Figure 21 Grid Meshing along Vector2(1.0,0.3,0.0)

6.20.3.10 growFactor `double GEOM_FADE25D::MeshGenParams::growFactor`

Limits the growth of adjacent triangles. The mesh is constructed such that for any two adjacent triangles t0 and t1 (where t0 is the larger one) area(t0)/area(t1) $<$ growFactor. Recommendation: growFactor$>$5.0, Default: grow↩ Factor=DBL_MAX

6.20.3.11 growFactorMinArea `double GEOM_FADE25D::MeshGenParams::growFactorMinArea`

The growFactor value is ignored for triangles with a smaller area than growFactorMinArea. This value prevents generation of hundreds of tiny triangles around one that is unusually small. Default: 0.001

6.20.3.12 maxEdgeLength `double GEOM_FADE25D::MeshGenParams::maxEdgeLength`

This value is returned by the default implementation of getMaxEdgeLength(Triangle$*$ pT). Larger edges are automatically subdivided. If a custom implementation of getMaxEdgeLength(Triangle$*$ pT) is provided then this value is ignored. Default value: DBL_MAX.

6.20.3.13 maxHeightError `double GEOM_FADE25D::MeshGenParams::maxHeightError`

If pHeightGuideTriangulation is set and the height error exceeds locally maxHeightError then the triangulation is further refined.

6.20.3.14 maxTriangleArea `double GEOM_FADE25D::MeshGenParams::maxTriangleArea`

This value is returned by the default implementation of getMaxTriangleArea(Triangle$*$ pT). Larger triangles are automatically subdivided. If a custom implementation of getMaxTriangleArea(Triangle$*$ pT) is provided then this value is ignored. Default value: DBL_MAX.

6.20.3.15 minAngleDegree `double GEOM_FADE25D::MeshGenParams::minAngleDegree`

Minimum interior angle: Default: 20.0, maximum: 30.0

6.20.3.16 minEdgeLength `double GEOM_FADE25D::MeshGenParams::minEdgeLength`

Edges below the minimum length are not subdivided. This parameter is useful to avoid tiny triangles. Default: 0.001

6.20.3.17 pHeightGuideTriangulation `Fade_2D* GEOM_FADE25D::MeshGenParams::pHeightGuideTriangulation`

When new vertices are created then their height (z-coordinate) is usually computed from the existing triangles. In a situation where an extra triangulation with more accurate heights exists this extra triangulation cn be set als height guide triangulation. In this case the z-coordinates are computed from the triangles of the height guide triangulation.
The documentation for this class was generated from the following file:

- MeshGenParams.h

6.21 GEOM_FADE25D::MsgBase Class Reference

MsgBase, a base class for message subscriber classes.
`#include <MsgBase.h>`

Public Member Functions

- virtual void update (MsgType msgType, const char $*$s, double d)=0

  update

6.21.1 Detailed Description

MsgBase is a base class from which message subscriber classes (for example widgets, progress bars, ...) can be derived which then receive messages (progress, warnings, ...) from Fade.

See also

http://www.geom.at/progress-bar/

6.21.2 Member Function Documentation

6.21.2.1 update()

```
virtual void GEOM_FADE25D::MsgBase::update (
        MsgType msgType,
        const char * s,
        double d )  [pure virtual]
```

This method must be defined in derived classes. It is automatically called everytime Fade has a message of type `msgType`.
The documentation for this class was generated from the following file:

- MsgBase.h

6.22 GEOM_FADE25D::PeelPredicateTS Class Reference

User-defined peel predicate.
`#include <UserPredicates.h>`

Public Member Functions

- virtual bool **operator()** (const Triangle2 *, std::set< Triangle2 * > *pCurrentSet)=0

6.22.1 Detailed Description

This class is the successor of the deprecated (but still valid) UserPredicateT. In contrast to UserPredicateT the operator() receives also a set of current triangles to enable border-edge tests.

See also

`https://www.geom.at/mesh-improvements/`

The documentation for this class was generated from the following file:

- UserPredicates.h

6.23 GEOM_FADE25D::Point2 Class Reference

Point.
`#include <Point2.h>`

Public Member Functions

- Point2 ()
  Default constructor.
- Point2 (const double x_, const double y_, const double z_)
  Constructor.
- Point2 (const Point2 &p_)
  Copy constructor.
- int getCustomIndex () const
  Get the custom index.
- Triangle2 * getIncidentTriangle () const
  Get the associated triangle.
- double getMaxAbs () const
  Get max(abs(x),abs(y))
- bool operator!= (const Point2 &p) const
  Inequality operator.
- Point2 operator+ (const Vector2 &vec) const

Add vector and point.

- Vector2 operator- (const Point2 &other) const

  Returns a vector from other to ∗this.

- Point2 operator- (const Vector2 &vec) const

  Subtract vector from point.

- bool operator< (const Point2 &p) const

  Less than operator.

- Point2 & **operator=** (const Point2 &other)
- bool operator== (const Point2 &p) const

  Equality operator.

- bool operator> (const Point2 &p) const

  Greater than operator.

- bool samePoint (const Point2 &p) const

  Equality operator.

- void set (const double x_, const double y_, const double z_, int customIndex_)

  Set the coordinates.

- void set (const Point2 &pnt)

  Set the coordiantes.

- void setCoords (const double x_, const double y_, const double z_)

  Set the coordinates.

- void setCustomIndex (int customIndex_)

  Set a custom index.

- void setHeight (double z)

  Set the z-coordinate.

- void setIncidentTriangle (Triangle2 ∗pT)

  Associate a triangle with the point.

- double x () const

  Get the x-coordinate.

- void xy (double &x_, double &y_) const

  Get the x- and y-coordinate.

- void xyz (double &x_, double &y_, double &z_) const

  Get the x-, y- and z-coordinate.

- double y () const

  Get the y-coordinate.

- double z () const

  Get the z-coordinate.

Protected Attributes

- double **coordX**
- double **coordY**
- double **coordZ**
- int **customIndex**
- Triangle2 ∗ **pAssociatedTriangle**

Friends

- class **Dt2**
- std::ostream & operator<< (std::ostream &stream, const Point2 &pnt)

  Print to stream.

- std::istream & operator>> (std::istream &stream, Point2 &pnt)

  Stream-to-Point.

6.23.1 Detailed Description

This class represents a point in 2D with x- and y-coordinates and an additional pointer to an associated triangle.

6.23.2 Constructor & Destructor Documentation

6.23.2.1 Point2() [1/2] GEOM_FADE25D::Point2::Point2 (const double x_, const double y_, const double z_) [inline]

Parameters

x_	x-coordinate
y_	y-coordinate
z_	z-coordinate

6.23.2.2 Point2() [2/2] GEOM_FADE25D::Point2::Point2 (const Point2 & p_) [inline]

Create a point as a copy of p_. The associated triangle pointer is initialized to NULL

6.23.3 Member Function Documentation

6.23.3.1 getCustomIndex() int GEOM_FADE25D::Point2::getCustomIndex ( ) const [inline]

Returns

the custom index.

Note

The custom index defaults to -1. It is not the index of the point in the triangulation (such an index does not exist) but an arbitrary value which can be set by the user.

See also

void setCustomIndex(int customIndex_)

A best practices example that deals with indices: http://www.geom.at/runtime/

6.23.3.2 getIncidentTriangle() Triangle2* GEOM_FADE25D::Point2::getIncidentTriangle ( ) const [inline]

Returns

the associated triangle

6.23.3.3 operator"!=() bool GEOM_FADE25D::Point2::operator!= (const Point2 & p) const [inline]

Compares the x and y coordinates

Note

Although a point has a z-coordinate in the 2.5D version only x and y a compared by this method

6.23.3.4 operator<() bool GEOM_FADE25D::Point2::operator< (const Point2 & p) const [inline]

Compares the x and y coordinates

Note

Although a point has a z-coordinate in the 2.5D version only x and y a compared by this method

6.23.3.5 operator==() bool GEOM_FADE25D::Point2::operator== (const Point2 & p) const [inline]

Compares the x and y coordinates

Note

Although a point has a z-coordinate in the 2.5D version only x and y a compared by this method

6.23.3.6 operator>() bool GEOM_FADE25D::Point2::operator> (const Point2 & p) const [inline]

Compares the x and y coordinates

Note

Although a point has a z-coordinate in the 2.5D version only x and y a compared by this method

6.23.3.7 samePoint() bool GEOM_FADE25D::Point2::samePoint (const Point2 & p) const [inline]

Compares the x,y,z coordinates while operator==() compares only x,y

6.23.3.8 set() [1/2] void GEOM_FADE25D::Point2::set (const double x_, const double y_, const double z_, int customIndex_) [inline]

Internal method

Parameters

*x_*	x-coordinate
*y_*	y-coordinate
*z_*	z-coordinate
*customIndex_*	Arbitrary index, use -1 if not required

6.23.3.9 set() [2/2] void GEOM_FADE25D::Point2::set (const Point2 & pnt) [inline]

Parameters

pnt	is the point whose coordinates are assigned to the current point

6.23.3.10 setCoords() void GEOM_FADE25D::Point2::setCoords (const double x_, const double y_, const double z_) [inline]

Internal method

Parameters

*x_*	x-coordinate
*y_*	y-coordinate
*z_*	z-coordinate

Note

Does not adapt customIndex and pAssociatedTriangle.

6.23.3.11 setCustomIndex() void GEOM_FADE25D::Point2::setCustomIndex (int customIndex_) [inline]

An arbitrary index can be assigned to a point. Use getCustomIndex() to retrieve it later.

Note

This method is provided for the users' convenience. It has nothing to do with the internal data structures of Fade 2D and using this method is optional. By default this index is -1.

See also

int getCustomIndex()

A best practices example that deals with indices: http://www.geom.at/runtime/

6.23.3.12 setHeight() void GEOM_FADE25D::Point2::setHeight (double z) [inline]

Allows to exchange the z-coordinate

6.23.3.13 setIncidentTriangle() void GEOM_FADE25D::Point2::setIncidentTriangle (Triangle2 * pT) [inline]

Parameters

pT	will be associated with the triangle

6.23.3.14 x() `double GEOM_FADE25D::Point2::x ( ) const [inline]`

Returns

the x-coordinate

6.23.3.15 xy() `void GEOM_FADE25D::Point2::xy ( double & x_, double & y_ ) const [inline]`

Parameters

*x_*	x-coordinate
*y_*	y-coordinate

6.23.3.16 xyz() `void GEOM_FADE25D::Point2::xyz ( double & x_, double & y_, double & z_ ) const [inline]`

Parameters

*x_*	x-coordinate
*y_*	y-coordinate
*z_*	z-coordinate

6.23.3.17 y() `double GEOM_FADE25D::Point2::y ( ) const [inline]`

Returns

the y-coordinate

6.23.3.18 z() `double GEOM_FADE25D::Point2::z ( ) const [inline]`

Returns

the z-coordinate

The documentation for this class was generated from the following file:

- Point2.h

6.24 GEOM_FADE25D::PShape Class Reference

Polygonal Shape for Visualization.
`#include <PShape.h>`

Public Member Functions

- **PShape** (const PShape &other)
- PShape (std::vector< Point2 > &vP_)

  Constructor.
- PShape & **operator=** (const PShape &other)

Protected Attributes

- std::vector< Point2 > * **pVP**

Friends

- std::ostream & **operator**<< (std::ostream &stream, PShape b)
- class **Visualizer2**

6.24.1 Detailed Description

See also

Visualizer2

The documentation for this class was generated from the following file:

- PShape.h

6.25 GEOM_FADE25D::Segment2 Class Reference

Segment.
`#include <Segment2.h>`

Public Member Functions

- Segment2 ()
- Segment2 (const Point2 &src_, const Point2 &trg_)

  Create a Segment2.
- double getSqLen25D () const
- double getSqLen2D () const
- Point2 getSrc () const
- Point2 getTrg () const
- bool operator< (const Segment2 &other) const
- bool operator== (const Segment2 &other) const
- void swapSrcTrg ()

Protected Attributes

- Point2 **src**
- Point2 **trg**

Friends

- std::ostream & **operator**<< (std::ostream &stream, Segment2 seg)

6.25.1 Constructor & Destructor Documentation

6.25.1.1 Segment2() [1/2] GEOM_FADE25D::Segment2::Segment2 (

```
const Point2 & src_,
const Point2 & trg_ )
```

Parameters

*src_*	First endpoint (source)
*trg_*	Second endpoint (target)

6.25.1.2 Segment2() [2/2] GEOM_FADE25D::Segment2::Segment2 ( )

Create a Segment2 Default constructor

6.25.2 Member Function Documentation

6.25.2.1 getSqLen25D() double GEOM_FADE25D::Segment2::getSqLen25D ( ) const

Get the squared length (2.5D version)

6.25.2.2 getSqLen2D() double GEOM_FADE25D::Segment2::getSqLen2D ( ) const

Get the squared length

6.25.2.3 getSrc() Point2 GEOM_FADE25D::Segment2::getSrc ( ) const

Get the source point

Returns

the source point

6.25.2.4 getTrg() Point2 GEOM_FADE25D::Segment2::getTrg ( ) const

Get the target point

Returns

the target point

6.25.2.5 operator<() bool GEOM_FADE25D::Segment2::operator< (

```
const Segment2 & other ) const  [inline]
```

operator<() Used to compare segments lexicographically

6.25.2.6 operator==() bool GEOM_FADE25D::Segment2::operator== (

```
const Segment2 & other ) const
```

operator==()
Undirected equality operator

6.25.2.7 swapSrcTrg() void GEOM_FADE25D::Segment2::swapSrcTrg ( )

Internally swaps the source and target point
The documentation for this class was generated from the following file:

- Segment2.h

6.26 GEOM_FADE25D::SegmentChecker Class Reference

SegmentChecker identifies intersecting line segments.
`#include <SegmentChecker.h>`

Public Member Functions

- SegmentChecker (const std::vector< Segment2 * > &vSegments_)
- ClipResult clipSegment (Segment2 &seg)
- void getIllegalSegments (bool bAlsoEndPointIntersections, std::vector< Segment2 * > &vIllegalSegments↩ Out) const
- int getIndex (Segment2 *pSeg) const
- void getIntersectionPoint (SegmentIntersectionType sit, const Segment2 &seg0, const Segment2 &seg1, Point2 &ispOut0, Point2 &ispOut1) const
- void getIntersectionSegment (const Segment2 &seg0, const Segment2 &seg1, Segment2 &issOut0, Segment2 &issOut1) const
- SegmentIntersectionType getIntersectionType (const Segment2 *pSeg1, const Segment2 *pSeg2) const
- void getIntersectors (Segment2 *pTestSegment, bool bAlsoEndPointIntersections, std::vector< std::pair< Segment2 *, SegmentIntersectionType > > &vIntersectorsOut) const
- Bbox2 getLimit () const
- size_t getNumberOfSegments () const
- Segment2 * getSegment (size_t i) const
- void setLimit (const Bbox2 &bbx)
- void showIllegalSegments (bool bAlsoEndPointIntersections, const char *name) const
- void showSegments (const char *name) const
- void subscribe (MsgType msgType, MsgBase *pMsg)
- void unsubscribe (MsgType msgType, MsgBase *pMsg)

Static Public Member Functions

- static const char * getIntersectionTypeString (SegmentIntersectionType sit)

6.26.1 Detailed Description

SegmentChecker takes a bunch of line segments and fully automatically identifies illegal segment intersections. The intersection points can be computed in 2D and in 2.5D. Further this class offers visualization methods. Due to the underlying datastructure the search algorithm scales very well to large inputs.




Figure 22 Polylines: Intersecting segments are automatically found

See also

http://www.geom.at/segment-checker/

6.26.2 Constructor & Destructor Documentation

6.26.2.1 SegmentChecker() `GEOM_FADE25D::SegmentChecker::SegmentChecker ( const std::vector< Segment2 * > & vSegments_ ) [explicit]`

Internally this constructor prepares a data structure from `vSegments` that enables efficient spatial searches. The time complexity is O(n∗log(n)).

Parameters

*vSegments_*	contains the segments to be checked

6.26.3 Member Function Documentation

6.26.3.1 clipSegment()

```
ClipResult GEOM_FADE25D::SegmentChecker::clipSegment (
        Segment2 & seg )
```

Clip Segment
Use this method to limit the length of a line-segment to its intersection with a box. The result can be the whole segment, a subsegment, a degenerate segment or the result can be empty. In the last case the segment is not changed but the method returns CR_EMPTY.

Parameters

in,out	*seg*	is the line segment to be clipped

Returns

CR_INVALID,CR_EMPTY, CR_CLIPPED_DEGENERATE, CR_CLIPPED_NONDEGENERATE, CR_COMPLETE_DEGENERATE, CR_COMPLETE_NONDEGENERATE or CR_INVALID.

Note

In case that you missed to call setLimit() with a valid bounding box before, the method returns CR_INVALID };

6.26.3.2 getIllegalSegments()

```
void GEOM_FADE25D::SegmentChecker::getIllegalSegments (
        bool bAlsoEndPointIntersections,
        std::vector< Segment2 * > & vIllegalSegmentsOut ) const
```

Get illegal segments
Returns segments which are involved in intersections. Intersections at endpoints are only reported when bAlsoEndPointIntersections is true. The asymptotic time consumption for the lookup per segment S is O(log(n)+k) where k is the number of segments that intersect the minimal bounding box of S. Thus, for n segments the method takes O(n∗(log(n)+k)) time.

Parameters

	bAlsoEndPointIntersections	specifies if intersections at endpoints shall be detected
out	*vIllegalSegmentsOut*	is the output vector

6.26.3.3 getIndex()

```
int GEOM_FADE25D::SegmentChecker::getIndex (
        Segment2 * pSeg ) const
```

Returns the index of a segment

Parameters

pSeg	is the segment whose index is returned

6.26.3.4 getIntersectionPoint()

```
void GEOM_FADE25D::SegmentChecker::getIntersectionPoint (
        SegmentIntersectionType sit,
        const Segment2 & seg0,
        const Segment2 & seg1,
        Point2 & ispOut0,
```

```
Point2 & ispOut1 ) const
```

Compute the intersection point(s) of two segments.
Use getIntersectionType() to determine the segment intersection type `sit` before. Call this function only when the intersection type is SIT_POINT or SIT_ENDPOINT.

Parameters

	sit	is the segment intersection type (SIT_POINT or SIT_ENDPOINT for the present method)
	seg0,seg1	are the intersecting segments
out	*ispOut0*	output intersection point at `seg0`
out	*ispOut1*	output intersection point at `seg1`

The resulting two output intersection points `ispOut0` and `ispOut1` have always the same (x,y) coordinates but possibly different heights `z`.

Note

`pSeg1` and `pSeg2` do not need to be from the set of segments that have been used as argument for the constructor of the SegmentChecker. You can use any segments.

6.26.3.5 getIntersectionSegment()

```
void GEOM_FADE25D::SegmentChecker::getIntersectionSegment (
    const Segment2 & seg0,
    const Segment2 & seg1,
    Segment2 & issOut0,
    Segment2 & issOut1 ) const
```

Compute the intersection segment(s) of two collinear intersecting segments.
Use getIntersectionType() to determine the segment intersection type `sit` before. Call this function only when the intersection type is SIT_SEGMENT.

Parameters

	seg0,seg1	are intersecting segments such that their SegmentIntersectionType is SIT_SEGMENT
out	*issOut0*	intersection segment at `seg0`
out	*issOut1*	intersection segment at `seg1`

The two output segments have always the same (x,y) coordinates but possibly diffent heights `z`.

Note

`pSeg1` and `pSeg2` do not need to be from the set of segments that have been used as argument for the constructor of the SegmentChecker. You can use any segments.

6.26.3.6 getIntersectionType()

```
SegmentIntersectionType GEOM_FADE25D::SegmentChecker::getIntersectionType (
    const Segment2 * pSeg1,
    const Segment2 * pSeg2 ) const
```

Get the intersection type of two segments

Parameters

pSeg1,pSeg2	are the segments to be checked

Returns

SIT_NONE (no intersection),
SIT_SEGMENT (collinear intersection),
SIT_POINT (intersection somewhere between the endpoints) or
SIT_ENDPOINT (endpoint intersection)

Note

`pSeg1` and `pSeg2` do not need to be from the set that has been used to initialize the present object

6.26.3.7 getIntersectionTypeString()

```
static const char* GEOM_FADE25D::SegmentChecker::getIntersectionTypeString (
        SegmentIntersectionType sit ) [static]
```

Return the intersection type as a human readable string. This is a convenience function

Parameters

sit	is an intersection type to be converted to a string

6.26.3.8 getIntersectors()

```
void GEOM_FADE25D::SegmentChecker::getIntersectors (
        Segment2 * pTestSegment,
        bool bAlsoEndPointIntersections,
        std::vector< std::pair< Segment2 *, SegmentIntersectionType > > & vIntersectorsOut ) const
```

Return segments that intersect a certain segment along with their intersection type

Parameters

	pTestSegment	is the segment to be analyzed
	bAlsoEndPointIntersections	specifies if intersections of type SIT_ENDPOINT shall also be reported.
out	*vIntersectorsOut*	is the output vector. Segments intersecting `pTestSegment` are added to `vIntersectorsOut` along with their intersection type.

Note

When vIntersectorsOut is non-empty, it is not cleared but the intersected segments are added.

The time complexity is O(log(n)+k) where n is the number of segments and k is the number of intersections for `pTestSegment`.

6.26.3.9 getLimit()

```
Bbox2 GEOM_FADE25D::SegmentChecker::getLimit ( ) const
```

Get Limit

Returns

the bounding box that has been set before using setLimit()

6.26.3.10 getNumberOfSegments()

```
size_t GEOM_FADE25D::SegmentChecker::getNumberOfSegments ( ) const
```

Returns the number of segments contained in this SegmentChecker object

6.26.3.11 getSegment()

```
Segment2* GEOM_FADE25D::SegmentChecker::getSegment (
        size_t i ) const
```

Returns the i-th segment

Parameters

i	is the index of the segment to be returned

6.26.3.12 setLimit()

```
void GEOM_FADE25D::SegmentChecker::setLimit (
        const Bbox2 & bbx )
```

Set Limit

Sets the bounding box `bbx` that is used by clipSegment() to limit the length of a line segment

6.26.3.13 showIllegalSegments()

```
void GEOM_FADE25D::SegmentChecker::showIllegalSegments (
        bool bAlsoEndPointIntersections,
        const char * name ) const
```

Write a postscript file, highlight illegal segments

Parameters

bAlsoEndPointIntersections	specifies if intersections at endpoints are also illegal
name	is the output filename




Figure 23 Visualization of polyline intersections

6.26.3.14 showSegments() `void GEOM_FADE25D::SegmentChecker::showSegments ( const char * name ) const`

Write all segments, with and without intersection, to a postscript file

Parameters

name	is the output filename




Figure 24 Line segments written to a postscript file

6.26.3.15 subscribe()

```
void GEOM_FADE25D::SegmentChecker::subscribe (
        MsgType msgType,
        MsgBase * pMsg )
```

Register a progress bar object

The SegmentChecker does its job typically in fractions of a second. But inputs may contain a quadratic number of intersections and such tasks take a while. Therefore a user defined message object (your own progress-bar class) can be registered in order to get progress updates. This step is optional.

Parameters

msgType	is the message type. For progress information the type is always MSG_PROGRESS
pMsg	is a user defined progress bar which derives from Fade's MsgBase.

6.26.3.16 unsubscribe()

```
void GEOM_FADE25D::SegmentChecker::unsubscribe (
        MsgType msgType,
```

```
MsgBase * pMsg )
```

Unregister a progress bar object

Parameters

msgType	is the message type. For progress information the type is always MSG_PROGRESS
pMsg	is a user defined class which derives from Fade's MsgBase

The documentation for this class was generated from the following file:

- SegmentChecker.h

6.27 GEOM_FADE25D::Triangle2 Class Reference

Triangle.

`#include <Triangle2.h>`

Public Member Functions

- Triangle2 ()

  Constructor.
- void clearProperties ()

  Clear all corners and neighbor pointers.
- double getArea25D () const

  Get 2.5D Area.
- double getArea2D () const

  Get 2D Area.
- Point2 getBarycenter () const

  Get the barycenter of a triangle.
- Point2 getCircumcenter (CircumcenterQuality &ccq, bool bForceExact=false) const

  Get the circumcenter of the triangle.
- void getCorners (Point2 *&p0, Point2 *&p1, Point2 *&p2) const

  Get the 3 triangle corners.
- std::pair< Point2, bool > **getDual** (bool bForceExact=false) const
- double getInteriorAngle25D (int ith) const

  Get interior 2.5D angle.
- double getInteriorAngle2D (int ith) const

  Get interior 2D angle.
- int getIntraTriangleIndex (const Point2 *p) const

  Get the index of p in the triangle.
- int getIntraTriangleIndex (const Point2 *p0, const Point2 *p1) const

  Get the index of (p0,p1)
- int getIntraTriangleIndex (const Triangle2 *pTriangle) const

  Get the neighbor index of pTriangle.
- int getMaxIndex () const

  Get the index of the largest edge.
- double getMaxSqEdgeLen2D () const

  Get the maximum squared 2D edge length.
- int getMinIndex () const

  Get the index of the smallest edge.
- Vector2 getNormalVector () const

  Get the normal vector of a triangle.
- Triangle2 * getOppositeTriangle (const int ith) const

Get the i-th neighbor triangle.

- double getSquaredEdgeLength25D (int ith) const

  Squared edge length.

- double getSquaredEdgeLength2D (int ith) const

  **

- bool hasOn (const Point2 &q) const

  Has on (triangle)

- bool hasOnEdge (int i, const Point2 &q) const

  Has point on edge.

- bool hasVertex (const Point2 &vtx) const

  Has vertex.

- bool hasVertex (const Point2 *pVtx) const

  Has vertex.

- void setOppTriangle (const int ith, Triangle2 *pTriangle)

  Set the i-th neighbor triangle.

- void setProperties (Point2 *pI, Point2 *pJ, Point2 *pK)

  Set all corners.

- void setPropertiesAndOppT (Point2 *pI, Point2 *pJ, Point2 *pK, Triangle2 *pNeig0, Triangle2 *pNeig1, Triangle2 *pNeig2)

  Set all corners and neighbor triangles.

- void setVertexPointer (const int ith, Point2 *pp)

  Set the i-th corner.

Protected Member Functions

- double **computeArea** (double l0, double l1, double l2) const
- bool **getCC_inexact** (double avgOffX, double avgOffY, Point2 &cc) const

Protected Attributes

- Triangle2 * **aOppTriangles** [3]
- Point2 * **aVertexPointer** [3]

Friends

- std::ostream & **operator<<** (std::ostream &stream, const Triangle2 &c)
- void **registerTriangles** (Triangle2 *fromTriangle, int ith, Triangle2 *toTriangle, int jth)

6.27.1 Detailed Description

Triangle2 is a triangle in the Fade_2D triangulation. It holds three Point2 pointers to its corners. The corners are numbered in counterclockwise order. We refer to these indices as intra-triangle-indices.
Each triangle has three neighbors which can be accessed through intra-triangle-indices: The i-th neighbor triangle of a certain triangle T is the one which shares an edge with T such that this edge does not include the i-th corner of T.




Figure 25 Indices and neighborships, *tb* is the 0-th neighbor of *ta* and *ta* is the 2nd neighbor of *tb*.

See also

TriangleAroundVertexIterator to find out how to access all triangles incident to a certain vertex.

6.27.2 Member Function Documentation

6.27.2.1 getArea25D() `double GEOM_FADE25D::Triangle2::getArea25D ( ) const`

Returns the 2.5D area of the triangle.
Note: The getArea() method is deprecated and replaced by getArea2D() and getArea25D()

6.27.2.2 getArea2D() `double GEOM_FADE25D::Triangle2::getArea2D ( ) const`

Returns the 2D area of the triangle.
Note: The getArea() method is deprecated and replaced by getArea2D() and getArea25D()

6.27.2.3 getBarycenter() `Point2 GEOM_FADE25D::Triangle2::getBarycenter ( ) const`

Returns

the barycenter of the triangle.

6.27.2.4 getCircumcenter()

```
Point2 GEOM_FADE25D::Triangle2::getCircumcenter (
    CircumcenterQuality & ccq,
    bool bForceExact = false ) const
```

Parameters

out	*ccq*	returns the quality of the computed point and is one of CCQ_INEXACT, CCQ_EXACT and CCQ_OUT_OF_BOUNDS.
in	*bForceExact*	forces exact computation with multiple-precision arithmetic. When bForceExact=false, then the faster double-precision arithmetic is used for good shaped triangles.

Returns

the circumcenter of the triangle. The z-coordinate is 0.0. You can use Fade_2D::getHeight(..) to determine the height.

Attention

Attention: The circumcenter of a nearly collinear triangle can have extremely large coordinates. Fade computes the circumcenter with multiple-precision artihmetic in this case but the result might nevertheless not be exact because it too large for double-precision coordinates. In such cases a finite point is returned and `ccq` returns CCQ_OUT_OF_BOUNDS. You can avoid such extreme numeric cases easily: Just insert four dummy vertices around the triangulation at coordinates 10 times larger than the domain of the data points because this restricts the Voronoi cells of the data points to this range.

6.27.2.5 getInteriorAngle25D()

```
double GEOM_FADE25D::Triangle2::getInteriorAngle25D (
    int ith ) const
```

Returns

the interior 2.5D angle at the ith vertex

6.27.2.6 getInteriorAngle2D() `double GEOM_FADE25D::Triangle2::getInteriorAngle2D ( int ith ) const`

Note: The getInteriorAngle() method is deprecated and replaced by getInteriorAngle2D() and getInteriorAngle25D()

Returns

the interior 2D angle at the ith vertex

6.27.2.7 getIntraTriangleIndex() [1/3] `int GEOM_FADE25D::Triangle2::getIntraTriangleIndex ( const Point2 * p ) const [inline]`




Figure 26 Intra triangle index of a vertex pointer

Parameters

p	is a pointer to a vertex in ∗*this*

Returns

the intra-triangle-index 0,1 or 2 of *p* in ∗*this*

6.27.2.8 getIntraTriangleIndex() [2/3] `int GEOM_FADE25D::Triangle2::getIntraTriangleIndex ( const Point2 * p0, const Point2 * p1 ) const [inline]`

Returns

the index of the edge (p0,p1) in the triangle

6.27.2.9 getIntraTriangleIndex() [3/3] `int GEOM_FADE25D::Triangle2::getIntraTriangleIndex ( const Triangle2 * pTriangle ) const [inline]`




Figure 27 pTriangle is the 0-th neighbor of ∗this

Parameters

pTriangle	is a neighbor triangle of ∗this.

Returns

the intra-triangle-index of the vertex in ∗*this* which is opposite (i.e., does not touch the neighbor) *pTriangle*.

6.27.2.10 getNormalVector() `Vector2 GEOM_FADE25D::Triangle2::getNormalVector ( ) const`

Returns

the normalized normal vector

6.27.2.11 getOppositeTriangle() `Triangle2 * GEOM_FADE25D::Triangle2::getOppositeTriangle ( const int ith ) const [inline]`

Returns the *i-th* neighbor triangle, i.e. the one opposite to the *i-th* corner.




Figure 28 Neighbors of a triangle

Parameters

ith	is the intra-triangle-index of the opposite corner of ∗*this*

Returns

the i-th neighbor triangle, i.e. the one opposite to the i-th vertex or NULL if no neighbor triangle exists which is the case at the convex hull edges of the triangulation.

6.27.2.12 getSquaredEdgeLength25D() `double GEOM_FADE25D::Triangle2::getSquaredEdgeLength25D ( int ith ) const`

Returns the squared length of the *ith* edge.

6.27.2.13 getSquaredEdgeLength2D() `double GEOM_FADE25D::Triangle2::getSquaredEdgeLength2D ( int ith ) const`

Method for internal use
Squared edge length
Returns the squared length of the *ith* edge. This method ignores the z-coordinate.

6.27.2.14 hasOn() `bool GEOM_FADE25D::Triangle2::hasOn ( const Point2 & q ) const`

Returns

if q is on the triangle

This is a 2D test i.e., z coordinate is not evaluated

6.27.2.15 hasOnEdge()

```
bool GEOM_FADE25D::Triangle2::hasOnEdge (
    int i,
    const Point2 & q ) const
```

Returns

if q is exactly on the i-th edge

This is a 2D test i.e., z coordinate is not evaluated

6.27.2.16 hasVertex() [1/2]

```
bool GEOM_FADE25D::Triangle2::hasVertex (
    const Point2 & vtx ) const
```

Returns

if vtx is a corner of the triangle

6.27.2.17 hasVertex() [2/2]

```
bool GEOM_FADE25D::Triangle2::hasVertex (
    const Point2 * pVtx ) const
```

Returns

if pVtx is a corner of the triangle

6.27.2.18 setOppTriangle()

```
void GEOM_FADE25D::Triangle2::setOppTriangle (
    const int ith,
    Triangle2 * pTriangle ) [inline]
```




Figure 29 Make pTriangle the 0-th neighbor of ∗this

Parameters

ith	is the index of the corner of ∗*this* which does not touch *pTriangle*
pTriangle	is a pointer to the triangle which shares two corners with ∗*this*

The documentation for this class was generated from the following file:

- Triangle2.h

6.28 GEOM_FADE25D::TriangleAroundVertexIterator Class Reference

Iterator for all triangles around a given vertex.
`#include <TriangleAroundVertexIterator.h>`

Public Member Functions

- TriangleAroundVertexIterator (const Point2 *pPnt_)
  Constructor.
- TriangleAroundVertexIterator (const TriangleAroundVertexIterator &it)
  Copy constructor.
- TriangleAroundVertexIterator (Point2 *pPnt_, Triangle2 *pTr_)
  Constructor.
- bool operator!= (const TriangleAroundVertexIterator &rhs)
  operator!=()
- Triangle2 * operator* ()
  Returns a pointer to the current triangle (or NULL)
- TriangleAroundVertexIterator & operator++ ()
  Proceed to the next triangle (the one in counterclockwise order)
- TriangleAroundVertexIterator & operator-- ()
  Proceed to the previous triangle (the one in clockwise order)
- TriangleAroundVertexIterator & **operator=** (const TriangleAroundVertexIterator &other)
- bool operator== (const TriangleAroundVertexIterator &rhs)
  operator==()
- Triangle2 * previewNextTriangle ()
  Preview next triangle (CCW direction)
- Triangle2 * previewPrevTriangle ()
  Preview previous triangle (CW direction)

Protected Member Functions

- void **loop** ()

Protected Attributes

- const Point2 * **pPnt**
- Triangle2 * **pSavedTr**
- Triangle2 * **pTr**

6.28.1 Detailed Description

The TriangleAroundVertexIterator iterates over all triangles incident to a given vertex of a Fade_2D instance. The advantage is that the incident triangles can be visited in a certain order, namely counterclockwise with operator++() or clockwise using operator--(). If the order is not important you can use Fade_2D::getIncidentTriangles() instead.




Figure 30 Left: the iterator visits the triangles around a vertex. Right: The iterator 'jumps' over the border edges of the triangulation

6.28.2 Constructor & Destructor Documentation

6.28.2.1 TriangleAroundVertexIterator() [1/3] GEOM_FADE25D::TriangleAroundVertexIterator::↩ TriangleAroundVertexIterator (const Point2 * pPnt_) [inline], [explicit]

Parameters

p↩ Pnt↩ _	is the vertex whose incident triangles can be visited with the iterator

Initially the iterator points to an arbitrary triangle (not NULL)

6.28.2.2 TriangleAroundVertexIterator() [2/3] GEOM_FADE25D::TriangleAroundVertexIterator::↩ TriangleAroundVertexIterator (Point2 * pPnt_, Triangle2 * pTr_) [inline]

Parameters

p↩ Pnt↩ _	is the vertex whose incident triangles can be visited with the iterator
pTr↩ _	is the triangle the iterator initially points to

6.28.2.3 TriangleAroundVertexIterator() [3/3] GEOM_FADE25D::TriangleAroundVertexIterator::↩ TriangleAroundVertexIterator (const TriangleAroundVertexIterator & it) [inline]

Copies the iterator `it`

6.28.3 Member Function Documentation

6.28.3.1 operator"!=() bool GEOM_FADE25D::TriangleAroundVertexIterator::operator!= (const TriangleAroundVertexIterator & rhs) [inline]

Compares the center and the current triangle of ∗this and `rhs`

Returns

true when they are different, false otherwise

6.28.3.2 operator∗() Triangle2* GEOM_FADE25D::TriangleAroundVertexIterator::operator* ( ) [inline]

Dereferencing the iterator yields a pointer to the triangle to which the iterator points.

Warning

This method might yield NULL at the border of a triangulation.

6.28.3.3 operator++() TriangleAroundVertexIterator& GEOM_FADE25D::TriangleAroundVertexIterator::operator++ ( ) [inline]

Moves the iterator to the next triangle in counterclockwise order.

Warning

At the border of a triangulation, two border edges exist which are incident to the center vertex. Consequently, the neighbor triangles are NULL there. If operator++() leads the iterator off the triangulation then the iterator will point to NULL. Another call to operator++() will set the iterator to the next triangle in counterclockwise order.

6.28.3.4 operator--() TriangleAroundVertexIterator& GEOM_FADE25D::TriangleAroundVertexIterator::operator-- ( ) [inline]

Moves the iterator to the next triangle in clockwise order.

Warning

At the border of a triangulation, two border edges are incident to the center vertex. Consequently, the neighbor triangles are NULL there. If operator--() leads the iterator off the triangulation then the iterator will point to NULL. Another call to operator--() will set the iterator to the next triangle in clockwise order.

6.28.3.5 operator==() bool GEOM_FADE25D::TriangleAroundVertexIterator::operator== (const TriangleAroundVertexIterator & *rhs*) [inline]

Compares the center and the current triangle of *this and rhs

Returns

true when they are identically or false otherwise

6.28.3.6 previewNextTriangle() Triangle2* GEOM_FADE25D::TriangleAroundVertexIterator::previewNextTriangle ( ) [inline]

Returns

the next triangle (the one in CCW direction) without changing the current position.

Warning

This method might yield NULL at the border of a triangulation.

6.28.3.7 previewPrevTriangle() Triangle2* GEOM_FADE25D::TriangleAroundVertexIterator::previewPrevTriangle ( ) [inline]

Returns

the previous triangle (the one in CW direction) without changing the current position.

Warning

This method might yield NULL at the border of a triangulation.

The documentation for this class was generated from the following file:

- TriangleAroundVertexIterator.h

6.29 GEOM_FADE25D::UserPredicateT Class Reference

User-defined predicate (deprecated)
`#include <UserPredicates.h>`

Public Member Functions

- virtual bool **operator()** (const Triangle2 *)=0

6.29.1 Detailed Description

This class is deprecated in favor of PeelPredicateTS. It is kept for backwards compatibility.
The documentation for this class was generated from the following file:

- UserPredicates.h

6.30 GEOM_FADE25D::Vector2 Class Reference

Vector.
`#include <Vector2.h>`

Public Member Functions

- Vector2 ()
  Default constructor.
- Vector2 (const double x_, const double y_, const double z_)
  Constructor.
- Vector2 (const Vector2 &v_)
  Copy constructor.
- int getMaxIndex () const
  Get max index.
- bool isDegenerate () const
  isDegenerate
- double length () const
  Get the length of the vector.
- double operator* (const Vector2 &other) const
  Scalar product.
- Vector2 operator* (double val) const
  Multiplication.
- Vector2 operator/ (double val) const
  Division.
- Vector2 & operator= (const Vector2 &other)
  Assignment operator.
- Vector2 orthogonalVector () const
  Get an orthogonal vector (CCW direction)
- void set (const double x_, const double y_, const double z_)
  Set the values.
- double sqLength () const
  Get the squared length of the vector.
- double x () const
  Get the x-value.
- double y () const
  Get the y-value.
- double z () const
  Get the z-value.

Protected Attributes

- double **valX**
- double **valY**
- double **valZ**

6.30.1 Detailed Description

This class represents a vector in 2D

6.30.2 Constructor & Destructor Documentation

6.30.2.1 Vector2() [1/2] GEOM_FADE25D::Vector2::Vector2 ( )

The vector is initialized to (0,0,0)

6.30.2.2 Vector2() [2/2] GEOM_FADE25D::Vector2::Vector2 (const Vector2 & v_)

Create a copy of vector v_

6.30.3 Member Function Documentation

6.30.3.1 getMaxIndex() int GEOM_FADE25D::Vector2::getMaxIndex ( ) const

Returns

the index of the largest component (0,1 or 2)

6.30.3.2 isDegenerate() bool GEOM_FADE25D::Vector2::isDegenerate ( ) const

Returns

true if the vector length is 0, false otherwise.

6.30.3.3 operator*() [1/2] double GEOM_FADE25D::Vector2::operator* (const Vector2 & other) const

Scalar product

6.30.3.4 operator*() [2/2] Vector2 GEOM_FADE25D::Vector2::operator* (double val) const

Multiply by a scalar value

6.30.3.5 operator/() Vector2 GEOM_FADE25D::Vector2::operator/ (double val) const

Divide by a scalar value

The documentation for this class was generated from the following file:

- Vector2.h

6.31 GEOM_FADE25D::Visualizer2 Class Reference

Visualizer2 is a PDF- and Postscript writer.

`#include <Visualizer2.h>`

Public Member Functions

- Visualizer2 (const char *filename_)

  Constructor.
- void addHeaderLine (const char *s)

  Add a header line to the visualization.
- void addObject (const Circle2 &circ, const Color &c)

  Add a Circle2 object to the visualization.
- void addObject (const Edge2 &edge, const Color &c)

  Add an Edge2 object to the visualization.
- void addObject (const Label &lab, const Color &c)

  Add a Label object to the visualization.
- void addObject (const Point2 &pnt, const Color &c)

  Add a Point2 object to the visualization.
- void addObject (const PShape &polygonalShape, const Color &c)

  Add a polygonal shape.
- void addObject (const Segment2 &seg, const Color &c)

  Add a Segment2 object to the visualization.
- void addObject (const std::vector< ConstraintSegment2 * > &vConstraintSegments, const Color &c)

  Add a vector of ConstraintSegment2 pointers to the visualization.
- void addObject (const std::vector< Edge2 > &vSegments, const Color &c)

  Add a vector of Edge2 objects to the visualization.
- void addObject (const std::vector< Point2 * > &vPoints, const Color &c)

  Add a vector of Point2 pointers to the visualization.
- void addObject (const std::vector< Point2 > &vPoints, const Color &c)

  Add a vector of Point2 objects to the visualization.
- void addObject (const std::vector< PShape > &vPolygonalShapes, const Color &c)

  Add polygonal shapes.
- void addObject (const std::vector< Segment2 > &vSegments, const Color &c)

  Add a vector of Segment2 objects to the visualization.
- void addObject (const std::vector< Triangle2 * > &vT, const Color &c)

  Add a vector of Triangle2 pointers to the visualization.
- void addObject (const std::vector< Triangle2 > &vT, const Color &c)

  Add a vector of Triangle2 objects to the visualization.
- void addObject (const std::vector< VoroCell2 * > &vC, const Color &c)

  Add a vector of Voronoi Cells to the visualization.
- void addObject (const Triangle2 &tri, const Color &c)

  Add a Triangle2 object to the visualization.
- void addObject (ConstraintGraph2 *pCG, const Color &c)

  Add a ConstraintGraph2 object to the visualization.
- void addObject (VoroCell2 *pVoroCell, const Color &c)

  Add a Voronoi cell to the visualization.
- Bbox2 computeRange (bool bWithVoronoi)

  Compute the range.
- void writeFile ()

  Finish and write the output file.

Protected Member Functions

- **Visualizer2** (const Visualizer2 &)
- void **changeColor** (const Color &c)
- void **changeColor** (float r, float g, float b, float linewidth, bool bFill)
- Visualizer2 & **operator=** (const Visualizer2 &)
- void **periodicStroke** ()
- double **scaledDouble** (const double &d)
- Point2 **scaledPoint** (const Point2 &p)
- void **writeCircle** (const Point2 &p1_, double radius, bool bFill)
- void **writeFooter** ()
- void **writeHeader** (const char *title)
- void **writeHeaderLines** ()
- void **writeLabel** (Label l)
- void **writeLine** (const Point2 &pSource, const Point2 &pTarget)
- void **writeMark** (const Point2 &p1_, float size)
- void **writePoint** (const Point2 &p1_, float size)
- void **writePolygon** (PShape &pshape, bool bFill, double width)
- void **writeTriangle** (const Point2 &p0_, const Point2 &p1_, const Point2 &p2_, bool bFill, double width)
- void **writeTriangle** (const Triangle2 *pT, bool bFill_, double width)
- void **writeVoroCell** (VoroCell2 *pVoroCell, bool bFill, double width)

Protected Attributes

- Bbox2 **bbox**
- bool **bFileClosed**
- bool **bFill**
- bool **bTypePS**
- Color **lastColor**
- std::ofstream **outFile**
- Dat * **pDat**
- int **updateCtr**
- std::vector< std::pair< Circle2, Color > > **vCircles**
- std::vector< std::pair< Label, Color > > **vLabels**
- std::vector< std::pair< Point2, Color > > **vPoints**
- std::vector< std::pair< PShape, Color > > **vPolygons**
- std::vector< std::pair< Segment2, Color > > **vSegments**
- std::vector< std::pair< Triangle2, Color > > **vTriangles**
- std::vector< std::pair< VoroCell2 *, Color > > **vVoroCells**

6.31.1 Detailed Description

See also

http://www.geom.at/example2-traversing/




Figure 31 Example output of the Visualizer

6.31.2 Constructor & Destructor Documentation

6.31.2.1 Visualizer2() `GEOM_FADE25D::Visualizer2::Visualizer2 ( const char * filename_ ) [explicit]`

Parameters

*filename_*	must end with ".ps" or ".pdf".

6.31.3 Member Function Documentation

6.31.3.1 addHeaderLine() `void GEOM_FADE25D::Visualizer2::addHeaderLine ( const char * s )`

Parameters

s	Header line as a C-string.

6.31.3.2 addObject() [1/18] `void GEOM_FADE25D::Visualizer2::addObject ( const Circle2 & circ, const Color & c )`

Parameters

circ	Circle2 object.
c	Color for the circle. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to fill the circle

6.31.3.3 addObject() [2/18] `void GEOM_FADE25D::Visualizer2::addObject (`

```
        const Edge2 & edge,
        const Color & c )
```

Parameters

edge	Edge2 object.
c	Color for the edge. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to draw marks at the endpoints.

6.31.3.4 addObject() [3/18] void GEOM_FADE25D::Visualizer2::addObject (

```
        const Label & lab,
        const Color & c )
```

Parameters

lab	Label object.
c	Color for the label.

6.31.3.5 addObject() [4/18] void GEOM_FADE25D::Visualizer2::addObject (

```
        const Point2 & pnt,
        const Color & c )
```

Parameters

pnt	Point2 object.
c	Color for the point.

6.31.3.6 addObject() [5/18] void GEOM_FADE25D::Visualizer2::addObject (

```
        const PShape & polygonalShape,
        const Color & c )
```

Parameters

polygonalShape	A single polygonal shape.
c	Color for the polygonal shapes. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to fill the shape.

6.31.3.7 addObject() [6/18] void GEOM_FADE25D::Visualizer2::addObject (

```
        const Segment2 & seg,
        const Color & c )
```

Parameters

seg	Segment2 object.
c	Color for the segment. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to draw marks at the endpoints.

6.31.3.8 addObject() [7/18] void GEOM_FADE25D::Visualizer2::addObject (

```
const std::vector< ConstraintSegment2 * > & vConstraintSegments,
const Color & c )
```

Parameters

vConstraintSegments	Vector of pointers to ConstraintSegment2 objects.
c	Color for the constraint segments. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to draw marks at the endpoints.

6.31.3.9 addObject() [8/18] void GEOM_FADE25D::Visualizer2::addObject (

```
const std::vector< Edge2 > & vSegments,
const Color & c )
```

Parameters

vSegments	Vector of Edge2 objects.
c	Color for the edges. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to draw marks at the endpoints.

6.31.3.10 addObject() [9/18] void GEOM_FADE25D::Visualizer2::addObject (

```
const std::vector< Point2 * > & vPoints,
const Color & c )
```

Parameters

vPoints	Vector of pointers to Point2 objects.
c	Color for the points.

6.31.3.11 addObject() [10/18] void GEOM_FADE25D::Visualizer2::addObject (

```
const std::vector< Point2 > & vPoints,
const Color & c )
```

Parameters

vPoints	Vector of Point2 objects.
c	Color for the points.

6.31.3.12 addObject() [11/18] void GEOM_FADE25D::Visualizer2::addObject (

```
const std::vector< PShape > & vPolygonalShapes,
const Color & c )
```

Parameters

vPolygonalShapes	Vector of polygonal shapes.

Parameters

c	Color for the polygonal shapes. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to fill the shapes.

6.31.3.13 addObject() [12/18]

```
void GEOM_FADE25D::Visualizer2::addObject (
    const std::vector< Segment2 > & vSegments,
    const Color & c )
```

Parameters

vSegments	Vector of Segment2 objects.
c	Color for the segments.

6.31.3.14 addObject() [13/18]

```
void GEOM_FADE25D::Visualizer2::addObject (
    const std::vector< Triangle2 * > & vT,
    const Color & c )
```

Parameters

vT	Vector of pointers to Triangle2 objects.
c	Color for the triangles. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to fill the triangles.

6.31.3.15 addObject() [14/18]

```
void GEOM_FADE25D::Visualizer2::addObject (
    const std::vector< Triangle2 > & vT,
    const Color & c )
```

Parameters

vT	Vector of Triangle2 objects.
c	Color for the triangles. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to fill the triangles

6.31.3.16 addObject() [15/18]

```
void GEOM_FADE25D::Visualizer2::addObject (
    const std::vector< VoroCell2 * > & vC,
    const Color & c )
```

Parameters

vC	Vector of pointers to Voronoi cells.
c	Color for the Voronoi cells. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to fill the Voronoi cells.

6.31.3.17 addObject() [16/18]

```
void GEOM_FADE25D::Visualizer2::addObject (
    const Triangle2 & tri,
    const Color & c )
```

Parameters

tri	Triangle2 object.
c	Color for the triangle. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to fill the triangle.

6.31.3.18 addObject() [17/18]

```
void GEOM_FADE25D::Visualizer2::addObject (
    ConstraintGraph2 * pCG,
    const Color & c )
```

Parameters

pCG	Pointer to a ConstraintGraph2
c	Color for the ConstraintGraph2. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to draw marks at the endpoints.

6.31.3.19 addObject() [18/18]

```
void GEOM_FADE25D::Visualizer2::addObject (
    VoroCell2 * pVoroCell,
    const Color & c )
```

Parameters

pVoroCell	Pointer to a Voronoi cell.
c	Color for the Voronoi cell. Define the Color with bFill=true, i.e., Color(CRED,0.01,true), to fill the Voronoi cell.

6.31.3.20 computeRange()

```
Bbox2 GEOM_FADE25D::Visualizer2::computeRange (
    bool bWithVoronoi )
```

Parameters

bWithVoronoi	specifies if the Voronoi cells shall be incorporated.

Returns

a bounding box of currently contained objects.

6.31.3.21 writeFile()

```
void GEOM_FADE25D::Visualizer2::writeFile ( )
```

Note

This method *must* be called at the end when all the objects have been added.

The documentation for this class was generated from the following file:

- Visualizer2.h

6.32 GEOM_FADE25D::Visualizer3 Class Reference

Visualizer3 is a 3D scene writer for the Geomview viewer.

```
#include <Visualizer3.h>
```

Public Member Functions

- **Visualizer3** (const char *name)
- void **closeFile** ()
- void **setBackfaces** (bool bWithBackfaces_)
- void **writeBall** (const Point2 &p, double radius)
- void **writeCubes** (const std::vector< Point2 > &vPoints, const char *color)
- void **writeNormals** (const std::vector< Triangle2 * > &vT, double scale)
- void **writePoint** (const Point2 &p, unsigned linewidth, const char *color)
- void **writePoints** (const std::vector< Point2 * > &vPoints, unsigned linewidth, const char *color)
- void **writePoints** (const std::vector< Point2 > &vPoints, unsigned linewidth, const char *color)
- void **writeSegment** (const Point2 &src, const Point2 &trg, const char *color, bool bWithEndPoints=false)
- void **writeSegments** (const std::vector< Edge2 > &vSegments, const char *color, bool bWithEnd↩ Points=false)
- void **writeSegments** (const std::vector< Segment2 > &vSegments, const char *color, bool bWithEnd↩ Points=false)
- void **writeTriangle** (const Point2 &p0, const Point2 &p1, const Point2 &p2, const char *color)
- void **writeTriangle** (const Triangle2 &t, const char *color)
- void **writeTriangles** (const std::vector< Point2 > &vTriangleCorners, const char *color, bool bWithNNV)
- void **writeTriangles** (const std::vector< Triangle2 * > &vT, const char *color, bool bWithNormals=false)
- void **writeVertexPairs** (const std::vector< VertexPair2 > &vVertexPairs, const char *color)

Static Public Member Functions

- static const char * **getColor** (int i)
- static const char * **getNextColor** ()
- static const char * **getNextColorAndName** (const char *&)
- static int **getNextColorNum** ()

Static Public Attributes

- static const char *const **CBLACK**
- static const char *const **CCYAN**
- static const char *const **CDARKBLUE**
- static const char *const **CDARKBROWN**
- static const char *const **CDARKORANGE**
- static const char *const **CGOLDENROD**
- static const char *const **CGRAY**
- static const char *const **CGREEN**
- static const char *const **CGREENYELLOW**
- static const char *const **CLAWNGREEN**
- static const char *const **CLIGHTBLUE**
- static const char *const **CLIGHTBROWN**
- static const char *const **CLIGHTGRAY**
- static const char *const **CLIGHTSEAGREAN**
- static const char *const **CMEDSPRINGGREEN**
- static const char *const **COLIVE**
- static const char *const **CORANGE**
- static const char *const **CPALEGREEN**
- static const char *const **CPINK**
- static const char *const **CPURPLE**
- static const char *const **CRED**
- static const char *const **CRIMSON**
- static const char *const **CSTEELBLUE**
- static const char *const **CWHEAT**
- static const char *const **CWHITE**

- static const char *const **CYELLOW**
- static const char *const **MIDNIGHTBLUE**

The documentation for this class was generated from the following file:

- Visualizer3.h

6.33 GEOM_FADE25D::VtxColor Struct Reference

Public Member Functions

- **VtxColor** (unsigned char r_, unsigned char g_, unsigned char b_, unsigned char a_)

Public Attributes

- float **a**
- float **b**
- float **g**
- float **r**

The documentation for this struct was generated from the following file:

- Point2.h

6.34 GEOM_FADE25D::Zone2 Class Reference

Zone2 is a certain defined area of a triangulation.
`#include <Zone2.h>`

Public Member Functions

- Zone2 * convertToBoundedZone ()

  Convert a zone to a bounded zone.
- void debug (const char *name="")

  Development function.
- void exportZone (FadeExport &fadeExport, bool bWithCustomIndices) const

  Export triangles from a zone.
- double getArea25D () const

  Get 2.5D Area.
- double getArea2D () const

  Get 2D Area.
- void getBorderEdges (std::vector< Edge2 > &vBorderEdgesOut) const

  Get border edges.
- void getBoundarySegments (std::vector< Segment2 > &vSegments) const

  Compute the boundary segments.
- Bbox2 getBoundingBox () const

  Compute the bounding box.
- void getComponentPolygons (std::vector< CompPolygon > &vCompPolygons) const

  Get connected components and their boundary polygons.
- ConstraintGraph2 * getConstraintGraph () const

  Get the associated constraint.
- void getConstraintGraphs (std::vector< ConstraintGraph2 * > &vConstraintGraphs_) const

  Get the associated constraint graphs.
- size_t getNumberOfTriangles () const

  Get the number of triangles.
- void getTriangles (std::vector< Triangle2 * > &vTriangles_) const

Get the triangles of the zone.

- void getVertices (std::vector< Point2 * > &vVertices_) const

  Get the vertices of the zone.
- ZoneLocation getZoneLocation () const

  Get the zone location.
- size_t numberOfConstraintGraphs () const

  Get a the number of ConstraintGraph2 objects.
- bool save (const char *filename)

  Save the zone.
- bool save (std::ostream &stream)

  Save the zone.
- void show (const char *postscriptFilename, bool bShowFull, bool bWithConstraints) const

  Postscript visualization.
- void show (Visualizer2 *pVisualizer, bool bShowFull, bool bWithConstraints) const

  Postscript visualization.
- void showGeomview (const char *filename, const char *color) const

  Geomview visualization.
- void showGeomview (Visualizer3 *pVis, const char *color) const

  Geomview visualization.
- void slopeValleyRidgeOptimization (OptimizationMode om=OPTMODE_BETTER)

  Optimize Slopes, Valleys and Ridges.
- void smoothing (int numIterations=2, bool bWithXY=true)

  Smoothing.
- void statistics (const char *s) const
- void subscribe (MsgType msgType, MsgBase *pMsg)

  Register a message receiver.
- void unifyGrid (double tolerance)
- void unsubscribe (MsgType msgType, MsgBase *pMsg)

  Unregister a message receiver.
- void writeObj (const char *outFilename) const

  *Write the zone to *.obj Writes the triangles of the present Zone2 to an *.obj file (The *.obj format represents a 3D scene).*
- bool writePly (const char *filename, bool bASCII=false) const

  *Write the zone to a *.ply file.*
- bool writePly (std::ostream &os, bool bASCII=false) const

  *Write the zone to a *.ply file.*

Protected Member Functions

- Zone2 & **operator=** (const Zone2 &)

Friends

- Zone2 * peelOffIf (Zone2 *pZone, bool bAvoidSplit, PeelPredicateTS *pPredicate)

  Peel off border triangles.
- Zone2 * peelOffIf (Zone2 *pZone, UserPredicateT *pPredicate, bool bVerbose)

  Peel off border triangles (deprecated)
- Zone2 * zoneDifference (Zone2 *pZone0, Zone2 *pZone1)

  Compute the difference of two zones.
- Zone2 * zoneIntersection (Zone2 *pZone0, Zone2 *pZone1)

  Compute the intersection of two zones.
- Zone2 * zoneSymmetricDifference (Zone2 *pZone0, Zone2 *pZone1)

  Compute the symmetric difference of two zones.
- Zone2 * zoneUnion (Zone2 *pZone0, Zone2 *pZone1)

  Compute the union of two zones.

6.34.1 Detailed Description

See also

http://www.geom.at/example4-zones-defined-areas-in-triangulations/

http://www.geom.at/boolean-operations/

createZone in the Fade2D class

6.34.2 Member Function Documentation

6.34.2.1 convertToBoundedZone() `Zone2* GEOM_FADE25D::Zone2::convertToBoundedZone ( )`

The mesh generation algorithms refine() and refineAdvanced() require a zone object that is bounded by constraint segments. This is always the case for zones with zoneLocation ZL_INSIDE but other types of zones may be unbounded. For convenience this method is provided to create a bounded zone from a possibly unbounded one.

Returns

a pointer to a new Zone2 object with zoneLocation ZL_RESULT_BOUNDED or a pointer to the present zone if this->getZoneLocation() is ZL_INSIDE.

6.34.2.2 exportZone()

```
void GEOM_FADE25D::Zone2::exportZone (
        FadeExport & fadeExport,
        bool bWithCustomIndices ) const
```

Parameters

fadeExport	is a struct that will hold the requested triangulation data
bWithCustomIndices	determines whether the custom indices of the points are also stored

6.34.2.3 getArea25D() `double GEOM_FADE25D::Zone2::getArea25D ( ) const`

Returns the 2.5D area of the zone.
Note: The getArea() method is deprecated and replaced by getArea2D() and getArea25D()

6.34.2.4 getArea2D() `double GEOM_FADE25D::Zone2::getArea2D ( ) const`

Returns the 2D area of the zone.
Note: The getArea() method is deprecated and replaced by getArea2D() and getArea25D()

6.34.2.5 getBorderEdges()

```
void GEOM_FADE25D::Zone2::getBorderEdges (
        std::vector< Edge2 > & vBorderEdgesOut ) const
```

Returns

: the CCW oriented border edges of the zone

6.34.2.6 getBoundarySegments()

```
void GEOM_FADE25D::Zone2::getBoundarySegments (
        std::vector< Segment2 > & vSegments ) const
```

Outputs the boundary segments of the zone. These are ccw-oriented but not returned in any specific order.

6.34.2.7 getComponentPolygons()

```
void GEOM_FADE25D::Zone2::getComponentPolygons (
        std::vector< CompPolygon > & vCompPolygons ) const
```

This method subdivides the zone into connected components. For each connected components it then returns a CompPolygon object consisting of the triangles, their outer boundary polygon and the hole polygons. Edges are represented by a triangle and an index and they are always counterclockwise (ccw) around their triangle. Thus the outer boundary polygon is also ccw-oriented while the polygons of inner holes are cw-oriented.

6.34.2.8 getConstraintGraph() `ConstraintGraph2* GEOM_FADE25D::Zone2::getConstraintGraph ( ) const`

Returns

a pointer to the ConstraintGraph2 object which defines the zone.
or NULL for ZL_RESULT-, ZL_GROW and ZL_GLOBAL_-zones.

6.34.2.9 getNumberOfTriangles() `size_t GEOM_FADE25D::Zone2::getNumberOfTriangles ( ) const`

Warning

This method is fast but O(n), so don't call it frequently in a loop.

6.34.2.10 getTriangles() `void GEOM_FADE25D::Zone2::getTriangles ( std::vector< Triangle2 * > & vTriangles_ ) const`

This command fetches the existing triangles of the zone.

Note

Fade_2D::void applyConstraintsAndZones() must be called after the last insertion of points and constraints.

that the lifetime of data from the Fade2D datastructures does exceed the lifetime of the Fade2D object.

6.34.2.11 getZoneLocation() `ZoneLocation GEOM_FADE25D::Zone2::getZoneLocation ( ) const`

Returns

ZL_INSIDE if the zone applies to the triangles inside one or more ConstraintGraph2 objects
ZL_OUTSIDE if the zone applies to the outside triangles
ZL_GLOBAL if the zone applies (dynamically) to all triangles
ZL_RESULT if the zone is the result of a set operation
ZL_GROW if the zone is specified by a set of constraint graphs and an inner point




Figure 32 An ouside zone and in inside zone

6.34.2.12 numberOfConstraintGraphs() `size_t GEOM_FADE25D::Zone2::numberOfConstraintGraphs ( ) const`

A Zone2 object might be defined by zero, one or more ConstraintGraph2 objects.

6.34.2.13 save() [1/2] `bool GEOM_FADE25D::Zone2::save ( const char * filename )`

This command saves the present Zone2 to a binary file. Any constraint edges and custom indices in the domain are retained.

Parameters

in	*filename*	is the output filename

Returns

whether the operation was successful

Note

A Delaunay triangulation is convex without holes but this may not hold for the zone to be saved. Thus extra triangles may be saved to fill concavities. These extra-triangles will belong to the Fade_2D instance but not to the Zone2 object when reloaded.

See also

save(std::ostream& stream). Use the similar command Fade_2D::saveZones(const char* file, std::vector<Zone2*>& vZones) to store more than just one zone. Use Fade_2D::saveTriangulation() to store all triangles of the triangulation plus any specified zones. Use Fade_2D::load() to reload the data from such files.

6.34.2.14 save() [2/2] `bool GEOM_FADE25D::Zone2::save ( std::ostream & stream )`

This command saves the present Zone2 to an ostream. Any constraint edges and custom indices in the domain are retained.

Parameters

stream	is the output stream

Returns

whether the operation was successful

Note

A Delaunay triangulation is convex without holes but this may not hold for the zone to be saved. Thus extra triangles may be saved to fill concavities. These extra-triangles will belong to the Fade_2D instance but not to the Zone2 object when reloaded.

See also

Use the similar command Fade_2D::saveZones(const char* file, std::vector<Zone2*>& vZones) to store more than just one zone. Use Fade_2D::saveTriangulation() to store all triangles of the triangulation plus any specified zones. Use Fade_2D::load() to reload the data from such files.

6.34.2.15 show() [1/2]

```
void GEOM_FADE25D::Zone2::show (
    const char * postscriptFilename,
    bool bShowFull,
    bool bWithConstraints ) const
```

Parameters

postscriptFilename	is the name of the output file.
bShowFull	specifies if only the zone or the full triangulation shall be drawn
bWithConstraints	specifies if constraint edges shall be drawn

6.34.2.16 show() [2/2]

```
void GEOM_FADE25D::Zone2::show (
    Visualizer2 * pVisualizer,
    bool bShowFull,
    bool bWithConstraints ) const
```

Parameters

pVisualizer	is a pointer to an existing Visualizer2 object.

Note

You must call pVisualizer->writeFile() before program end

Parameters

bShowFull	specifies if only the zone or the full triangulation shall be drawn
bWithConstraints	specifies if constraint edges shall be drawn

6.34.2.17 showGeomview() [1/2]

```
void GEOM_FADE25D::Zone2::showGeomview (
    const char * filename,
    const char * color ) const
```

Parameters

filename	is the name of the output file.
color	is a string ("red green blue alpha"), e.g., "1.0 0.0 0.0 1.0"*

6.34.2.18 showGeomview() [2/2]

```
void GEOM_FADE25D::Zone2::showGeomview (
    Visualizer3 * pVis,
    const char * color ) const
```

Parameters

pVis	points to a Visualizer3 object
color	is a string ("red green blue alpha"), e.g., "1.0 0.0 0.0 1.0"*

6.34.2.19 slopeValleyRidgeOptimization()

```
void GEOM_FADE25D::Zone2::slopeValleyRidgeOptimization (
        OptimizationMode om = OPTMODE_BETTER )
```

A pure Delaunay triangulation takes only the x and y coordinates into account. However, for terrain scans, it is important to consider the z coordinate as well, otherwise ridges, valleys and rivers will look unnatural. This method leaves the points constant, but uses edge flips to change the connectivity, making the surface smoother overall.

Parameters

om	is the optimization mode: OPTMODE_NORMAL is the fastest. OPTMODE_BETTER provides significantly better results while still taking a moderate amount of time. OPTMODE_BEST delivers the best results, but also has a significantly higher time requirement. This method supports the progress-bar mechanism.

Note

Flipping edges makes the triangulation non-delaunay, i.e. the empty-circle-property is then no longer given. Improving the smoothness of the surface by edge flips also means degrading the interior angles of the triangles (to a certain degree).

6.34.2.20 smoothing()

```
void GEOM_FADE25D::Zone2::smoothing (
        int numIterations = 2,
        bool bWithXY = true )
```

Weighted laplacian smoothing for the z-coordinate of all zone vertices. The x and y coordinates can also be optimized but only for vertices not belonging to the boundary of the zone or to constraint edges. This method is very fast but does nevertheless support the progress bar mechanism.

Parameters

numIterations	is the number of smoothing passes.
bWithXY	specifies if the x and y coordinates are also adapted.

6.34.2.21 statistics()

```
void GEOM_FADE25D::Zone2::statistics (
        const char * s ) const
```

Statistics
Prints statistics to stdout.

6.34.2.22 subscribe()

```
void GEOM_FADE25D::Zone2::subscribe (
        MsgType msgType,
        MsgBase * pMsg )
```

Parameters

msgType	is the type of message the subscriber shall receive, e.g. MSG_PROGRESS or MSG_WARNING
pMsg	is a pointer to a custom class derived from MsgBase

6.34.2.23 unifyGrid()

```
void GEOM_FADE25D::Zone2::unifyGrid (
        double tolerance )
```

Unify Grid
A Delaunay triangulation is not unique when when 2 or more triangles lie on a common circle. As a consequence

the four corners of a rectangle can be triangulated in two different ways: Either the diagonal proceeds from the lower left to the upper right corner or it connects the other two corners. Both solutions are valid and an arbitrary one is applied when points are triangulated. To improve the repeatability and for reasons of visual appearance this method unifies such diagonals to point from the lower left to the upper right corner (or in horizontal direction).

Parameters

tolerance	is 0 when only exact cases of more than 3 points on a common circumcircle shall be changed. But in practice input data can be disturbed by noise and tiny rounding errors such that grid points are not exactly on a grid. The numeric error is computed as $error = \frac{abs(diagonalA - diagonalB)}{max(diagonalA, diagonalB)}$. and `tolerance` is an upper threshold to allow modification despite such tiny inaccuracies. Use with caution, such flips break the empty circle property and this may or may not fit your setting.

6.34.2.24 unsubscribe()

```
void GEOM_FADE25D::Zone2::unsubscribe (
    MsgType msgType,
    MsgBase * pMsg )
```

Parameters

msgType	is the type of message the subscriber shall not receive anymore
pMsg	is a pointer to a custom class derived from MsgBase

6.34.2.25 writeObj()

```
void GEOM_FADE25D::Zone2::writeObj (
    const char * outFilename ) const
```

Parameters

outFilename	is the output filename

6.34.2.26 writePly() [1/2]

```
bool GEOM_FADE25D::Zone2::writePly (
    const char * filename,
    bool bASCII = false ) const
```

Parameters

filename	is the output filename
bASCII	specifies whether to write the $*$.ply in ASCII or binary format

Note

Method available for platforms with C++11

6.34.2.27 writePly() [2/2]

```
bool GEOM_FADE25D::Zone2::writePly (
    std::ostream & os,
    bool bASCII = false ) const
```

Parameters

os	is the output file

Parameters

bASCII	specifies whether to write the ∗.ply in ASCII or binary format

Note

Method available for platforms with C++11

6.34.3 Friends And Related Function Documentation

6.34.3.1 peelOffIf [1/2]

```
Zone2* peelOffIf (
        Zone2 * pZone,
        bool bAvoidSplit,
        PeelPredicateTS * pPredicate )  [friend]
```

Parameters

pZone	is the input zone
bAvoidSplit	if true, then the algorithm removes a triangle only if it does not break the zone into independent components.
pPredicate	is a user-defined predicate that decides if a triangle shall be removed.

Returns

a new zone containing a subset of the triangles of `pZone` or NULL when no triangles remain.

Attention

Check whether NULL is returned!

6.34.3.2 peelOffIf [2/2]

```
Zone2* peelOffIf (
        Zone2 * pZone,
        UserPredicateT * pPredicate,
        bool bVerbose )  [friend]
```

This function is DEPRECATED but kept for backwards compatibility. The new and better function is↩ : peelOffIf(Zone2∗ pZone, bool bAvoidSplit,PeelPredicateTS∗ pPredicate)

Parameters

pZone	
pPredicate	
bVerbose	

Returns

a new zone containing a subset of the triangles of `pZone` or NULL when no triangles remain.

6.34.3.3 zoneDifference

```
Zone2* zoneDifference (
        Zone2 * pZone0,
        Zone2 * pZone1 )  [friend]
```

Returns

a new zone containing the triangles of ∗pZone0 minus the ones of ∗pZone1

Note

pZone0 and pZone1 must belong to the same Fade_2D object.

6.34.3.4 zoneIntersection

```
Zone2* zoneIntersection (
        Zone2 * pZone0,
        Zone2 * pZone1 )  [friend]
```

Returns

a new zone containing the intersection of ∗pZone0 and ∗pZone1

Note

pZone0 and pZone1 must belong to the same Fade_2D object.

6.34.3.5 zoneSymmetricDifference

```
Zone2* zoneSymmetricDifference (
        Zone2 * pZone0,
        Zone2 * pZone1 )  [friend]
```

Returns

a new zone containing the triangles that are present in one of the zones but not in the other one.

Note

pZone0 and pZone1 must belong to the same Fade_2D object.

6.34.3.6 zoneUnion

```
Zone2* zoneUnion (
        Zone2 * pZone0,
        Zone2 * pZone1 )  [friend]
```

Returns

a new zone containing the union of the triangles of ∗pZone0 and ∗pZone1

Note

pZone0 and pZone1 must belong to the same Fade_2D object.

The documentation for this class was generated from the following file:

- Zone2.h

7 File Documentation

7.1 Bbox2.h File Reference

```
#include "Segment2.h"
#include "common.h"
```

Classes

- class GEOM_FADE25D::Bbox2

  Bbox2 is an axis aligned 2D bounding box.

Functions

- Bbox2 GEOM_FADE25D::getBox (std::vector< Point2 * > &vP)

  Compute the bounding box.
- Bbox2 GEOM_FADE25D::getBox (std::vector< Point2 > &vP)

  Compute the bounding box.
- std::ostream & GEOM_FADE25D::operator<< (std::ostream &stream, const Bbox2 &pC)

  Print the box.

7.1.1 Function Documentation

7.1.1.1 getBox() [1/2]

```
Bbox2 GEOM_FADE25D::getBox (
        std::vector< Point2 * > & vP )
```

Computes the bounding box of points

7.1.1.2 getBox() [2/2]

```
Bbox2 GEOM_FADE25D::getBox (
        std::vector< Point2 > & vP )
```

Computes the bounding box of points

7.1.1.3 operator<<()

```
std::ostream& GEOM_FADE25D::operator<< (
        std::ostream & stream,
        const Bbox2 & pC )  [inline]
```

Prints the box coordinates to `stream`

7.2 CAF_Component.h File Reference

```
#include <map>
#include "common.h"
#include "Segment2.h"
```

Classes

- class GEOM_FADE25D::CAF_Component

  CAF_Component stands for CUT AND FILL COMPONENT. It represents a connected area of the surface.

Enumerations

- enum GEOM_FADE25D::CAFTYP { GEOM_FADE25D::CT_NULL , GEOM_FADE25D::CT_CUT , GEOM_FADE25D::CT_FILL }

Functions

- std::ostream & GEOM_FADE25D::operator<< (std::ostream &stream, const CAF_Component &c)

7.2.1 Enumeration Type Documentation

7.2.1.1 CAFTYP

```
enum GEOM_FADE25D::CAFTYP
```

enumerates the three possible Cut-And-Fill types

Enumerator

CT_NULL	the first surface corresponds to the second one
CT_CUT	the first surface is above the second one
CT_FILL	the first surface is below the second one

7.2.2 Function Documentation

7.2.2.1 operator<<() `std::ostream& GEOM_FADE25D::operator<< ( std::ostream & stream, const CAF_Component & c ) [inline]`

Report

7.3 Circle2.h File Reference

```
#include "Point2.h"
#include "common.h"
```

Classes

- class GEOM_FADE25D::Circle2

  Circle for visualization.

7.4 CloudPrepare.h File Reference

```
#include "common.h"
#include "Point2.h"
```

Classes

- class GEOM_FADE25D::CloudPrepare

  CloudPrepare simplifies overdense point clouds and helps to avoid memory-usage-peaks during data transfer.

Enumerations

- enum GEOM_FADE25D::ConvexHullStrategy { GEOM_FADE25D::CHS_NOHULL , GEOM_FADE25D::CHS_MAXHULL , GEOM_FADE25D::CHS_MINHULL }

  ConvexHullStrategy for CloudPrepare.
- enum GEOM_FADE25D::SumStrategy { GEOM_FADE25D::SMS_MINIMUM , GEOM_FADE25D::SMS_MAXIMUM , GEOM_FADE25D::SMS_MEDIAN , GEOM_FADE25D::SMS_AVERAGE }

  SumStrategy for CloudPrepare.

7.4.1 Enumeration Type Documentation

7.4.1.1 ConvexHullStrategy `enum GEOM_FADE25D::ConvexHullStrategy`

Enumerator

CHS_NOHULL	No special treatment for convex hull points.
CHS_MAXHULL	Use all points from the convex hull.
CHS_MINHULL	Use only convex points of the convex hull (no collinear ones)

7.4.1.2 SumStrategy `enum GEOM_FADE25D::SumStrategy`

Enumerator

SMS_MINIMUM	Assign the minimum height.
SMS_MAXIMUM	Assign the maximum height.
SMS_MEDIAN	Assign the median height.
SMS_AVERAGE	Assign the average height.

7.5 Color.h File Reference

```
#include "common.h"
```

Classes

- class GEOM_FADE25D::Color

  Color for visualization.

Enumerations

- enum GEOM_FADE25D::Colorname {
  CRED , **CGREEN** , **CBLUE** , **CBLACK** ,
  CPINK , **CGRAY** , **CORANGE** , **CLIGHTBLUE** ,
  CLIGHTBROWN , **CDARKBROWN** , **CPURPLE** , **COLIVE** ,
  CLAWNGREEN , **CPALEGREEN** , **CCYAN** , **CYELLOW** ,
  CWHITE }

  Predefined colors for convenience.

Functions

- std::ostream & **GEOM_FADE25D::operator**<< (std::ostream &stream, const Color &c)

7.6 ConstraintGraph2.h File Reference

```
#include "Segment2.h"
#include "ConstraintSegment2.h"
#include "Edge2.h"
#include <map>
#include "common.h"
```

Classes

- class GEOM_FADE25D::ConstraintGraph2

  ConstraintGraph2 is a set of Constraint Edges (ConstraintSegment2)

7.7 ConstraintSegment2.h File Reference

```
#include <set>
#include "common.h"
```

Classes

- class GEOM_FADE25D::ConstraintSegment2

  A ConstraintSegment2 represents a Constraint Edge.

Enumerations

- enum GEOM_FADE25D::ConstraintInsertionStrategy {
  GEOM_FADE25D::CIS_CONFORMING_DELAUNAY =0 , GEOM_FADE25D::CIS_CONSTRAINED_DELAUNAY
  =1 , GEOM_FADE25D::CIS_CONFORMING_DELAUNAY_SEGMENT_LEVEL =2 , GEOM_FADE25D::CIS_KEEP_DELAUNAY
  =0 ,
  GEOM_FADE25D::CIS_IGNORE_DELAUNAY =1 }

  Constraint Insertion Strategy determines how a constraint edge shall be inserted:

7.7.1 Enumeration Type Documentation

7.7.1.1 ConstraintInsertionStrategy `enum GEOM_FADE25D::ConstraintInsertionStrategy`

- CIS_CONSTRAINED_DELAUNAY inserts a segment without subdivision unless required (which is the case if existing vertices or constraint segments are crossed).

All other constraint insertion strategies are deprecated and only kept for backwards compatibility. Their behavior can be achieved using ConstraintGraph2::makeDelaunay() and/or Fade_2D::drape(). See also `examples_25D/terrain.cpp`.

Note

In former library versions the terms CIS_IGNORE_DELAUNAY and CIS_KEEP_DELAUNAY were used but these were misleading and are now deprecated. For backwards compatibility they are kept.

Enumerator

CIS_CONFORMING_DELAUNAY	Deprecated.
CIS_CONSTRAINED_DELAUNAY	The recommended insertion strategy.
CIS_CONFORMING_DELAUNAY_SEGMENT_LEVEL	Deprecated.
CIS_KEEP_DELAUNAY	Deprecated name.
CIS_IGNORE_DELAUNAY	Deprecated.

7.8 CutAndFill.h File Reference

```
#include "common.h"
#include "MsgBase.h"
#include "CAF_Component.h"
```

Classes

- class GEOM_FADE25D::CutAndFill

  CutAndFill computes the volume(s) between two overlapping surfaces.

7.9 Edge2.h File Reference

```
#include "common.h"
```

Classes

- class GEOM_FADE25D::Edge2

  Edge2 is a directed edge.
- struct GEOM_FADE25D::Func_gtEdge2D

  Functor to sort edges by 2d length (descending)
- struct GEOM_FADE25D::Func_ltEdge25D

  Functor to sort edges by 2.5d length (ascending)
- struct GEOM_FADE25D::Func_ltEdge2D

  Functor to sort edges by 2d length (ascending)

Functions

- bool **GEOM_FADE25D::sameEdge** (const Edge2 &eA, const Edge2 &eB)

7.10 EfficientModel.h File Reference

```
#include "common.h"
#include "Point2.h"
```

Classes

- class GEOM_FADE25D::EfficientModel

  EfficientModel (DEPRECATED in favor of the new CloudPrepare class)

Enumerations

- enum SmoothingStrategy { SMST_MINIMUM , SMST_MAXIMUM , SMST_MEDIAN , SMST_AVERAGE }

7.10.1 Enumeration Type Documentation

7.10.1.1 SmoothingStrategy `enum SmoothingStrategy`

Enumerator

SMST_MINIMUM	Assign the minimum height.
SMST_MAXIMUM	Assign the maximum height.
SMST_MEDIAN	Assign the median height.
SMST_AVERAGE	Assign the average height.

7.11 Fade_2D.h File Reference

```
#include "common.h"
#include "freeFunctions.h"
#include "License.h"
#include "Point2.h"
#include "Triangle2.h"
#include "TriangleAroundVertexIterator.h"
#include "Visualizer2.h"
#include "Zone2.h"
#include "ConstraintGraph2.h"
#include "Performance.h"
#include "MeshGenParams.h"
```

```
#include "MsgBase.h"
#include "SegmentChecker.h"
#include "testDataGenerators.h"
#include "FadeExport.h"
#include "Voronoi2.h"
#include "IsoContours.h"
#include "EfficientModel.h"
#include "CutAndFill.h"
#include "CloudPrepare.h"
```

Classes

- class GEOM_FADE25D::Fade_2D

  Fade_2D is the Delaunay triangulation class.

Functions

- void GEOM_FADE25D::copyFade (Fade_2D &dt0, std::vector< Zone2 * > &vZones0, Fade_2D &dt1, std::vector< Zone2 * > &vZones1)

  Copy a Fade_2D object and selected Zone2 objects.

7.11.1 Detailed Description

Fade_2D.h is the main API file of the Fade library

7.11.2 Function Documentation

7.11.2.1 copyFade()

```
void GEOM_FADE25D::copyFade (
    Fade_2D & dt0,
    std::vector< Zone2 * > & vZones0,
    Fade_2D & dt1,
    std::vector< Zone2 * > & vZones1 )  [inline]
```

Parameters

in	*dt0*	is the source triangulation
out	*dt1*	is the target triangulation
in	*vZones0*	(possibly empty) contains the source zones
out	*vZones1*	returns the target zones in the same order

7.12 FadeExport.h File Reference

```
#include <vector>
#include <algorithm>
#include "common.h"
```

Classes

- struct GEOM_FADE25D::FadeExport

  FadeExport is a simple struct to export triangulation data.

7.13 freeFunctions.h File Reference

```
#include "Point2.h"
#include "Segment2.h"
#include "Edge2.h"
#include <vector>
```

Functions

- void GEOM_FADE25D::edgesToPolygons (const std::vector< Edge2 > &vEdgesIn, std::vector< std::vector< Edge2 > > &vvPolygonsOut, std::vector< Edge2 > &vRemainingOut)

  Create polygons from a set of edges.
- bool GEOM_FADE25D::fillHole (const std::vector< Point2 > &vMeshCorners, const std::vector< Segment2 > &vPolygonSegments, bool bWithRefine, bool bVerbose, std::vector< Point2 > &vCornersOut)

  Fill a hole in a 3D mesh with triangles (deprecated)
- bool GEOM_FADE25D::fillHole (const std::vector< std::pair< Segment2, Vector2 > > &vPolygonSegments, bool bWithRefine, bool bVerbose, std::vector< Point2 > &vCornersOut)

  Fill a hole in a 3D mesh with triangles (deprecated)
- bool GEOM_FADE25D::fillHole (Mesh3 *pMesh, const std::vector< Edge2 > &vPolygonEdges, bool bWithRefine, bool bVerbose, std::vector< Point2 > &vCornersOut)

  Fill a hole in a 3D mesh with triangles (deprecated)
- double GEOM_FADE25D::getArea25D (const Point2 *p0, const Point2 *p1, const Point2 *p2)

  Get 2.5D area of a triangle.
- double GEOM_FADE25D::getArea2D (const Point2 *p0, const Point2 *p1, const Point2 *p2)

  Get 2D area of a triangle.
- void GEOM_FADE25D::getBorders (const std::vector< Triangle2 * > &vT, std::vector< Segment2 > &vBorderSegmentsOut)

  Get Borders.
- void GEOM_FADE25D::getConnectedComponents (const std::vector< Triangle2 * > &vT, std::vector< std::vector< Triangle2 * > > &vvT)

  Get connected components.
- void GEOM_FADE25D::getDirectedEdges (const std::vector< Triangle2 * > &vT, std::vector< Edge2 > &vDirectedEdgesOut)

  Get directed edges The directed edges of `vT` are returned in `vDirectedEdgesOut`. Directed means that each edge (a,b) with two adjacent triangles in vT is returned twice, as edge(a,b) and edge(b,a).
- const char * GEOM_FADE25D::getFade2DVersion ()

  Get the Fade2D version string.
- int GEOM_FADE25D::getGlobalNumCPU ()

  Get the global number of threads to be used.
- int GEOM_FADE25D::getMajorVersionNumber ()

  Get the major version number.
- int GEOM_FADE25D::getMinorVersionNumber ()

  Get the minor version number.
- Vector2 GEOM_FADE25D::getNormalVector (const Point2 &p0, const Point2 &p1, const Point2 &p2, bool &bOK)

  Get normal vector.
- Orientation2 GEOM_FADE25D::getOrientation2 (const Point2 *p0, const Point2 *p1, const Point2 *p2)

  Get the orientation of three points.
- Orientation2 GEOM_FADE25D::getOrientation2_mt (const Point2 *p0, const Point2 *p1, const Point2 *p2)

  Get Orientation2 (MT)
- int GEOM_FADE25D::getRevisionNumber ()

  Get the revision version number.

- void GEOM_FADE25D::getSortedBoundaryPolygons (std::vector< Triangle2 * > &vConnectedComponent, std::vector< Edge2 > &vOutsidePolygon, std::vector< std::vector< Edge2 > > &vHolePolygons)

  Get sorted boundary polygons.
- void GEOM_FADE25D::getUndirectedEdges (const std::vector< Triangle2 * > &vT, std::vector< Edge2 > &vUndirectedEdgesOut)

  Get undirected edges.
- bool GEOM_FADE25D::isRelease ()

  Check if a RELEASE or a DEBUG version is used.
- bool GEOM_FADE25D::isSimplePolygon (std::vector< Segment2 > &vSegments)

  isSimplePolygon
- void GEOM_FADE25D::offsetPolygonPoints (double offset, const std::vector< Point2 > &vOrgPoints, std::vector< Point2 > &vOffsetPoints, double maxCorrectionFactor=1.0)

  Create an offet polygon.
- void GEOM_FADE25D::pointsToPolyline (std::vector< Point2 > &vInPoints, bool bClose, std::vector< Segment2 > &vOutSegments)

  Points-to-Polyline.
- bool GEOM_FADE25D::readPointsBIN (const char *filename, std::vector< Point2 > &vPointsIn, bool bWithHeader=true)

  Read points from a binary file.
- bool GEOM_FADE25D::readPointsPLY (const char *filename, bool bUniquePoints, std::vector< Point2 > &vPoints, std::vector< VtxColor > *pVertexColors=NULL)

  *Read points from a *.PLY file.*
- bool GEOM_FADE25D::readPointsPLY (std::istream &is, bool bUniquePoints, std::vector< Point2 > &vPoints, std::vector< VtxColor > *pVertexColors=NULL)

  *Read points from a *.PLY file.*
- bool GEOM_FADE25D::readSegmentsBIN (const char *filename, std::vector< Segment2 > &vSegmentsOut)

  Read segments from a binary file.
- bool GEOM_FADE25D::readXY (const char *filename, std::vector< Point2 > &vPointsOut)

  Read (x y) points.
- bool GEOM_FADE25D::readXYZ (const char *filename, std::vector< Point2 > &vPointsOut)

  Read (x y z) points.
- int GEOM_FADE25D::setGlobalNumCPU (int numCPU)

  Set the global number of threads to be used.
- bool GEOM_FADE25D::sortRing (std::vector< Segment2 > &vRing)

  Sort a vector of Segments.
- bool GEOM_FADE25D::sortRingCCW (std::vector< Segment2 > &vRing)

  Sort a vector of Segments.
- void GEOM_FADE25D::untwistPolygon (std::vector< Segment2 > &vPolygon, std::vector< std::vector< Segment2 > > &vvPolygon)

  Repair a selfintersecting polygon.
- bool GEOM_FADE25D::writePointsASCII (const char *filename, const std::vector< Point2 * > &vPointsIn)

  Write points to an ASCII file.
- bool GEOM_FADE25D::writePointsASCII (const char *filename, const std::vector< Point2 > &vPointsIn)

  Write points to an ASCII file.
- bool GEOM_FADE25D::writePointsBIN (const char *filename, std::vector< Point2 * > &vPoints)

  Write points to a binary file.
- bool GEOM_FADE25D::writePointsBIN (const char *filename, std::vector< Point2 > &vPoints)

  Write points to a binary file.
- bool GEOM_FADE25D::writePointsPLY (const char *filename, std::vector< Point2 * > &vPoints, bool bASCII)

  *Write points to a *.PLY file.*

- bool GEOM_FADE25D::writePointsPLY (std::ostream &os, std::vector< Point2 * > &vPoints, bool bASCII)

  *Write points to a *.PLY file.*
- bool GEOM_FADE25D::writeSegmentsBIN (const char *filename, std::vector< Segment2 > &vSegmentsIn)

  Write segments to a binary file.

7.13.1 Function Documentation

7.13.1.1 getGlobalNumCPU() `int GEOM_FADE25D::getGlobalNumCPU ( )`

Note

Fade is by default *single-threaded* to avoid nested multithreading when Fade runs in multiple threads of your application but you can change the number of threads using setGlobalNumCPU()

7.13.1.2 getSortedBoundaryPolygons()

```
void GEOM_FADE25D::getSortedBoundaryPolygons (
    std::vector< Triangle2 * > & vConnectedComponent,
    std::vector< Edge2 > & vOutsidePolygon,
    std::vector< std::vector< Edge2 > > & vHolePolygons )
```

This function takes ONE connected component of triangles. It returns the outer polygon as well as the inner hole polygons if any.

Parameters

in	*vConnectedComponent*	is a connected component of triangles where the term "connected" means adjacency on edges. It is important that just one connected component is passed!
out	*vOutsidePolygon*	is the outside boundary of the connected component.
out	*vHolePolygons*	contains the hole polygons (if any)

Edges in output polygons are sorted and CCW-oriented with respect to their triangle. Thus the outer polygon is always CCW oriented and holes are always CW oriented. This is sometimes a useful property.

Attention

Pass only one connected component.

7.13.1.3 offsetPolygonPoints()

```
void GEOM_FADE25D::offsetPolygonPoints (
    double offset,
    const std::vector< Point2 > & vOrgPoints,
    std::vector< Point2 > & vOffsetPoints,
    double maxCorrectionFactor = 1.0 )
```




Figure 33 Offset polygon without angle correction




Figure 34 Offset polygon with angle correction factor 1.414 (down to 90 degrees)




Figure 35 Offset polygon with angle correction factor 6.25 (for angles as low as 18.4 degrees)

Parameters

	offset	specifies the offset distance (positive or negative)
`in`	*vOrgPoints*	are ordered points of a *counterclockwise* polygon (no point repeated)
`out`	*vOffsetPoints*	returns points moved outside/inside by a positive/negative offset distance (times the angle correction factor)
`in`	*maxCorrectionFactor*	is the maximum angle correction factor that may be applied to the `offset` value. It's default value is 1.0 (no angle correction), lower values are ignored. The angle that can be corrected with a certain maxCorrectionFactor is computed according to $2 * asin(1.0/maxCorrectionFactor)$. This means, a maxCorrectionFactor=1.4143 can account for angles down to 90 degrees while 2.6132 is required to correct angles as low as 45 degrees.

Warning

An offset polygon can selfintersect!

7.13.1.4 setGlobalNumCPU() `int GEOM_FADE25D::setGlobalNumCPU ( int numCPU )`

Parameters

numCPU	is the number of CPU cores to be used and is 0 (means autodetect) or greater.

Returns

the number of CPU cores that will be used

Note

Fade is by default *single-threaded* to avoid nested multithreading when Fade runs in multiple threads of your application.

Characteristics:

- For technical reasons you should insert points into a triangulation before you insert constraint segments. Then the algorithm can fully benefit from multithreading.
- Fade continues support for very old compilers but multithreading is not available for VS2010 and CentOS6.4 library versions.

7.13.1.5 untwistPolygon()

```
void GEOM_FADE25D::untwistPolygon (
        std::vector< Segment2 > & vPolygon,
        std::vector< std::vector< Segment2 > > & vvPolygon )
```

Parameters

vPolygon	[in] The input polygon, no specific order and orientation
vvPolygon	[out] One or more output polygons, free of selfintersections, counterclockwise oriented

7.14 IsoContours.h File Reference

```
#include "Segment2.h"
#include <map>
#include "common.h"
```

Classes

- class GEOM_FADE25D::IsoContours

  IsoContours uses a fast datastructure to compute intersections of horizontal planes with a given list of triangles.

7.15 Label.h File Reference

```
#include "Point2.h"
#include "common.h"
```

Classes

- class GEOM_FADE25D::Label

  Label is a Text-Label for Visualization.

7.16 MeshGenParams.h File Reference

```
#include "common.h"
#include "Vector2.h"
#include "Point2.h"
```

Classes

- class GEOM_FADE25D::MeshGenParams

  Parameters for the mesh generator.

Functions

- template<typename T >
  void GEOM_FADE25D::unusedParameter (const T &)

  Unused parameter.

7.16.1 Function Documentation

7.16.1.1 unusedParameter() `template<typename T >`

```
void GEOM_FADE25D::unusedParameter (
            const T &  )  [inline]
```

Empty template to avoid compiler warnings about unused function parameters

7.17 MsgBase.h File Reference

```
#include "common.h"
```

Classes

- class GEOM_FADE25D::MsgBase

  MsgBase, a base class for message subscriber classes.

Enumerations

- enum **MsgType** { **MSG_PROGRESS** , **MSG_WARNING** }

7.18 Performance.h File Reference

```
#include "common.h"
```

Functions

- double GEOM_FADE25D::timer (const char *cstr)

  Timer.

7.18.1 Function Documentation

7.18.1.1 timer() `double GEOM_FADE25D::timer (`

```
            const char * cstr )
```

Call the timer function with a certain string to start time measurement. Call it a second time with the same string to finish the time measurement.

Returns

-1 when the timer is started or the elapsed time in seconds when the timer is stopped.

7.19 Point2.h File Reference

```
#include "common.h"
#include "Vector2.h"
#include <cstring>
```

Classes

- struct GEOM_FADE25D::Func_ltPointXYZ

  Functor to sort points lexicographically.
- class GEOM_FADE25D::Point2

  Point.
- struct GEOM_FADE25D::VtxColor

Functions

- Point2 GEOM_FADE25D::center (const Point2 &p0, const Point2 &p1)

  Compute the midpoint of p0 and p1.
- Point2 GEOM_FADE25D::centerWithShift (const Point2 &p0, const Point2 &p1)

  Compute the midpoint of p0 and p1 and adapt it.
- std::ostream & GEOM_FADE25D::operator<< (std::ostream &stream, const Point2 &pnt)

  Print to stream.
- std::istream & GEOM_FADE25D::operator>> (std::istream &stream, Point2 &pnt)

  Stream-to-Point.
- double GEOM_FADE25D::sqDistance25D (const double x0, const double y0, const double z0, const Point2 &p1)

  Get the squared distance between two points in 2D.
- double GEOM_FADE25D::sqDistance25D (const Point2 &p0, const Point2 &p1)

  Get the squared distance between two points.
- double GEOM_FADE25D::sqDistance2D (const double x0, const double y0, const Point2 &p1)

  Get the squared distance between two points in 2D.
- double GEOM_FADE25D::sqDistance2D (const Point2 &p0, const Point2 &p1)

  Get the squared distance between two points in 2D.

7.19.1 Function Documentation

7.19.1.1 center()

```
Point2 GEOM_FADE25D::center (
        const Point2 & p0,
        const Point2 & p1 )  [inline]
```

Note

: The exact midpoint of p0 and p1 may not exist in floating point numbers. Thus the returned point may not be collinear with p0 and p1.

7.19.1.2 centerWithShift()

```
Point2 GEOM_FADE25D::centerWithShift (
        const Point2 & p0,
        const Point2 & p1 )
```

Experimental new function that may change in the future. Thought for specific applications.
This function works like center() but additionally it adapts the midpoint to the segment (p0,p1) such that it is 'as collinear as possible' with p0 and p1 in the x/y plane. Bounds for the shift are 0.01 and 1 % of the range in x- and y-direction.

7.19.1.3 sqDistance25D() [1/2]

```
double GEOM_FADE25D::sqDistance25D (
        const double x0,
        const double y0,
        const double z0,
        const Point2 & p1 )  [inline]
```

Note

In contrast to sqDistance2D this method uses also the z-coordinate of the points

7.19.1.4 sqDistance25D() [2/2]

```
double GEOM_FADE25D::sqDistance25D (
        const Point2 & p0,
        const Point2 & p1 )  [inline]
```

Note

In contrast to sqDistance2D this method uses also the z-coordinate of the points

7.19.1.5 sqDistance2D() [1/2]

```
double GEOM_FADE25D::sqDistance2D (
        const double x0,
        const double y0,
        const Point2 & p1 )  [inline]
```

Note

This method does not use the z-coordinate

7.19.1.6 sqDistance2D() [2/2]

```
double GEOM_FADE25D::sqDistance2D (
        const Point2 & p0,
        const Point2 & p1 )  [inline]
```

Note

This method does not use the z-coordinate

7.20 PShape.h File Reference

```
#include "Point2.h"
#include "common.h"
```

Classes

- class GEOM_FADE25D::PShape

  Polygonal Shape for Visualization.

7.21 Segment2.h File Reference

```
#include "Point2.h"
#include "common.h"
```

Classes

- class GEOM_FADE25D::Segment2

  Segment.

7.22 SegmentChecker.h File Reference

```
#include <map>
#include "common.h"
#include "License.h"
#include "Segment2.h"
#include "MsgBase.h"
#include "Bbox2.h"
```

Classes

- class GEOM_FADE25D::SegmentChecker

  SegmentChecker identifies intersecting line segments.

Enumerations

- enum ClipResult {
  CR_INVALID , CR_EMPTY , CR_CLIPPED_DEGENERATE , CR_CLIPPED_NONDEGENERATE ,
  CR_COMPLETE_DEGENERATE , CR_COMPLETE_NONDEGENERATE }
- enum SegmentIntersectionType {
  SIT_UNINITIALIZED , SIT_NONE , SIT_SEGMENT , SIT_POINT ,
  SIT_ENDPOINT }

7.22.1 Enumeration Type Documentation

7.22.1.1 ClipResult `enum ClipResult`

Enumerator

CR_INVALID	Can't compute a result, call setLimit() with a valid Bbox2 before!
CR_EMPTY	The result is empty (input completely outside the box)
CR_CLIPPED_DEGENERATE	The result has been clipped and is degenerate
CR_CLIPPED_NONDEGENERATE	The result has been clipped and is non-degenerate
CR_COMPLETE_DEGENERATE	The result is unclipped and degenerate (because the segment was already degenerate)
CR_COMPLETE_NONDEGENERATE	The result is unclipped and non-degenerate

7.22.1.2 SegmentIntersectionType `enum SegmentIntersectionType`

The Segment intersection type enumerates the way two line segments intersect each other

Enumerator

SIT_UNINITIALIZED	Invalid value
SIT_NONE	No intersection
SIT_SEGMENT	The intersection is a non-degenerate segment (collinear intersection)
SIT_POINT	The intersection is a single point differnt from the endpoints
SIT_ENDPOINT	The two segments share a common endpoint which is the only intersection

7.23 testDataGenerators.h File Reference

```
#include "Point2.h"
#include "Segment2.h"
#include <vector>
```

Functions

- void GEOM_FADE25D::generateCircle (int numPoints, double x, double y, double z, double radiusX, double radiusY, std::vector< Point2 > &vCirclePointsOut)

  Generate a circle.
- void GEOM_FADE25D::generateRandomNumbers (size_t num, double min, double max, std::vector< double > &vRandomNumbersOut, unsigned int seed=0)

  Generate random numbers.
- void GEOM_FADE25D::generateRandomPoints (size_t numRandomPoints, double min, double max, std::vector< Point2 > &vRandomPointsOut, unsigned int seed=0)

  Generate random points.
- void GEOM_FADE25D::generateRandomPoints3D (size_t numRandomPoints, double min, double max, std::vector< Point2 > &vRandomPointsOut, unsigned int seed=0)

  Generate random points with height.
- void GEOM_FADE25D::generateRandomPolygon (size_t numSegments, double min, double max, std::vector< Segment2 > &vPolygonOut, unsigned int seed=0)

  Generate a random simple polygon.
- void GEOM_FADE25D::generateRandomSegments (size_t numSegments, double min, double max, double maxLen, std::vector< Segment2 > &vSegmentsOut, unsigned int seed)

  Generate random line segments.
- void GEOM_FADE25D::generateRandomSurfacePoints (size_t numX, size_t numY, size_t numCenters, double xmin, double ymin, double zmin, double xmax, double ymax, double zmax, std::vector< Point2 > &vSurfacePointsOut, unsigned int seed, bool bGrid=true)

  Generate a random surface.
- void GEOM_FADE25D::generateSineSegments (int numSegments, int numPeriods, double xOffset, double yOffset, double xFactor, double yFactor, bool bSwapXY, std::vector< Segment2 > &vSineSegmentsOut)

  Generate segments from a sine function.
- void **GEOM_FADE25D::shear** (std::vector< Point2 > &vPointsInOut, double shearX, double shearY)

7.24 Triangle2.h File Reference

```
#include "Point2.h"
#include "common.h"
```

Classes

- class GEOM_FADE25D::Triangle2

  Triangle.

Enumerations

- enum GEOM_FADE25D::CircumcenterQuality { GEOM_FADE25D::CCQ_INIT , GEOM_FADE25D::CCQ_INEXACT , GEOM_FADE25D::CCQ_EXACT , GEOM_FADE25D::CCQ_OUT_OF_BOUNDS }

  CircumcenterQuality.

7.24.1 Enumeration Type Documentation

7.24.1.1 CircumcenterQuality enum GEOM_FADE25D::CircumcenterQuality

Enumerator

CCQ_INIT	Init value.
CCQ_INEXACT	Double precision computation, the result is accurate enough.
CCQ_EXACT	Computation with multiple-precision arithmetic, the result is exact (apart from tiny quantization errors)
CCQ_OUT_OF_BOUNDS	Computation with multiple-precision arithmetic, but the result is not representable with double precision coordinates.

7.25 TriangleAroundVertexIterator.h File Reference

```
#include "common.h"
#include "Point2.h"
#include "Triangle2.h"
```

Classes

- class GEOM_FADE25D::TriangleAroundVertexIterator

  Iterator for all triangles around a given vertex.

7.26 UserPredicates.h File Reference

```
#include "common.h"
#include "Triangle2.h"
```

Classes

- class GEOM_FADE25D::PeelPredicateTS

  User-defined peel predicate.
- class GEOM_FADE25D::UserPredicateT

  User-defined predicate (deprecated)

7.27 Vector2.h File Reference

```
#include "common.h"
```

Classes

- class GEOM_FADE25D::Vector2

  Vector.

Functions

- Vector2 GEOM_FADE25D::crossProduct (const Vector2 &vec0, const Vector2 &vec1)

  Cross product.
- Vector2 GEOM_FADE25D::normalize (const Vector2 &other)

  Normalize a vector.
- Vector2 GEOM_FADE25D::operator∗ (double d, const Vector2 &vec)

  Multiplication with a scalar.
- Vector2 GEOM_FADE25D::operator+ (const Vector2 &vec0, const Vector2 &vec1)

  Addition.
- Vector2 GEOM_FADE25D::operator- (const Vector2 &in)

Opposite vector.

- Vector2 GEOM_FADE25D::operator- (const Vector2 &vec0, const Vector2 &vec1)

  Subtraction.

- std::ostream & GEOM_FADE25D::operator<< (std::ostream &stream, const Vector2 &vec)

  Print to stream.

7.27.1 Function Documentation

7.27.1.1 crossProduct()

```
Vector2 GEOM_FADE25D::crossProduct (
        const Vector2 & vec0,
        const Vector2 & vec1 )  [inline]
```

Cross product of two vectors

7.27.1.2 operator*()

```
Vector2 GEOM_FADE25D::operator* (
        double d,
        const Vector2 & vec )  [inline]
```

Multiplication with a scalar

7.27.1.3 operator+()

```
Vector2 GEOM_FADE25D::operator+ (
        const Vector2 & vec0,
        const Vector2 & vec1 )  [inline]
```

Addition

7.27.1.4 operator-() [1/2]

```
Vector2 GEOM_FADE25D::operator- (
        const Vector2 & in )  [inline]
```

Returns

a vector that points in the opposite direction

7.27.1.5 operator-() [2/2]

```
Vector2 GEOM_FADE25D::operator- (
        const Vector2 & vec0,
        const Vector2 & vec1 )  [inline]
```

Subtraction

7.27.1.6 operator<<()

```
std::ostream& GEOM_FADE25D::operator<< (
        std::ostream & stream,
        const Vector2 & vec )  [inline]
```

Print to stream

7.28 Visualizer2.h File Reference

```
#include "Point2.h"
#include "Circle2.h"
#include "PShape.h"
#include "Segment2.h"
#include "Color.h"
#include "Label.h"
#include "Bbox2.h"
#include "Edge2.h"
#include "common.h"
```

Classes

- class GEOM_FADE25D::Visualizer2

  Visualizer2 is a PDF- and Postscript writer.

7.29 Visualizer3.h File Reference

```
#include "common.h"
#include "Point2.h"
#include "Segment2.h"
#include "VertexPair2.h"
#include "Edge2.h"
```

Classes

- class GEOM_FADE25D::Visualizer3

  Visualizer3 is a 3D scene writer for the Geomview viewer.

7.30 Zone2.h File Reference

```
#include "common.h"
#include "freeFunctions.h"
#include "FadeExport.h"
#include "Bbox2.h"
#include "Edge2.h"
#include "Segment2.h"
#include "UserPredicates.h"
#include "MsgBase.h"
```

Classes

- struct GEOM_FADE25D::CompPolygon

  Connected component with boundary- and hole polygons.
- class GEOM_FADE25D::Zone2

  Zone2 is a certain defined area of a triangulation.

Enumerations

- enum GEOM_FADE25D::OptimizationMode { GEOM_FADE25D::OPTMODE_STANDARD , GEOM_FADE25D::OPTMODE_BE , GEOM_FADE25D::OPTMODE_BEST }

Functions

- Zone2 * GEOM_FADE25D::zoneDifference (Zone2 *pZone0, Zone2 *pZone1)

  Compute the difference of two zones.
- Zone2 * GEOM_FADE25D::zoneIntersection (Zone2 *pZone0, Zone2 *pZone1)

  Compute the intersection of two zones.
- Zone2 * GEOM_FADE25D::zoneSymmetricDifference (Zone2 *pZone0, Zone2 *pZone1)

  Compute the symmetric difference of two zones.
- Zone2 * GEOM_FADE25D::zoneUnion (Zone2 *pZone0, Zone2 *pZone1)

  Compute the union of two zones.

7.30.1 Enumeration Type Documentation

7.30.1.1 OptimizationMode enum GEOM_FADE25D::OptimizationMode

Enumerates the possible modes for Valley/Ridge optimization through Zone2::slopeValleyRidgeOptimization().

Enumerator

OPTMODE_STANDARD	Fastest optimization mode.
OPTMODE_BETTER	Considerably better quality and still fast.
OPTMODE_BEST	Best quality but quite time consuming.

7.30.2 Function Documentation

7.30.2.1 zoneDifference()

```
Zone2* GEOM_FADE25D::zoneDifference (
        Zone2 * pZone0,
        Zone2 * pZone1 )
```

Returns

a new zone containing the triangles of ∗pZone0 minus the ones of ∗pZone1

Note

pZone0 and pZone1 must belong to the same Fade_2D object.

7.30.2.2 zoneIntersection()

```
Zone2* GEOM_FADE25D::zoneIntersection (
        Zone2 * pZone0,
        Zone2 * pZone1 )
```

Returns

a new zone containing the intersection of ∗pZone0 and ∗pZone1

Note

pZone0 and pZone1 must belong to the same Fade_2D object.

7.30.2.3 zoneSymmetricDifference()

```
Zone2* GEOM_FADE25D::zoneSymmetricDifference (
        Zone2 * pZone0,
        Zone2 * pZone1 )
```

Returns

a new zone containing the triangles that are present in one of the zones but not in the other one.

Note

pZone0 and pZone1 must belong to the same Fade_2D object.

7.30.2.4 zoneUnion() `Zone2* GEOM_FADE25D::zoneUnion (`

```
Zone2 * pZone0,
Zone2 * pZone1 )
```

Returns

a new zone containing the union of the triangles of ∗pZone0 and ∗pZone1

Note

`pZone0` and `pZone1` must belong to the same Fade_2D object.

Index

adaptiveSimplify
GEOM_FADE25D::CloudPrepare, 47
add
GEOM_FADE25D::Bbox2, 39
GEOM_FADE25D::CloudPrepare, 47, 48
addHeaderLine
GEOM_FADE25D::Visualizer2, 131
addLockedConstraint
GEOM_FADE25D::MeshGenParams, 97
addObject
GEOM_FADE25D::Visualizer2, 131–135
applyConstraintsAndZones
GEOM_FADE25D::Fade_2D, 70

bAllowConstraintSplitting
GEOM_FADE25D::MeshGenParams, 99
Bbox2
GEOM_FADE25D::Bbox2, 38
Bbox2.h, 146
getBox, 147
operator<<, 147
bGridMeshingLQ
GEOM_FADE25D::MeshGenParams, 99
bKeepExistingSteinerPoints
GEOM_FADE25D::MeshGenParams, 99
bReproducibleResults
GEOM_FADE25D::MeshGenParams, 99

CAF_Component.h, 147
CAFTYP, 147
CT_CUT, 148
CT_FILL, 148
CT_NULL, 148
operator<<, 148
CAFTYP
CAF_Component.h, 147
capAspectLimit
GEOM_FADE25D::MeshGenParams, 99
CCQ_EXACT
Triangle2.h, 164
CCQ_INEXACT
Triangle2.h, 164
CCQ_INIT
Triangle2.h, 164
CCQ_OUT_OF_BOUNDS
Triangle2.h, 164
center
Point2.h, 159
centerWithShift
Point2.h, 159
checkValidity
GEOM_FADE25D::Fade_2D, 71
CHS_MAXHULL
CloudPrepare.h, 148
CHS_MINHULL
CloudPrepare.h, 148
CHS_NOHULL
CloudPrepare.h, 148
Circle2
GEOM_FADE25D::Circle2, 44, 45
Circle2.h, 148
CircumcenterQuality
Triangle2.h, 162
CIS_CONFORMING_DELAUNAY
ConstraintSegment2.h, 150
CIS_CONFORMING_DELAUNAY_SEGMENT_LEVEL
ConstraintSegment2.h, 150
CIS_CONSTRAINED_DELAUNAY
ConstraintSegment2.h, 150
CIS_IGNORE_DELAUNAY
ConstraintSegment2.h, 150
CIS_KEEP_DELAUNAY
ConstraintSegment2.h, 150
ClipResult
SegmentChecker.h, 161
clipSegment
GEOM_FADE25D::SegmentChecker, 112
CloudPrepare.h, 148
CHS_MAXHULL, 148
CHS_MINHULL, 148
CHS_NOHULL, 148
ConvexHullStrategy, 148
SMS_AVERAGE, 149
SMS_MAXIMUM, 149
SMS_MEDIAN, 149
SMS_MINIMUM, 149
SumStrategy, 149
Color
GEOM_FADE25D::Color, 51
Color.h, 149
command
GEOM_FADE25D::MeshGenParams, 99
computeBoundingBox
GEOM_FADE25D::Fade_2D, 71
computeConvexHull
GEOM_FADE25D::CloudPrepare, 48
computeRange
GEOM_FADE25D::Visualizer2, 135
ConstraintGraph2.h, 149
ConstraintInsertionStrategy
ConstraintSegment2.h, 150
ConstraintSegment2.h, 149
CIS_CONFORMING_DELAUNAY, 150
CIS_CONFORMING_DELAUNAY_SEGMENT_LEVEL, 150
CIS_CONSTRAINED_DELAUNAY, 150
CIS_IGNORE_DELAUNAY, 150
CIS_KEEP_DELAUNAY, 150
ConstraintInsertionStrategy, 150
convertToBoundedZone
GEOM_FADE25D::Zone2, 139

ConvexHullStrategy
CloudPrepare.h, 148
copyFade
Fade_2D.h, 152
CR_CLIPPED_DEGENERATE
SegmentChecker.h, 161
CR_CLIPPED_NONDEGENERATE
SegmentChecker.h, 161
CR_COMPLETE_DEGENERATE
SegmentChecker.h, 161
CR_COMPLETE_NONDEGENERATE
SegmentChecker.h, 161
CR_EMPTY
SegmentChecker.h, 161
CR_INVALID
SegmentChecker.h, 161
createConstraint
GEOM_FADE25D::Fade_2D, 71
createZone
GEOM_FADE25D::Fade_2D, 72–74
createZone_cookieCutter
GEOM_FADE25D::Fade_2D, 74
crossProduct
Vector2.h, 165
CT_CUT
CAF_Component.h, 148
CT_FILL
CAF_Component.h, 148
CT_NULL
CAF_Component.h, 148
CutAndFill
GEOM_FADE25D::CutAndFill, 58
CutAndFill.h, 150
cutTriangles
GEOM_FADE25D::Fade_2D, 74, 75

deleteZone
GEOM_FADE25D::Fade_2D, 75
doIntersect
GEOM_FADE25D::Bbox2, 39
doubleTheBox
GEOM_FADE25D::Bbox2, 39
drape
GEOM_FADE25D::Fade_2D, 75

Edge2
GEOM_FADE25D::Edge2, 63
Edge2.h, 150
edgesToPolygons
Tools, 20
EfficientModel.h, 151
SmoothingStrategy, 151
SMST_AVERAGE, 151
SMST_MAXIMUM, 151
SMST_MEDIAN, 151
SMST_MINIMUM, 151
enlargeRanges
GEOM_FADE25D::Bbox2, 39
exportTriangulation
GEOM_FADE25D::Fade_2D, 76
exportZone
GEOM_FADE25D::Zone2, 139
extract
GEOM_FADE25D::EfficientModel, 65

Fade_2D
GEOM_FADE25D::Fade_2D, 70
Fade_2D.h, 151
copyFade, 152
FadeExport.h, 152
File I/O, 25
readPointsBIN, 26
readPointsPLY, 26, 27
readSegmentsBIN, 27
readXY, 27
readXYZ, 27
writePointsASCII, 27, 28
writePointsBIN, 28
writePointsPLY, 28, 29
writeSegmentsBIN, 29
fillHole
Tools, 21, 22
freeFunctions.h, 153
getGlobalNumCPU, 155
getSortedBoundaryPolygons, 155
offsetPolygonPoints, 155
setGlobalNumCPU, 156
untwistPolygon, 157

generateCircle
Test Data Generators, 30
generateRandomNumbers
Test Data Generators, 31
generateRandomPoints
Test Data Generators, 31
generateRandomPoints3D
Test Data Generators, 32
generateRandomPolygon
Test Data Generators, 33
generateRandomSegments
Test Data Generators, 34
generateRandomSurfacePoints
Test Data Generators, 35
generateSineSegments
Test Data Generators, 35
GEOM_FADE25D::Bbox2, 37
add, 39
Bbox2, 38
doIntersect, 39
doubleTheBox, 39
enlargeRanges, 39
get_maxX, 40
get_maxY, 40
get_minX, 40
get_minY, 40
getBoundary, 40
getCorners, 40
getMaxCoord, 40

getMaxPoint, 40
getMaxRange, 41
getMinCoord, 41
getMinPoint, 41
getOffsetCorners, 41
getRangeX, 41
getRangeY, 41
inflateIfDegenerate, 41
isInBox, 41
isValid, 41
operator<<, 42
operator+, 42
reset, 42
GEOM_FADE25D::CAF_Component, 42
getBorder, 43
getCAFType, 43
getLabel, 43
getTriangles, 43
getVolume, 44
GEOM_FADE25D::Circle2, 44
Circle2, 44, 45
getCenter, 45
getRadius, 45
getSqRadius, 45
GEOM_FADE25D::CloudPrepare, 45
adaptiveSimplify, 47
add, 47, 48
computeConvexHull, 48
getBounds, 48
getNumPoints, 48
getPoints, 49
getRangeX, 49
getRangeY, 49
getRangeZ, 49
uniformSimplifyGrid, 49
uniformSimplifyNum, 50
GEOM_FADE25D::Color, 50
Color, 51
GEOM_FADE25D::CompPolygon, 52
GEOM_FADE25D::ConstraintGraph2, 52
getChildConstraintSegments, 53
getDirectChildren, 53
getDt2, 54
getInsertionStrategy, 54
getOriginalConstraintSegments, 54
getPolygonVertices, 54
isConstraint, 54
isOriented, 55
isPolygon, 55
isReverse, 55
makeDelaunay, 55
GEOM_FADE25D::ConstraintSegment2, 56
getCIS, 57
getSrc, 57
getTrg, 57
insertAndSplit, 57
isAlive, 57
split_combinatorialOnly, 57
GEOM_FADE25D::CutAndFill, 57
CutAndFill, 58
getComponent, 59
getDiffZone, 59
getNumberOfComponents, 59
go, 59
show, 60
subscribe, 60
unsubscribe, 62
GEOM_FADE25D::Edge2, 62
Edge2, 63
getIndex, 63
getLength25D, 63
getLength2D, 63
getPoints, 63
getSrc, 63
getTrg, 63
getTriangle, 64
getTriangles, 64
operator!=, 64
operator<, 64
operator==, 64
GEOM_FADE25D::EfficientModel, 64
extract, 65
zSmoothing, 65
GEOM_FADE25D::Fade_2D, 67
applyConstraintsAndZones, 70
checkValidity, 71
computeBoundingBox, 71
createConstraint, 71
createZone, 72–74
createZone_cookieCutter, 74
cutTriangles, 74, 75
deleteZone, 75
drape, 75
exportTriangulation, 76
Fade_2D, 70
getAdjacentTriangle, 77
getConstraintSegment, 77
getConvexHull, 77
getHeight, 77
getIncidentTriangles, 78
getIncidentVertices, 78
getNearestNeighbor, 78
getOrientation, 78
getPeeledZone, 78
getTrianglePointers, 79
getUndirectedEdges, 79
getVertexPointer, 79
getVertexPointers, 79
getVoronoiDiagram, 80
hasArea, 80
importTriangles, 80
importTriangles_robust, 81
importTrianglesFromPly, 81
insert, 82, 83
isConstraint, 83
load, 83, 84

locate, 84
measureTriangulationTime, 85
numberOfPoints, 85
numberOfTriangles, 85
refine, 85
refineAdvanced, 86
remove, 86
reset, 86
saveTriangulation, 86, 87
saveZones, 87, 88
setFastMode, 88
setNumCPU, 89
show, 89
showGeomview, 89
statistics, 90
subscribe, 90
unsubscribe, 90
writeObj, 90
writePly, 90, 91
writeWebScene, 91
GEOM_FADE25D::FadeExport, 91
getCoordinates, 92
getCornerIndices, 92
getCustomIndex, 93
lexiSort, 93
reset, 93
GEOM_FADE25D::Func_gtEdge2D, 93
GEOM_FADE25D::Func_ltEdge25D, 93
GEOM_FADE25D::Func_ltEdge2D, 93
GEOM_FADE25D::Func_ltPointXYZ, 94
GEOM_FADE25D::IsoContours, 94
getContours, 95
getMaxHeight, 95
getMinHeight, 95
getProfile, 95
IsoContours, 94
GEOM_FADE25D::Label, 95
Label, 96
GEOM_FADE25D::MeshGenParams, 96
addLockedConstraint, 97
bAllowConstraintSplitting, 99
bGridMeshingLQ, 99
bKeepExistingSteinerPoints, 99
bReproducibleResults, 99
capAspectLimit, 99
command, 99
getMaxEdgeLength, 97
getMaxTriangleArea, 98
gridLength, 99
gridPoint, 100
gridVector, 100
growFactor, 100
growFactorMinArea, 101
maxEdgeLength, 101
maxHeightError, 101
maxTriangleArea, 101
minAngleDegree, 101
minEdgeLength, 101
pHeightGuideTriangulation, 101
GEOM_FADE25D::MsgBase, 101
update, 102
GEOM_FADE25D::PeelPredicateTS, 102
GEOM_FADE25D::Point2, 102
getCustomIndex, 104
getIncidentTriangle, 104
operator!=, 104
operator<, 105
operator>, 105
operator==, 105
Point2, 104
samePoint, 105
set, 105
setCoords, 106
setCustomIndex, 106
setHeight, 106
setIncidentTriangle, 106
x, 107
xy, 107
xyz, 107
y, 107
z, 107
GEOM_FADE25D::PShape, 108
GEOM_FADE25D::Segment2, 108
getSqLen25D, 109
getSqLen2D, 109
getSrc, 109
getTrg, 109
operator<, 109
operator==, 109
Segment2, 108, 109
swapSrcTrg, 109
GEOM_FADE25D::SegmentChecker, 110
clipSegment, 112
getIllegalSegments, 112
getIndex, 112
getIntersectionPoint, 112
getIntersectionSegment, 113
getIntersectionType, 113
getIntersectionTypeString, 114
getIntersectors, 114
getLimit, 114
getNumberOfSegments, 114
getSegment, 114
SegmentChecker, 111
setLimit, 115
showIllegalSegments, 115
showSegments, 116
subscribe, 117
unsubscribe, 117
GEOM_FADE25D::Triangle2, 118
getArea25D, 120
getArea2D, 120
getBarycenter, 120
getCircumcenter, 120
getInteriorAngle25D, 120
getInteriorAngle2D, 120

getIntraTriangleIndex, 121
getNormalVector, 122
getOppositeTriangle, 122
getSquaredEdgeLength25D, 122
getSquaredEdgeLength2D, 122
hasOn, 122
hasOnEdge, 123
hasVertex, 123
setOppTriangle, 123
GEOM_FADE25D::TriangleAroundVertexIterator, 124
operator!=, 125
operator*, 125
operator++, 125
operator--, 126
operator==, 126
previewNextTriangle, 126
previewPrevTriangle, 126
TriangleAroundVertexIterator, 125
GEOM_FADE25D::UserPredicateT, 127
GEOM_FADE25D::Vector2, 127
getMaxIndex, 128
isDegenerate, 128
operator*, 128
operator/, 128
Vector2, 128
GEOM_FADE25D::Visualizer2, 128
addHeaderLine, 131
addObject, 131–135
computeRange, 135
Visualizer2, 131
writeFile, 135
GEOM_FADE25D::Visualizer3, 135
GEOM_FADE25D::VtxColor, 137
GEOM_FADE25D::Zone2, 137
convertToBoundedZone, 139
exportZone, 139
getArea25D, 139
getArea2D, 139
getBorderEdges, 139
getBoundarySegments, 139
getComponentPolygons, 139
getConstraintGraph, 140
getNumberOfTriangles, 140
getTriangles, 140
getZoneLocation, 140
numberOfConstraintGraphs, 140
peelOffIf, 145
save, 141
show, 141, 142
showGeomview, 142
slopeValleyRidgeOptimization, 142
smoothing, 143
statistics, 143
subscribe, 143
unifyGrid, 143
unsubscribe, 144
writeObj, 144
writePly, 144
zoneDifference, 145
zoneIntersection, 146
zoneSymmetricDifference, 146
zoneUnion, 146
get_maxX
GEOM_FADE25D::Bbox2, 40
get_maxY
GEOM_FADE25D::Bbox2, 40
get_minX
GEOM_FADE25D::Bbox2, 40
get_minY
GEOM_FADE25D::Bbox2, 40
getAdjacentTriangle
GEOM_FADE25D::Fade_2D, 77
getArea25D
GEOM_FADE25D::Triangle2, 120
GEOM_FADE25D::Zone2, 139
Tools, 22
getArea2D
GEOM_FADE25D::Triangle2, 120
GEOM_FADE25D::Zone2, 139
Tools, 23
getBarycenter
GEOM_FADE25D::Triangle2, 120
getBorder
GEOM_FADE25D::CAF_Component, 43
getBorderEdges
GEOM_FADE25D::Zone2, 139
getBorders
Tools, 23
getBoundary
GEOM_FADE25D::Bbox2, 40
getBoundarySegments
GEOM_FADE25D::Zone2, 139
getBounds
GEOM_FADE25D::CloudPrepare, 48
getBox
Bbox2.h, 147
getCAFType
GEOM_FADE25D::CAF_Component, 43
getCenter
GEOM_FADE25D::Circle2, 45
getChildConstraintSegments
GEOM_FADE25D::ConstraintGraph2, 53
getCircumcenter
GEOM_FADE25D::Triangle2, 120
getCIS
GEOM_FADE25D::ConstraintSegment2, 57
getComponent
GEOM_FADE25D::CutAndFill, 59
getComponentPolygons
GEOM_FADE25D::Zone2, 139
getConnectedComponents
Tools, 23
getConstraintGraph
GEOM_FADE25D::Zone2, 140
getConstraintSegment
GEOM_FADE25D::Fade_2D, 77

getContours
GEOM_FADE25D::IsoContours, 95
getConvexHull
GEOM_FADE25D::Fade_2D, 77
getCoordinates
GEOM_FADE25D::FadeExport, 92
getCornerIndices
GEOM_FADE25D::FadeExport, 92
getCorners
GEOM_FADE25D::Bbox2, 40
getCustomIndex
GEOM_FADE25D::FadeExport, 93
GEOM_FADE25D::Point2, 104
getDiffZone
GEOM_FADE25D::CutAndFill, 59
getDirectChildren
GEOM_FADE25D::ConstraintGraph2, 53
getDt2
GEOM_FADE25D::ConstraintGraph2, 54
getGlobalNumCPU
freeFunctions.h, 155
getHeight
GEOM_FADE25D::Fade_2D, 77
getIllegalSegments
GEOM_FADE25D::SegmentChecker, 112
getIncidentTriangle
GEOM_FADE25D::Point2, 104
getIncidentTriangles
GEOM_FADE25D::Fade_2D, 78
getIncidentVertices
GEOM_FADE25D::Fade_2D, 78
getIndex
GEOM_FADE25D::Edge2, 63
GEOM_FADE25D::SegmentChecker, 112
getInsertionStrategy
GEOM_FADE25D::ConstraintGraph2, 54
getInteriorAngle25D
GEOM_FADE25D::Triangle2, 120
getInteriorAngle2D
GEOM_FADE25D::Triangle2, 120
getIntersectionPoint
GEOM_FADE25D::SegmentChecker, 112
getIntersectionSegment
GEOM_FADE25D::SegmentChecker, 113
getIntersectionType
GEOM_FADE25D::SegmentChecker, 113
getIntersectionTypeString
GEOM_FADE25D::SegmentChecker, 114
getIntersectors
GEOM_FADE25D::SegmentChecker, 114
getIntraTriangleIndex
GEOM_FADE25D::Triangle2, 121
getLabel
GEOM_FADE25D::CAF_Component, 43
getLength25D
GEOM_FADE25D::Edge2, 63
getLength2D
GEOM_FADE25D::Edge2, 63
getLimit
GEOM_FADE25D::SegmentChecker, 114
getMaxCoord
GEOM_FADE25D::Bbox2, 40
getMaxEdgeLength
GEOM_FADE25D::MeshGenParams, 97
getMaxHeight
GEOM_FADE25D::IsoContours, 95
getMaxIndex
GEOM_FADE25D::Vector2, 128
getMaxPoint
GEOM_FADE25D::Bbox2, 40
getMaxRange
GEOM_FADE25D::Bbox2, 41
getMaxTriangleArea
GEOM_FADE25D::MeshGenParams, 98
getMinCoord
GEOM_FADE25D::Bbox2, 41
getMinHeight
GEOM_FADE25D::IsoContours, 95
getMinPoint
GEOM_FADE25D::Bbox2, 41
getNearestNeighbor
GEOM_FADE25D::Fade_2D, 78
getNormalVector
GEOM_FADE25D::Triangle2, 122
Tools, 23
getNumberOfComponents
GEOM_FADE25D::CutAndFill, 59
getNumberOfSegments
GEOM_FADE25D::SegmentChecker, 114
getNumberOfTriangles
GEOM_FADE25D::Zone2, 140
getNumPoints
GEOM_FADE25D::CloudPrepare, 48
getOffsetCorners
GEOM_FADE25D::Bbox2, 41
getOppositeTriangle
GEOM_FADE25D::Triangle2, 122
getOrientation
GEOM_FADE25D::Fade_2D, 78
getOrientation2
Tools, 24
getOrientation2_mt
Tools, 24
getOriginalConstraintSegments
GEOM_FADE25D::ConstraintGraph2, 54
getPeeledZone
GEOM_FADE25D::Fade_2D, 78
getPoints
GEOM_FADE25D::CloudPrepare, 49
GEOM_FADE25D::Edge2, 63
getPolygonVertices
GEOM_FADE25D::ConstraintGraph2, 54
getProfile
GEOM_FADE25D::IsoContours, 95
getRadius
GEOM_FADE25D::Circle2, 45

getRangeX
GEOM_FADE25D::Bbox2, 41
GEOM_FADE25D::CloudPrepare, 49
getRangeY
GEOM_FADE25D::Bbox2, 41
GEOM_FADE25D::CloudPrepare, 49
getRangeZ
GEOM_FADE25D::CloudPrepare, 49
getSegment
GEOM_FADE25D::SegmentChecker, 114
getSortedBoundaryPolygons
freeFunctions.h, 155
getSqLen25D
GEOM_FADE25D::Segment2, 109
getSqLen2D
GEOM_FADE25D::Segment2, 109
getSqRadius
GEOM_FADE25D::Circle2, 45
getSquaredEdgeLength25D
GEOM_FADE25D::Triangle2, 122
getSquaredEdgeLength2D
GEOM_FADE25D::Triangle2, 122
getSrc
GEOM_FADE25D::ConstraintSegment2, 57
GEOM_FADE25D::Edge2, 63
GEOM_FADE25D::Segment2, 109
getTrg
GEOM_FADE25D::ConstraintSegment2, 57
GEOM_FADE25D::Edge2, 63
GEOM_FADE25D::Segment2, 109
getTriangle
GEOM_FADE25D::Edge2, 64
getTrianglePointers
GEOM_FADE25D::Fade_2D, 79
getTriangles
GEOM_FADE25D::CAF_Component, 43
GEOM_FADE25D::Edge2, 64
GEOM_FADE25D::Zone2, 140
getUndirectedEdges
GEOM_FADE25D::Fade_2D, 79
Tools, 24
getVertexPointer
GEOM_FADE25D::Fade_2D, 79
getVertexPointers
GEOM_FADE25D::Fade_2D, 79
getVolume
GEOM_FADE25D::CAF_Component, 44
getVoronoiDiagram
GEOM_FADE25D::Fade_2D, 80
getZoneLocation
GEOM_FADE25D::Zone2, 140
go
GEOM_FADE25D::CutAndFill, 59
gridLength
GEOM_FADE25D::MeshGenParams, 99
gridPoint
GEOM_FADE25D::MeshGenParams, 100
gridVector
GEOM_FADE25D::MeshGenParams, 100
growFactor
GEOM_FADE25D::MeshGenParams, 100
growFactorMinArea
GEOM_FADE25D::MeshGenParams, 101

hasArea
GEOM_FADE25D::Fade_2D, 80
hasOn
GEOM_FADE25D::Triangle2, 122
hasOnEdge
GEOM_FADE25D::Triangle2, 123
hasVertex
GEOM_FADE25D::Triangle2, 123

importTriangles
GEOM_FADE25D::Fade_2D, 80
importTriangles_robust
GEOM_FADE25D::Fade_2D, 81
importTrianglesFromPly
GEOM_FADE25D::Fade_2D, 81
inflateIfDegenerate
GEOM_FADE25D::Bbox2, 41
insert
GEOM_FADE25D::Fade_2D, 82, 83
insertAndSplit
GEOM_FADE25D::ConstraintSegment2, 57
isAlive
GEOM_FADE25D::ConstraintSegment2, 57
isConstraint
GEOM_FADE25D::ConstraintGraph2, 54
GEOM_FADE25D::Fade_2D, 83
isDegenerate
GEOM_FADE25D::Vector2, 128
isInBox
GEOM_FADE25D::Bbox2, 41
IsoContours
GEOM_FADE25D::IsoContours, 94
IsoContours.h, 157
isOriented
GEOM_FADE25D::ConstraintGraph2, 55
isPolygon
GEOM_FADE25D::ConstraintGraph2, 55
isReverse
GEOM_FADE25D::ConstraintGraph2, 55
isSimplePolygon
Tools, 24
isValid
GEOM_FADE25D::Bbox2, 41

Label
GEOM_FADE25D::Label, 96
Label.h, 157
lexiSort
GEOM_FADE25D::FadeExport, 93
load
GEOM_FADE25D::Fade_2D, 83, 84
locate
GEOM_FADE25D::Fade_2D, 84

makeDelaunay
GEOM_FADE25D::ConstraintGraph2, 55
maxEdgeLength
GEOM_FADE25D::MeshGenParams, 101
maxHeightError
GEOM_FADE25D::MeshGenParams, 101
maxTriangleArea
GEOM_FADE25D::MeshGenParams, 101
measureTriangulationTime
GEOM_FADE25D::Fade_2D, 85
MeshGenParams.h, 157
unusedParameter, 158
minAngleDegree
GEOM_FADE25D::MeshGenParams, 101
minEdgeLength
GEOM_FADE25D::MeshGenParams, 101
MsgBase.h, 158

numberOfConstraintGraphs
GEOM_FADE25D::Zone2, 140
numberOfPoints
GEOM_FADE25D::Fade_2D, 85
numberOfTriangles
GEOM_FADE25D::Fade_2D, 85

offsetPolygonPoints
freeFunctions.h, 155
operator!=
GEOM_FADE25D::Edge2, 64
GEOM_FADE25D::Point2, 104
GEOM_FADE25D::TriangleAroundVertexIterator, 125
operator<
GEOM_FADE25D::Edge2, 64
GEOM_FADE25D::Point2, 105
GEOM_FADE25D::Segment2, 109
operator<<
Bbox2.h, 147
CAF_Component.h, 148
GEOM_FADE25D::Bbox2, 42
Vector2.h, 165
operator>
GEOM_FADE25D::Point2, 105
operator*
GEOM_FADE25D::TriangleAroundVertexIterator, 125
GEOM_FADE25D::Vector2, 128
Vector2.h, 165
operator+
GEOM_FADE25D::Bbox2, 42
Vector2.h, 165
operator++
GEOM_FADE25D::TriangleAroundVertexIterator, 125
operator-
Vector2.h, 165
operator--
GEOM_FADE25D::TriangleAroundVertexIterator, 126
operator/
GEOM_FADE25D::Vector2, 128
operator==
GEOM_FADE25D::Edge2, 64
GEOM_FADE25D::Point2, 105
GEOM_FADE25D::Segment2, 109
GEOM_FADE25D::TriangleAroundVertexIterator, 126
OptimizationMode
Zone2.h, 166
OPTMODE_BEST
Zone2.h, 167
OPTMODE_BETTER
Zone2.h, 167
OPTMODE_STANDARD
Zone2.h, 167

peelOffIf
GEOM_FADE25D::Zone2, 145
Performance.h, 158
timer, 158
pHeightGuideTriangulation
GEOM_FADE25D::MeshGenParams, 101
Point2
GEOM_FADE25D::Point2, 104
Point2.h, 158
center, 159
centerWithShift, 159
sqDistance25D, 159, 160
sqDistance2D, 160
pointsToPolyline
Tools, 24
previewNextTriangle
GEOM_FADE25D::TriangleAroundVertexIterator, 126
previewPrevTriangle
GEOM_FADE25D::TriangleAroundVertexIterator, 126
PShape.h, 160

readPointsBIN
File I/O, 26
readPointsPLY
File I/O, 26, 27
readSegmentsBIN
File I/O, 27
readXY
File I/O, 27
readXYZ
File I/O, 27
refine
GEOM_FADE25D::Fade_2D, 85
refineAdvanced
GEOM_FADE25D::Fade_2D, 86
remove
GEOM_FADE25D::Fade_2D, 86
reset
GEOM_FADE25D::Bbox2, 42
GEOM_FADE25D::Fade_2D, 86

GEOM_FADE25D::FadeExport, 93

samePoint
GEOM_FADE25D::Point2, 105
save
GEOM_FADE25D::Zone2, 141
saveTriangulation
GEOM_FADE25D::Fade_2D, 86, 87
saveZones
GEOM_FADE25D::Fade_2D, 87, 88
Segment2
GEOM_FADE25D::Segment2, 108, 109
Segment2.h, 160
SegmentChecker
GEOM_FADE25D::SegmentChecker, 111
SegmentChecker.h, 161
ClipResult, 161
CR_CLIPPED_DEGENERATE, 161
CR_CLIPPED_NONDEGENERATE, 161
CR_COMPLETE_DEGENERATE, 161
CR_COMPLETE_NONDEGENERATE, 161
CR_EMPTY, 161
CR_INVALID, 161
SegmentIntersectionType, 161
SIT_ENDPOINT, 161
SIT_NONE, 161
SIT_POINT, 161
SIT_SEGMENT, 161
SIT_UNINITIALIZED, 161
SegmentIntersectionType
SegmentChecker.h, 161
set
GEOM_FADE25D::Point2, 105
setCoords
GEOM_FADE25D::Point2, 106
setCustomIndex
GEOM_FADE25D::Point2, 106
setFastMode
GEOM_FADE25D::Fade_2D, 88
setGlobalNumCPU
freeFunctions.h, 156
setHeight
GEOM_FADE25D::Point2, 106
setIncidentTriangle
GEOM_FADE25D::Point2, 106
setLimit
GEOM_FADE25D::SegmentChecker, 115
setNumCPU
GEOM_FADE25D::Fade_2D, 89
setOppTriangle
GEOM_FADE25D::Triangle2, 123
show
GEOM_FADE25D::CutAndFill, 60
GEOM_FADE25D::Fade_2D, 89
GEOM_FADE25D::Zone2, 141, 142
showGeomview
GEOM_FADE25D::Fade_2D, 89
GEOM_FADE25D::Zone2, 142
showIllegalSegments
GEOM_FADE25D::SegmentChecker, 115
showSegments
GEOM_FADE25D::SegmentChecker, 116
SIT_ENDPOINT
SegmentChecker.h, 161
SIT_NONE
SegmentChecker.h, 161
SIT_POINT
SegmentChecker.h, 161
SIT_SEGMENT
SegmentChecker.h, 161
SIT_UNINITIALIZED
SegmentChecker.h, 161
slopeValleyRidgeOptimization
GEOM_FADE25D::Zone2, 142
smoothing
GEOM_FADE25D::Zone2, 143
SmoothingStrategy
EfficientModel.h, 151
SMS_AVERAGE
CloudPrepare.h, 149
SMS_MAXIMUM
CloudPrepare.h, 149
SMS_MEDIAN
CloudPrepare.h, 149
SMS_MINIMUM
CloudPrepare.h, 149
SMST_AVERAGE
EfficientModel.h, 151
SMST_MAXIMUM
EfficientModel.h, 151
SMST_MEDIAN
EfficientModel.h, 151
SMST_MINIMUM
EfficientModel.h, 151
sortRing
Tools, 25
sortRingCCW
Tools, 25
split_combinatorialOnly
GEOM_FADE25D::ConstraintSegment2, 57
sqDistance25D
Point2.h, 159, 160
sqDistance2D
Point2.h, 160
statistics
GEOM_FADE25D::Fade_2D, 90
GEOM_FADE25D::Zone2, 143
subscribe
GEOM_FADE25D::CutAndFill, 60
GEOM_FADE25D::Fade_2D, 90
GEOM_FADE25D::SegmentChecker, 117
GEOM_FADE25D::Zone2, 143
SumStrategy
CloudPrepare.h, 149
swapSrcTrg
GEOM_FADE25D::Segment2, 109

Test Data Generators, 30

generateCircle, 30
generateRandomNumbers, 31
generateRandomPoints, 31
generateRandomPoints3D, 32
generateRandomPolygon, 33
generateRandomSegments, 34
generateRandomSurfacePoints, 35
generateSineSegments, 35
testDataGenerators.h, 162
timer
Performance.h, 158
Tools, 19
edgesToPolygons, 20
fillHole, 21, 22
getArea25D, 22
getArea2D, 23
getBorders, 23
getConnectedComponents, 23
getNormalVector, 23
getOrientation2, 24
getOrientation2_mt, 24
getUndirectedEdges, 24
isSimplePolygon, 24
pointsToPolyline, 24
sortRing, 25
sortRingCCW, 25
Triangle2.h, 162
CCQ_EXACT, 164
CCQ_INEXACT, 164
CCQ_INIT, 164
CCQ_OUT_OF_BOUNDS, 164
CircumcenterQuality, 162
TriangleAroundVertexIterator
GEOM_FADE25D::TriangleAroundVertexIterator, 125
TriangleAroundVertexIterator.h, 164

uniformSimplifyGrid
GEOM_FADE25D::CloudPrepare, 49
uniformSimplifyNum
GEOM_FADE25D::CloudPrepare, 50
unifyGrid
GEOM_FADE25D::Zone2, 143
unsubscribe
GEOM_FADE25D::CutAndFill, 62
GEOM_FADE25D::Fade_2D, 90
GEOM_FADE25D::SegmentChecker, 117
GEOM_FADE25D::Zone2, 144
untwistPolygon
freeFunctions.h, 157
unusedParameter
MeshGenParams.h, 158
update
GEOM_FADE25D::MsgBase, 102
UserPredicates.h, 164

Vector2
GEOM_FADE25D::Vector2, 128
Vector2.h, 164
crossProduct, 165
operator<<, 165
operator*, 165
operator+, 165
operator-, 165
Version Information, 25
Visualizer2
GEOM_FADE25D::Visualizer2, 131
Visualizer2.h, 165
Visualizer3.h, 166

writeFile
GEOM_FADE25D::Visualizer2, 135
writeObj
GEOM_FADE25D::Fade_2D, 90
GEOM_FADE25D::Zone2, 144
writePly
GEOM_FADE25D::Fade_2D, 90, 91
GEOM_FADE25D::Zone2, 144
writePointsASCII
File I/O, 27, 28
writePointsBIN
File I/O, 28
writePointsPLY
File I/O, 28, 29
writeSegmentsBIN
File I/O, 29
writeWebScene
GEOM_FADE25D::Fade_2D, 91

x
GEOM_FADE25D::Point2, 107
xy
GEOM_FADE25D::Point2, 107
xyz
GEOM_FADE25D::Point2, 107

y
GEOM_FADE25D::Point2, 107

z
GEOM_FADE25D::Point2, 107
Zone2.h, 166
OptimizationMode, 166
OPTMODE_BEST, 167
OPTMODE_BETTER, 167
OPTMODE_STANDARD, 167
zoneDifference, 167
zoneIntersection, 167
zoneSymmetricDifference, 167
zoneUnion, 167
zoneDifference
GEOM_FADE25D::Zone2, 145
Zone2.h, 167
zoneIntersection
GEOM_FADE25D::Zone2, 146
Zone2.h, 167
zoneSymmetricDifference
GEOM_FADE25D::Zone2, 146

Zone2.h, 167
zoneUnion
GEOM_FADE25D::Zone2, 146
Zone2.h, 167
zSmoothing
GEOM_FADE25D::EfficientModel, 65