

TB Noise Remover

DETAILED ENGLISH USER MANUAL

A targeted restoration processor with a core reduction stage plus modules for hiss, hum, whine, clicks, rumble, and clipped peaks.



Catalog version: 2.2.0

Documentation edition: 2026-08-04

Host-visible endpoints documented: 10

1. Product purpose

A targeted restoration processor with a core reduction stage plus modules for hiss, hum, whine, clicks, rumble, and clipped peaks.

Dialogue, podcast, vocal, and field recordings may contain several different fault types at once. A single aggressive gate cannot distinguish steady ambience from hum, clicks, or clipping. TB Noise Remover provides a central cleanup amount and targeted switches so only the required restoration modules are engaged.

What result it creates

- Reduced environmental noise and room tone
- Targeted 50/60 Hz hum control
- Suppression of hiss, whine, clicks, and low rumble
- Optional repair of clipped events

Signal flow

Input -> Basic restoration and Reduction control -> selected Hiss/Hum/Whine/Click/Rumble modules -> Clip Repair -> output

2. Complete feature guide

Basic and Reduction

Basic enables the primary broadband restoration path. Reduction moves from light natural cleanup toward stronger suppression. Increase it only until the noise is acceptably controlled.

Hiss

Targets broad high-frequency noise such as preamp hiss or air-system noise. Excessive use can dull consonants and cymbals.

50 Hz and 60 Hz Hum

Select the mains family that matches the recording. Do not enable both automatically; use the one that corresponds to the actual fundamental and harmonic pattern.

Digital Whine

Targets stable narrow electronic tones. Verify with headphones because musical sustained notes can resemble a whine.

Clicks

Detects and softens isolated short impulses. Use on mouth clicks or digital ticks, then confirm that drum transients remain intact.

Low Rumble

Reduces very low mechanical, handling, or traffic energy. Check that bass fundamentals and voice weight are not unnecessarily removed.

Clip Repair

Attempts to reconstruct flattened or damaged peak shapes. It cannot recover information that was never recorded and should be evaluated event by event.

3. Quick start

1. Start with only Basic enabled.
2. Raise Reduction until steady noise is controlled without watery movement.
3. Enable one targeted module at a time.
4. Choose either 50 Hz or 60 Hz hum treatment based on the recording.
5. Check speech consonants, breaths, and musical transients.
6. Use Clip Repair only when clipped peaks are present.

4. Practical workflows

Podcast cleanup

1. Enable Basic and use moderate Reduction.
2. Add Hiss if the preamp noise remains.
3. Add 50 or 60 Hz Hum only when audible.
4. Check breaths and S sounds in bypass comparison.

Expected result: Speech becomes clearer while natural room and articulation remain believable.

Field recording repair

1. Start with Low Rumble for handling or traffic energy.
2. Use Digital Whine for a stable electronic tone.
3. Enable Clicks only if impulses remain.
4. Use several moderate stages instead of maximum Reduction.

Expected result: Multiple fault types are reduced without forcing one algorithm to solve everything.

5. Automation, gain staging, and session use

- Automate only controls that serve a clear musical transition. Fast movement of frequency, time, pitch, mode, oversampling, or algorithm selectors may intentionally create artifacts or require a host-safe transition.
- Match perceived loudness before judging quality. A louder setting will often appear better even when the processing decision is not better.
- Use the plug-in bypass endpoint for comparison and preserve an unprocessed source or earlier project version.
- Factory programs are starting points. Loading a program changes multiple parameters; save a new DAW preset after adapting it to the source.
- The parameter appendix is captured from the installed VST3 host contract. It lists every host-visible endpoint, its displayed range/options, default, automation status, and identifier.

6. Limits, cautions, and troubleshooting

- Restoration is subtractive and cannot recreate fully masked detail.

- Heavy processing can create watery or gated artifacts.
- Always preserve the original recording.
- No audible change: confirm the plug-in and relevant sub-block are enabled, Mix/Amount is not at a neutral value, and the source contains energy in the processed region.
- Unexpected level: return input, output, send, feedback, and parallel-mix controls to conservative values, then rebuild the setting one block at a time.
- Automation does not match the panel: reload the project, confirm the DAW is addressing the current plug-in version, and check whether a factory program or state recall replaced values.
- Clicks or transitions: avoid sample-instant changes to algorithm, time, pitch, mode, or oversampling selectors unless the sound is intentional.

7. Complete host parameter reference

This appendix contains all 10 parameters exposed by the current installed VST3 to a host. Repeated EQ-band endpoints are intentionally listed rather than collapsed. Discrete options are printed in full when the host contract exposes them.

Parameter	Range / options	Default	Host status	Function
50 Hz Hum VST3 ID 99638171	Off, On	Off	Automatable	Host-automatable control for 50 Hz Hum. Its full range and default are shown in this table; use it with the related feature section above.
60 Hz Hum VST3 ID 99638202	Off, On	Off	Automatable	Host-automatable control for 60 Hz Hum. Its full range and default are shown in this table; use it with the related feature section above.
Basic VST3 ID 93508654	Off, On	On	Automatable	Host-automatable control for Basic. Its full range and default are shown in this table; use it with the related feature section above.
Bypass VST3 ID 1652125811	Off, On	Off	Automatable; Bypass	Turns the complete plug-in processing path off or on through the host-visible bypass endpoint.
Clicks VST3 ID 789769195	Off, On	Off	Automatable	Host-automatable control for Clicks. Its full range and default are shown in this table; use it with the related feature section above.
Clip Repair VST3 ID 1460400893	Off, On	Off	Automatable	Host-automatable control for Clip Repair. Its full range and default are shown in this table; use it with the related feature section above.
Digital Whine VST3 ID 123403319	Off, On	Off	Automatable	Host-automatable control for Digital Whine. Its full range and default are shown in this table; use it with the related feature section above.
Hiss VST3 ID 3202849	Off, On	Off	Automatable	Host-automatable control for Hiss. Its full range and default are shown in this table; use it with the related feature section above.
Low Rumble VST3 ID 1092091653	Off, On	Off	Automatable	Host-automatable control for Low Rumble. Its full range and default are shown in this table; use it with the related feature section above.
Reduction VST3 ID 2039460467	0 to 100	70	Automatable	Sets how strongly the named process affects the signal.

Documentation basis

Prepared from the current public catalog, current local product brief and implementation notes where available, existing English manuals where available, and a direct scan of the installed VST3 host contract. Internal implementation details that are not user-facing are intentionally excluded; all user-facing features and host-visible controls are documented.