



TB AUDIO PLUG-INS
Team Impulse Impact

USER MANUAL

TB Tune

Musical Pitch Correction

Real-time monophonic pitch correction that keeps a vocal in your key and scale, and lets ambiguous notes follow the direction of the melody.

16 scales

Auto Musical note choice

Formant ± 6 semitones

Real-time, monophonic



Contents

- 01 Overview
- 02 Quick start
- 03 Interface
- 04 Controls
- 05 Presets
- 06 Recipes
- 07 Tips and troubleshooting
- 08 Parameter reference
- 09 Version history
- 10 Support and license

01 Overview


TB Tune is a real-time pitch corrector for a single voice. It keeps the performance inside the key and scale you choose, with a more musical sense of direction than simply snapping to the nearest note.

When a sung note lands between two scale notes, **AUTO MUSICAL** considers the previous stable note and the direction of the melody before it chooses the target, so rising lines can keep rising and falling lines can keep falling. Each decision stays fixed for the whole note. **FORMANT** changes the vocal character without moving the corrected note.

Key features

- Key wheel for the 12 keys, and 16 scales from Major to Diminished
- **AUTO MUSICAL** sets how often ambiguous notes follow the melodic direction
- **FORMANT** from -6 to +6 semitones, independent of the corrected pitch
- Pitch-status display with the input note, target note, cents offset, and voicing
- Init and user presets

Signal flow



About this manual

This manual describes TB Tune 2.1.0 for Windows (VST3). The current macOS build is version 1.0.4 and may differ from the descriptions here.

02 Quick start

- 1 Insert TB Tune on a solo vocal or another monophonic, pitched track.
- 2 Click the song's key on the **KEY** wheel. The default is C.
- 3 Choose a scale group (MODES, MINOR, PENTA, or SYM), then the scale. The default is Major (Ionian).
- 4 Play the track and watch the display: INPUT shows the detected note, TARGET the note it is corrected to.
- 5 Raise **AUTO MUSICAL** if the correction picks the wrong neighbour on fast or sliding lines.

- 6 Adjust **FORMANT** only if you want a darker or brighter character.

03 Interface



TB Tune 2.x interface (portfolio image).

Area	What it does
KEY wheel	The 12 keys. Click a note to set the song key.
AUTO MUSICAL	How often an ambiguous note follows the melodic direction. Double-click to type a percentage.
Scale groups	MODES, MINOR, PENTA, and SYM tabs show the scales in each group.
Pitch display	TARGET shows the note being corrected to and its cents offset; INPUT shows the detected note.
FORMANT	Vocal character shift. Double-click to type a value in semitones.
SCALE	The selected scale and the scale buttons of the current group.
VOICED	Lights when a voiced, pitched input is detected.

04 Controls

Control	Range · default	What it does
KEY	C, C#, D, D#, E, F, F#, G, G#, A, A#, B · C	The song key: the root of the scale that correction targets. A wrong key pulls correct notes to other pitches.
SCALE	16 scales · Major (Ionian)	The set of notes that correction can target. Check which scale the melody and harmony actually use.
AUTO MUSICAL	0 to 100% · 0%	The chance that an ambiguous new note follows the detected melodic direction instead of the nearest scale note. High values can flatten intended drift and vibrato.

Control	Range · default	What it does
FORMANT	-6 to +6 st · 0 st	Shifts vocal character without moving the corrected note. 0 st preserves the character; negative is darker, positive is brighter.

Scales

Type	Scales
Major and minor	Major (Ionian), Natural Minor (Aeolian), Harmonic Minor, Melodic Minor Ascending
Pentatonic	Major Pentatonic, Minor Pentatonic, Blues
Modes	Dorian, Phrygian, Lydian, Mixolydian, Locrian
Symmetric	Chromatic, Whole Tone, Diminished Half-Whole, Diminished Whole-Half

Reading the pitch display

Display	Meaning
INPUT	The detected note of the incoming voice.
TARGET and cents	The note being corrected to, and how far the input is from it in cents.
NEAREST SCALE NOTE	The target was chosen as the nearest note of the scale.
AUTO MUSICAL CHOICE	Auto Musical chose the target from the melodic direction.
WAITING FOR VOICED INPUT	No pitched voice is detected, for example during silence, breaths, or noise.

TB Tune follows one voice at a time. Chords, doubled vocals, and heavy reverb confuse pitch detection, so use it on a dry, solo track.

05 Presets

Use the preset controls to step through presets, or open the list to choose Init or one of your user presets. Save stores the current settings as a .tbautotunepreset file. The name shows CUSTOM after you change a setting.

06 Recipes

Starting points for common jobs. Adjust them by ear.

Natural correction

A pop or rock lead vocal that should still sound human.

KEY / SCALE The song's key and scale

AUTO MUSICAL 0 to 30%

FORMANT 0 st

- 1 Check that the target notes match the melody before raising Auto Musical.

Fast, melismatic lines

Runs and slides where notes pass between scale steps.

AUTO MUSICAL 50 to 80%

- 1 Watch for AUTO MUSICAL CHOICE on the display while the run plays.

Minor-key song

A song in a minor key with raised leading tones.

SCALE Harmonic Minor or Melodic Minor
Ascending

- 1 Natural Minor has no raised seventh, so a raised seventh is corrected to a neighbouring note. Choose Harmonic Minor if the melody uses it.

Character shift

A darker or brighter voice for a double or a character.

FORMANT -3 to +3 st

- 1 Small values change character; large values sound processed.

07 Tips and troubleshooting

Symptom	What to check
Correct notes are pulled to wrong pitches.	KEY or SCALE does not match the song. Check both.
The display shows WAITING FOR VOICED INPUT.	The input is silent, unpitched, or too noisy. Use a dry, solo vocal.
Vibrato and expressive slides are flattened.	Lower AUTO MUSICAL, or check whether the scale has too few notes.
The voice sounds unnatural after correction.	Set FORMANT to 0 st and use a scale that fits the melody.
It does not work on a choir or chords.	TB Tune is monophonic. Use it on single-voice tracks.

08 Parameter reference

Panel label	Host parameter	Range	Default
KEY	Key	C to B (12 keys)	C
SCALE	Scale	16 scales	Major (Ionian)

Panel label	Host parameter	Range	Default
AUTO MUSICAL	Auto Musical	0 to 100%	0%
FORMANT	Formant Shift	−6 to +6 st	0 st

09 Version history

Version	Changes
2.1.0 · 2026-08-14	Redesigned the editor with a brighter key-and-scale workflow, a dedicated pitch-status panel, and higher-resolution controls. The pitch engine, parameter IDs, and saved-state compatibility are unchanged.
2.0.0 · 2026-08-09	Rebuilt the interface around direct key-note and scale selection with a dedicated pitch-status panel, expanded the scale choices, and made the Auto Musical and Formant controls easier to read.

10 Support and license

Report problems or request features at github.com/TaebeumKim/TB_Audio-Plugins/issues. Include the plug-in version, your DAW, and your operating system.

TB Audio plug-ins are free for personal and commercial work under the TB Audio Plug-ins Freeware License. If you release or monetize work made with them, add a credit such as **Made with TB Audio Plug-ins by Team Impulse Impact**. Selling or bundling the plug-ins is not allowed.

If the plug-ins help your music, you can support development at ko-fi.com/teamimpulseimpact.