


TB Recorder

DETAILED ENGLISH USER MANUAL

An insert-point capture utility with transparent passthrough, pause/resume, destination naming, automatic format conversion, and time-based file splitting.



Catalog version: 1.0.0

Documentation edition: 2026-08-04

Host-visible endpoints documented: 4

1. Product purpose

An insert-point capture utility with transparent passthrough, pause/resume, destination naming, automatic format conversion, and time-based file splitting.

A DAW bounce records a project output, not necessarily the exact signal at a particular insert. TB Recorder captures what reaches its plug-in position or standalone input while audio continues to pass through, making it useful for rehearsals, long sessions, processed stems, sound-design passes, and fast ideas.

What result it creates

- Exact insert-point recording
- Pause/resume without closing the temporary capture
- WAV, FLAC, AIFF, MP3, AAC, and Ogg delivery
- Automatic 1/5/10/30-minute or custom splitting

Signal flow

Input -> transparent passthrough and metering -> temporary lossless capture while Recording -> optional pause gaps excluded -> stop/finalize -> format conversion and splitting

2. Complete feature guide

Destination and file name

Choose a writable destination and clear file name before recording. The plug-in protects the live capture through a temporary file before final conversion.

Record, Pause, Resume, Stop

Record begins capture. Pause stops writing while passthrough and metering continue. Resume continues the same session. Stop finalizes and starts any required conversion/splitting.

Output Format

Choose WAV 32-bit float, FLAC 24-bit, AIFF 24-bit, MP3 320 kbps, AAC-LC 192 kbps, or Ogg Vorbis 320 kbps.

Split Length

Choose 1, 5, 10, or 30 minutes, Unlimited, or Custom. Custom Minutes ranges from 1 to 1440 and is used only when Custom is selected.

Pause-time behavior

Paused time is excluded from final duration and split calculation, preventing silent gaps from consuming segment length.

Passthrough and bypass

Recording does not intentionally change the signal that continues through the insert. Bypass behavior is host-dependent; avoid bypassing or removing the plug-in during an active capture.

3. Quick start

1. Choose the destination folder and base file name.

2. Select Output Format.
3. Set Split Length and Custom Minutes if needed.
4. Verify input meters and available disk space.
5. Press Record and confirm the recording state.
6. Use Pause/Resume when material should be excluded.
7. Press Stop and wait for finalization before closing the project.

4. Practical workflows

Long rehearsal

1. Choose FLAC 24-bit or WAV 32-bit float.
2. Set 30-minute or custom splitting.
3. Start before the session and monitor disk space.
4. Use Pause for long breaks.

Expected result: The rehearsal is preserved in manageable sequential files without recording break silence.

Processed stem capture

1. Place TB Recorder after the final insert to capture the processed signal.
2. Choose WAV 32-bit float.
3. Record the pass and stop only after tails finish.

Expected result: The exact insert output, including effects and tails, is captured for reuse.

5. Automation, gain staging, and session use

- Automate only controls that serve a clear musical transition. Fast movement of frequency, time, pitch, mode, oversampling, or algorithm selectors may intentionally create artifacts or require a host-safe transition.
- Match perceived loudness before judging quality. A louder setting will often appear better even when the processing decision is not better.
- Use the plug-in bypass endpoint for comparison and preserve an unprocessed source or earlier project version.
- Factory programs are starting points. Loading a program changes multiple parameters; save a new DAW preset after adapting it to the source.
- The parameter appendix is captured from the installed VST3 host contract. It lists every host-visible endpoint, its displayed range/options, default, automation status, and identifier.

6. Limits, cautions, and troubleshooting

- Do not quit the host or remove the plug-in before Stop/finalization completes.
- Lossy formats are unsuitable as the only archival master.
- Confirm destination permissions and free disk space before long recordings.
- No audible change: confirm the plug-in and relevant sub-block are enabled, Mix/Amount is not at a neutral value, and the source contains energy in the processed region.

- Unexpected level: return input, output, send, feedback, and parallel-mix controls to conservative values, then rebuild the setting one block at a time.
- Automation does not match the panel: reload the project, confirm the DAW is addressing the current plug-in version, and check whether a factory program or state recall replaced values.
- Clicks or transitions: avoid sample-instant changes to algorithm, time, pitch, mode, or oversampling selectors unless the sound is intentional.

7. Complete host parameter reference

This appendix contains all 4 parameters exposed by the current installed VST3 to a host. Repeated EQ-band endpoints are intentionally listed rather than collapsed. Discrete options are printed in full when the host contract exposes them.

Parameter	Range / options	Default	Host status	Function
Bypass VST3 ID 1652125811	Off, On	Off	Automatable; Bypass	Turns the complete plug-in processing path off or on through the host-visible bypass endpoint.
Custom Minutes VST3 ID 2082314286	1 to 1440	5	Not automatable	Sets automatic recording segment length or the custom duration used for splitting.
Output Format VST3 ID 1640331352	WAV 32-bit float, FLAC 24-bit, AIFF 24-bit, MP3 320 kbps, AAC-LC 192 kbps, OGG Vorbis 320 kbps	WAV 32-bit float	Not automatable	Sets or limits the final output level after the plug-in's main processing.
Split Length VST3 ID 404138973	1 min, 5 min, 10 min, 30 min, Unlimited, Custom	Unlimited	Not automatable	Sets automatic recording segment length or the custom duration used for splitting.

Documentation basis

Prepared from the current public catalog, current local product brief and implementation notes where available, existing English manuals where available, and a direct scan of the installed VST3 host contract. Internal implementation details that are not user-facing are intentionally excluded; all user-facing features and host-visible controls are documented.