# **Discrete Mathematical Models**

Lecture 9

Kane Townsend Semester 2, 2024

# Representing positives, negative and zero

# Representing positives, negative and zero

When writing positive and negative integers in binary, we may use a - or + in front of the integer to represent its sign.

We may write 
$$+(1101)_2$$
 for  $(13)_{10}$  and  $-(1101)_2$  for  $-(13)_{10}$ .

How can we, in a computer, represent integers in a range that includes negative integers?

1

# Naive approach

How can we, in a computer, represent integers in to a range that includes negative integers?

# Naive approach

How can we, in a computer, represent integers in to a range that includes negative integers?

FIRST IDEA: Use an extra **sign bit**. Fix a number of bits to use for each integer, and the left-most bit is 0 if the number is positive, and 1 is the number is negative.

In such a scheme with say, a byte to represent an integer:  $(00001101)_2 \text{ would represent } (13)_{10} \\ (10001101)_2 \text{ would represent } (-13)_{10} \\ \text{and } (00000000)_2 \text{ and } (10000000)_2 \text{ would both represent zero.}$ 

# Naive approach

How can we, in a computer, represent integers in to a range that includes negative integers?

FIRST IDEA: Use an extra **sign bit**. Fix a number of bits to use for each integer, and the left-most bit is 0 if the number is positive, and 1 is the number is negative.

In such a scheme with say, a byte to represent an integer:  $(00001101)_2 \text{ would represent } (13)_{10} \\ (10001101)_2 \text{ would represent } (-13)_{10} \\ \text{and } (00000000)_2 \text{ and } (10000000)_2 \text{ would both represent zero.}$ 

This is **NOT** how integers are usually represented.

#### A better idea

How can we, in a computer, represent integers in to a range that includes negative integers?

BETTER IDEA: Use an extra **sign bit**, but the binary representation of a negative is chosen according to a scheme called two's complement...

## Toggle plus one

We fix a number of bits, say t, to use for each integer. A string of t bits  $d_1d_2...d_t$  is interpreted as a number in one of two ways, depending on the value of  $d_1$ :

- if  $d_1 = 0$ , then the bit string  $(0d_2d_3 \dots d_t)$  represents  $(d_2d_3 \dots d_t)_2$
- if  $d_1=1$ , then the bit string  $(1d_2d_3\dots d_t)$  represents  $(d_2d_3\dots d_t)_2-2^{t-1}$ , which is equivalent to  $-[(e_2e_3\dots e_t)_2+001_2]$  where

$$e_i = \begin{cases} 1, & \text{if } d_i = 0 \\ 0, & \text{if } d_i = 1. \end{cases}$$

The process of evaluating  $(1d_2d_3...d_t)_2$  is often described as: 'toggle' all bits, add one, then negate.

4

# **Example: 4-bit signed integers**

When we use nibbles to represent integers, then t = 4 and we have:

nibble	decimal value	nibble	decimal value
0000	0	1000	-8
0001	1	1001	-7
0010	2	1010	-6
0011	3	1011	-5
0100	4	1100	-4
0101	5	1101	-3
0110	6	1110	-2
0111	7	1111	-1

In this case, we say we are using 4-bit signed integers.

## **Example**

Suppose we represent integers using 4-bit signed integers. Which integer is represented by 1101?

## Example

Suppose we represent integers using 4-bit signed integers. Which integer is represented by 1101?

Since the first bit in the bit-string is one, 1101 represents a negative integer and that integer is

$$(101)_2 - 2^3 = 5 - 8 = -3$$

OR

Since the first bit in the bit-string is one, 1101 represents a negative integer and that integer is

- drop the first bit to get 101
- toggle all the bits to get 010
- add one to get 011.
- Convert to decimal to get 3
- Multiply by -1 to get that 1101 represents  $(-3)_{10}$ .

## **Example: 8-bit signed integers**

When we use bytes to represent integers, then t=8 and we have:

nibble	decimal value	nibble	decimal value
00000000	0	10000000	-128
00000001	1	10000001	-127
0000010	2	10000010	-126
:	:	:	:
01111110	126	11111110	-2
01111111	127	11111111	-1

In this case, we say we are using **8-bit signed integers**.

## **Example**

Suppose we represent integers using 8-bit signed integers. Which integer is represented by 10110101?

## **Example**

Suppose we represent integers using 8-bit signed integers. Which integer is represented by 10110101?

Since the first bit in the bit-string is one, 1011010 represents a negative integer and that integer is

$$(0110101)_2 - 2^7 = ((1+4+16+32)-128)_{10} = (53-128)_{10} = (-75)_{10}.$$

OR

Since the first bit in the bit-string is one, 10110101 represents a negative integer and that integer is

- drop the bit to get 0110101
- toggle all the bits to get 1001010
- add one to get 1001011.
- Convert to decimal to get 1 + 2 + 8 + 64 = 75
- Multiply by -1 to get that 1101 represents  $(-75)_{10}$ .

## Comparison

Using the Naive approach with 8 bits:

• we can represent all integers in

$$\{-127, -126, -125, \dots, 127\}$$

- zero is represented by 00000000 and 100000000
- Designing processes for addition and subtraction is a hassle

# Comparison (cont.)

Using the two's complement approach with 8 bits:

• we can represent all integers in

$$\{-128, -127, -126, \dots, 127\}$$

- zero is represented only by 00000000
- Our usual addition process for positive numbers in binary works no matter whether the numbers are positive or negative.
- Converting 5, say, to -5 is an easy process: toggle all bits then add one.
- To accomplish x − y: Find the representation of −y from the representation for y; then add the representations for x and −y.

p	q	p-	+ q
1	1	1	0
1	0	0	1
0	1	0	1
0	0	0	0

р	q	p-	+ q
1	1	1	0
1	0	0	1
0	1	0	1
0	0	0	0

р	q	p+q		
		LB	RB	
1	1	1	0	
1	0	0	1	
0	1	0	1	
0	0	0	0	

р	q	p-	+ q
1	1	1	0
1	0	0	1
0	1	0	1
0	0	0	0


р	q	p+q		
		LB	RB	
1	1	1	0	
1	0	0	1	
0	1	0	1	
0	0	0	0	

р	q	p+q		
		$p \wedge q$	$p \oplus q$	
1	1	1	0	
1	0	0	1	
0	1	0	1	
0	0	0	0	

р	q	p-	+ q
1	1	1	0
1	0	0	1
0	1	0	1
0	0	0	0

р	q	p+q		
		LB	RB	
1	1	1	0	
1	0	0	1	
0	1	0	1	
0	0	0	0	

р	q	p+q		
		$p \wedge q$	$p \oplus q$	
1	1	1	0	
1	0	0	1	
0	1	0	1	
0	0	0	0	



This circuit is called a half adder (2 bits in, 2 bits out)

р	q	r	p+q	+ <i>r</i>
1	1	1	1	1
1	1	0	1 (	)
1	0	1	1 (	)
1	0	0	0	1
0	1	1	1 (	)
0	1	0	0	1
0	0	1	0	1
0	0	0	0 (	)

р	q	r	p+q+r		
1	1	1	1	1	
1	1	0	1	0	
1	0	1	1	0	
1	0	0	0	1	
0	1	1	1	0	
0	1	0	0	1	
0	0	1	0	1	
0	0	0	0	0	

_					
р	q	r	p+q+r		
			LB	RB	
1	1	1	1	1	
1	1	0	1	0	
1	0	1	1	0	
1	0	0	0	1	
0	1	1	1	0	
0	1	0	0	1	
0	0	1	0	1	
0	0	0	0	0	

CHALLENGE: Construct a circuit diagram for a circuit which implements the above (3 bits in, 2 bits out). We shall call such a circuit a **full adder**.

# Meaningful renaming of bits in a full adder

p	q	carry	carry	sum	
		in	out	out	
1	1	1	1	1	
1	1	0	1	0	
1	0	1	1	0	
1	0	0	0	1	
0	1	1	1	0	
0	1	0	0	1	
0	0	1	0	1	
0	0	0	0	0	

#### 4-bit addition via a cascade of full adders




Diagram extracted from "Concepts in Computing" course notes at Dartmouth College, Hanover, New Hampshire, USA, 2009. http://www.cs.dartmouth.edu/~cbk/classes/4/notes/19.php

# Circuits for integer subtraction

Since x-y is the same as x+(-y), we can accomplish integer subtraction provided we can convert y to -y (because we already know how to add).

Our clever way of representing negative numbers means

- the integer representation of an integer y can be converted to the integer representation of −y by toggling all bits and adding one.
- A NOT gate will toggle a single bit, and we already know how to build a circuit that adds, so we can build a circuit that adds one.

# Something amazingly neat

Our clever way of representing negative numbers means

- the usual algorithm (the step-by-step process) that works for adding two non-negative integers, works for adding two negative integers and for adding a non-negative integer and a negative integer
- the carry bit from the most significant place in an addition can be ignored.
- this will work provided that the sum is in the range of integers that can be represented by the number of bits we have chosen.

# **Examples**

#### 4-bit examples:

$$\begin{array}{rrr} 4 & 0100 \\ -6 & +1010 \\ \hline -2 & 1110 \end{array}$$

$$\begin{array}{rrr}
7 & 0 1 1 1 \\
-3 & +1 1 0 1 \\
\hline
4 & (1) 0 1 0 0
\end{array}$$

The carry bit in () is ignored.

#### 8-bit example:

$$\begin{array}{ccc} 81 & 0 & 1 & 0 & 1 & 0 & 0 & 0 & 1 \\ -98 & +1 & 0 & 0 & 1 & 1 & 1 & 1 & 0 \\ \hline -17 & 1 & 1 & 1 & 0 & 1 & 1 & 1 & 1 & 1 \end{array}$$

$$\begin{bmatrix} 81 = & 64 + 16 + 1 & \rightarrow 0101\,0001 \\ 98 = & 64 + 32 + 2 & \rightarrow 0110\,0010 \\ -98 \rightarrow 1001\,1101 + 1 \rightarrow 1001\,1110 \\ 1110\,1111 \rightarrow -(0001\,0000 + 1) \\ \rightarrow -0001\,0001 \rightarrow -17 \end{bmatrix}$$

# Multiplication

#### Example:

# Multiplication

Example:

Notice that no 'multiplication tables' are required since the only multiplications used are 'times 0' which results in all zeroes, and 'times 1' which has no effect.

# Multiplication

$$\begin{array}{c} & 1 & 0 & 1 & 1 \\ & \times & \frac{1}{0} & \frac{1}{0} & 0 & 0 & 0 \\ & + & 0 & 0 & 0 & 0 & 0 \\ & + & 1 & 0 & 1 & 1 & 0 & 0 \\ \hline & 1 & 0 & 0 & 0 & 0 & 1 & 0 & 0 \\ \hline & 1 & 1 & 1 & 1 & 1 & 1 & 1 \end{array}$$

Notice that no 'multiplication tables' are required since the only multiplications used are 'times 0' which results in all zeroes, and 'times 1' which has no effect.

This is one of the bonuses of using binary in computers.

## Multiplication by shifts and additions

For computer implementation of multiplication (within  $\mathbb{N}$ ) we only need a 'shift' circuit (to move bits left and append a zero on the right) and addition circuits.

But we also need an algorithm to control the process.

An **algorithm** is a sequence of operations on an input. The result is called an output.

Examples: Addition, subtraction, multiplication, division.

## Example

Here is very simple list processing algorithm, set out using a standard format for displaying algorithms:

```
Input: L: a list of students.
```

**Output:** O: list of students who have submitted their assignment.

#### Method:

```
Set j=1, O= empty list. (Initialization phase)

Loop: If j= length(L) + 1, stop.

If L[j] (the j-th element in L) has submitted the assignment, append L[j] to O.

Replace j by j+1.
```

# Algorithm for binary addition

This algorithm formalizes the method described earlier, which is implemented with a cascade of full adders.

Contrary to notation used in some earlier examples, in this context it is usual to *number the bits starting from the rightmost bit, which is called the 0-th bit.* 

So the leftmost bit of an n-bit number is its (n-1)-th bit.

Example: For the number 01101001 we have

0	1	1	0	1	0	0	1
$\uparrow$							
7-th	6-th	5-th	4-th	3-th	2-th	1-th	0-th
bit							

## Algorithm for binary addition

```
Input: Two numbers p,q in base 2 with n bits. 

Output: The sum s=p+q in base 2 with n+1 bits. 

Method: 

Set j=0, c=0, and the n-th bits of p and q to 0. 

Loop: If j=n+1 stop. 

Add the j-th bits of p and q plus c. 

Store the result part as the j-th bit of s. 

Store the carry part as c (replacing the old value of c). 

Replace j by j+1. 

Repeat loop
```

Example: Add p = 0110 and q = 1111 with n = 4.

**Input:** Two numbers p, q in base 2 with n bits.

**Output:** The sum s = p + q in base 2 with n + 1 bits.

Method:

Set j = 0, c = 0, and the *n*-th bits of *p* and *q* to 0.

Loop: If j = n + 1 stop.

Add the j-th bits of p and q plus c.

Store the result part as the j-th bit of s.

Store the carry part as c (replacing the old value of c).

Replace j by j + 1.

Repeat loop

# Algorithm for binary multiplication

This algorithm formalises the method described earlier, except that addition is done progressively rather than at the end.

The additions may be done by the algorithm of the previous frame.

This algorithm also assumes the existence of a shift algorithm, which shifts all the bits of a number one place to the left and then fills the vacant rightmost place with a 0.

# Algorithm for binary multiplication

```
Input: Two numbers x, y in base 2 with n bits. 

Output: The product p = x \times y in base 2 with 2n bits. 

Method:

Set j = 0 and p = 0.

Loop: If j = n stop.

If the j-th bit of y is 1 then replace p by p + x.

Shift x.

Replace j by j + 1.
```

Example: Multiply x = 1111 by y = 0110 with n = 4.

**Input:** Two numbers x, y in base 2 with n bits.

**Output:** The product  $p = x \times y$  in base 2 with 2n bits.

#### Method:

Set j = 0 and p = 0.

Loop: If j = n stop.

If the *j*-th bit of y is 1 then replace p by p + x.

Shift x.

Replace j by j + 1.

Repeat loop.