Account Receivables(AR)/Subledger Accounting(XLA)/General Ledger(GL)主要檔案關聯圖 Account Receivables(AR) Subledger Accounting(XLA) General Ledger(GL) xla.XLA TRANSACTION ENTITIES(xte) RA CUST TRX LINE GL DIST ALL **ENTITY ID *APPLICATION ID = 222 AR立帳 - ENTITY CODE **CUST TRX_LINE_GL_DIST_ID GL IMPORT REFERENCES - SOURCE ID INT 1/TRANSACTION NUMBER - EVENT ID - LEDGER ID - CUSTOMER TRX ID - GL SL LINK ID - CUSTOMER TRX LINE ID GL SL LINK TABLE (=' XLAJEL') XLA_EVENTS(xe) - JE HEADER ID - JE LINE NUM **APPLICATION ID AR CASH RECEIPT HISTORY ALL **EVENT ID - ENTITY ID AR收款 - EVENT TYPE CODE **CASH RECEIPT HISTORY ID - EVENT STATUS CODE / PROCESS STATUS CODE - EVENT ID - CASH RECEIPT ID Journal Import成功 Create Accounting xah.GL_TRANSFER_STATUS_CODE = 'Y' AR RECEIVABLE APPLICATIONS ALL XLA AE HEADERS(xah) AR沖銷(包括收款/Credit Memo沖銷) **AE HEADER ID **RECEIVABLE APPLICATION ID **APPLICATION ID **GL JE HEADERS** - EVENT ID - EVENT ID - CASH RECEIPT HISTORY ID - GL TRANSFER STATUS CODE **JE HEADER ID - CUSTOMER TRX ID (credit memo) - JE_SOURCE (=' Receivables') - APPLIED CUSTOMER TRX ID XLA AE LINES(xal) - APPLIED CUSTOMER TRX LINE ID **AE HEADER ID **AE LINE NUM **APPLICATION ID AR MISC CASH DISTRIBUTIONS ALL GL SL LINK ID / GL SL LINK TABLE (=' XLAJEL') - GL TRANSFER MODE CODE **GL JE LINES** 雜項收款 - CODE COMBINATION ID **MISC CASH DISTRIBUTION ID - ENTERED DR/ENTERED DR **JE HEADER ID - EVENT ID - ACCOUNTED DR/ACCOUNTED CR - CASH RECEIPT ID **JE LINE NUM - GL SL LINK ID XLA DISTRIBUTION LINKS(xdl) GL SL LINK TABLE - ENTERED DR/ENTERED DR AR ADJUSTMENTS ALL **APPLICATION ID ACCOUNTED DR/ACCOUNTED CR **AE HEADER ID (+REF AE HEADER ID/TEMP LINE NUM) AR帳款調整 - AE LINE NUM **ADJUSTMENT ID - EVENT ID - EVENT ID - SOURCE DISTRIBUTION ID NUM 1 - CUSTOMER TRX ID/CUSTOMER TRX LINE ID - APPLIED TO SOURCE ID NUM 1 - RECEIVABLES TRX ID - UNROUNDED ENTERED DR/UNROUNDED ENTERED CR - UNROUNDED ACCOUNTED DR/ UNROUNDED ACCOUNTED CR AR DISTRIBUTIONS ALL