


Deploy Autopilot SDK to AEM cloud as local dependency

1. Add be-ixf-java-sdk to core project

- In core project, create a folder call libs
- add be-ixf-java-sdk-11.jar file as shown in below image
- **Note - don't forget to commit be-ixf-java-sdk-11.jar to cloud**



2. Add Autopilot configuration to the core/pom.xml

core/pom.xml

```
<configuration>
  <bnd><![CDATA[
    Import-Package: javax.annotation;version=0.0.0,*
    -includeresource: be-ixf-java-sdk-11.jar
    Bundle-ClassPath: ., be-ixf-java-sdk-11.jar</bnd>
  </configuration>
```

core/pom.xml after update:

```
35  <plugin>
36    <groupId>biz.aQute.bnd</groupId>
37    <artifactId>bnd-maven-plugin</artifactId>
38    <executions>
39      <execution>
40        <id>bnd-process</id>
41        <goals>
42          <goal>bnd-process</goal>
43        </goals>
44        <configuration>
45          <bnd>
46            <![CDATA[
47      Import-Package: javax.annotation;version=0.0.0,*
48      -includeresource: be-ixf-java-sdk-11.jar
49      Bundle-ClassPath: ., be-ixf-java-sdk-11.jar
50            ]]>
51          </bnd>
52        </configuration>
53      </execution>
54    </executions>
55  </plugin>
```

3. Add be-ixf-java-sdk dependency to the core/pom.xml

core/pom.xml


```
<dependency>
  <groupId>com.brightedge</groupId>
  <artifactId>be-ixf-java-sdk</artifactId>
  <version>1.5</version>
  <scope>system</scope>
  <systemPath>${project.basedir}/libs/be-ixf-java-sdk-11.jar</systemPath>
</dependency>
```

core/pom.xml after update:

```
285⊖      <dependency>
286          <groupId>com.brightedge</groupId>
287          <artifactId>be-ixf-java-sdk</artifactId>
288          <version>1.5</version>
289          <scope>system</scope>
290          <systemPath>${project.basedir}/libs/be-ixf-java-sdk-11.jar</systemPath>
291      </dependency>
```

AEM Template Integration

1. Add BrightEdgeUtil class



2. Assign three variables headOpen, BodyString, and closeString with the respective methods.

```
package com.aem.customer.core.util;

import javax.annotation.PostConstruct;

@Model(adaptables = SlingHttpServletRequest.class,
defaultInjectionStrategy = DefaultInjectionStrategy.OPTIONAL)
public class BrightEdgeUtil {

    private IXFConfiguration ixfConfig;

    private String headOpen;
    private String bodyString;
    private String closeString;
    private String pagePath;
    private String hostname;
    private String country;

    @Self
    private SlingHttpServletRequest request;

    @Self
    private SlingHttpServletResponse response;

    @PostConstruct
    protected void init() throws Exception {
        String currenturl = request.getRequestURL().toString();

        IXFConfiguration ixfConfig = new IXFSDKConfiguration();
        ixfConfig.setProperty(IXFConfiguration.CAPSULE_MODE, IXFConfiguration.REMOTE_PROD_CAPSULE_MODE);
        ixfConfig.setProperty(IXFConfiguration.ACCOUNT_ID, "f00000000041543");
        ixfConfig.setProperty(IXFConfiguration.API_ENDPOINT, "https://ixfd1-api.bc0a.com/");

        // BE IXF: Update CHARSET if needed
        ixfConfig.setProperty(IXFConfiguration.CHARSET, "UTF-8");

        // BE IXF: By default, all URL parameters are ignored. If you have URL
        // parameters that add value to page content. Add them to this config value,
        // separated by the pipe character (|).
        ixfConfig.setProperty(IXFConfiguration.WHITELIST_PARAMETER_LIST, "ixf");
    }
}
```

```
// Log Level
// options:LOG_LEVEL_ALL,LOG_LEVEL_INFO,LOG_LEVEL_WARN,LOG_LEVEL_ERROR,LOG_LEVEL_DEBUG
ixfConfig.setProperty(IXFConfiguration.LOG_LEVEL, IXFConfiguration.LOG_LEVEL_ERROR);

// ixfConfig.setProperty(IXFConfiguration.PAGE_ALIAS_URL,"https://" +hostname+"/"+this.pagePath);
ixfConfig.setProperty(IXFConfiguration.PAGE_ALIAS_URL, currenturl);

// Optional parameters
// ixfConfig.setProperty(IXFConfiguration.PROXY_HOST, hostname);
// ixfConfig.setProperty(IXFConfiguration.PROXY_PORT, "1234");
// ixfConfig.setProperty(IXFConfiguration.PROXY_PROTOCOL, "https");

IXFSDKParameters parameters = new IXFSDKParameters(request);
IXFSDKClient client = new IXFSDKClient(ixfConfig, response, parameters);

headOpen = client.getHeadOpen();
bodyString = client.getBodyString("body_1");
closeString = client.close();
}

public IXFConfiguration getIxfConfig() {
    return ixfConfig;
}

public String getHeadOpen() {
    return headOpen;
}

public String getBodyString() {
    return bodyString;
}

public String getCloseString() {
    return closeString;
}
}
```

3. In the template, add the variables in the respective locations

```
<!doctype html>
<html>
<head>
<!-- BE IXF: BE IXF: Place getHeadOpen just inside of the head tag -->
<sly data-sly-use.
brightEdgeUtil="${com.aem.customer.core.util.BrightEdgeUtil'
@pagePath=currentPage.Path}"/>
${brightEdgeUtil.headOpen @context='unsafe'}
</head>
<body>
<footer>
<!-- BE IXF: The following <div> block needs to be placed in the location where the link block
will be displayed
BE IXF: For your website, the location is above/below ...-->
<div class="be-ix-link-block">
${brightEdgeUtil.bodyString @context='unsafe'}
${brightEdgeUtil.closeString @context='unsafe'}
</div>
</footer>
</body>
</html>
```

On-page Diagnostic Information

Upon successful integration, on-page diagnostic information

```
<!-- be_ixf, sdk, gho-->
<meta name="be:sdk" content="java_sdk_1.6.5" />
<meta name="be:timer" content="165ms" />
<meta name="be:norm_url" content="http://localhost:4502/content/brightedge-
plugin/test.html" />
<meta name="be:capsule_url" content="https://ixfd1-
api.bc0a.com/api/ixf/1.0.0/get_capsule/f00000000041543/1404993592" />
<meta name="be:api_dt" content="pny_2022; pnm_11; pnd_09; pnh_07; pnmh_31;
pn_epoch:1668007863136" />
<meta name="be:mod_dt" content="pny_1969; pnm_12; pnd_31; pnh_16; pnmh_00;
pn_epoch:0" />
<meta name="be:orig_url" content="http://localhost:4502/content/brightedge-
plugin/test.html" />
<meta name="be:messages" content="0" />
</head>
<body>
```