

User Manual and Access Guide

A docs-style reference for login, permissions, modules, workflows, and user actions across the full system.

English HTML



HTML

English PDF



PDF

COMPLETE USER MANUAL

HIVE.OS User Access and Module Guide

A fuller, more visual playbook for how users sign in, switch between central and tenant workspaces, understand what they can access, and use each visible feature across the system without missing major functionality.

AUDIENCE

Operators, tenant admins, central admins, support teams, auditors, and technical users who need a single source of truth.

GOAL

Make the system easier to navigate and explain not only where each module is, but what users can actually do inside it.

COVERAGE

Login, 2FA, navigation, dashboard, tenant management, security, audit, storage, settings, alerts, profile, API docs, and tools.

Generated: April 1, 2026

Source basis: active frontend and backend code in this repository

How to use this manual: start with the quick access map if you need orientation fast, then jump to the module section for the area you are working in. This version is intentionally more complete so that shared controls, hidden context rules, and smaller tool features are not left out.

DOCUMENTATION MAP

Navigate the manual by task, not just by page

Borrowing the feel of a product documentation portal, this jump menu groups the guide into onboarding, permissions, core modules, operations, and help so users can find the right section faster.

START HERE

Use these sections first if the reader needs orientation, login help, or a quick system map.

Contents overview

Quick access map

Sign-in and 2FA

Access model

SHARED EXPERIENCE

These sections explain the common interface and controls users see across the product.

Shared navigation and controls

Dashboard

Profile settings

API docs

ADMIN MODULES

Operational areas used by central admins, tenant admins, support, and security-focused users.

Tenant management

Identity and access

Audit logs

Settings

OPERATIONS AND HELP

Hands-on workflows, troubleshooting notes, and route-level reference for day-to-day system usage.

Storage workspace

Document converter

Common workflows

Troubleshooting and route matrix

1. Contents

SECTION	WHAT IT COVERS
2. Quick access map	Where modules live, who usually sees them, and what they are for.
3. Getting started	Central login, tenant login, 2FA, and what happens after sign-in.
4. Access model	Roles, permissions, central vs tenant visibility, and why menus differ between users.

SECTION	WHAT IT COVERS
5. Shared interface	Sidebar, mobile navigation, topbar, tours, alerts, theme, language, fullscreen, and profile menu.
6. Module playbook	Detailed usage notes for each module and major page.
7. Common workflows	Step-by-step examples for the tasks users are most likely to perform.
8. Troubleshooting	What to check when pages, buttons, or modules do not appear as expected.
9. Route and permission matrix	A final summary of routes, access rules, and notable actions.

2. Quick Access Map

HIVE.OS is a permission-aware, multi-context application. The same user may see a different menu depending on whether they are working in the central platform or inside a tenant node, and the same page may show different actions depending on the role attached to the session.

WORKSPACE	MAIN ROUTE	WHO USUALLY SEES IT	WHAT USERS DO THERE
Dashboard	/dashboard	Users with dashboard visibility	Overview metrics, alerts, live activity, quick actions, and context-sensitive summary cards.
Tenant Management	/dashboard/tenants	Central tenant administrators	Provision, inspect, suspend, reconfigure, and purge tenant nodes.
Identity & Access	/dashboard/security	Security and operations roles	Manage operators, access roles, and the permission dictionary.
Audit Logs	/dashboard/audit-logs	Auditors, admins, compliance users	Search live logs, inspect archived logs, set retention, archive records, and run exports.
Storage	/dashboard/storage	Users with storage management permission	Upload, organize, preview, edit, share, favorite, restore, and permanently delete files.
Settings	/dashboard/settings	Configuration owners	Manage brand, general settings, localization, and backups based on tab-level access.

WORKSPACE	MAIN ROUTE	WHO USUALLY SEES IT	WHAT USERS DO THERE
System Alerts	/dashboard/alerts	Users who can view alerts	Review critical, warning, and info alerts and dismiss them when permitted.
Profile Settings	/dashboard/profile	Any signed-in user	Update personal details, avatar, and two-factor authentication.
API Docs	/dashboard/api-docs	Technical users	Switch between central and tenant API testing modes and use interactive Swagger docs.
Document Converter	/dashboard/tools/document-converter	Storage-enabled power users	Upload HTML, use IDE mode, attach assets, generate PDFs, and save results back to storage.

CENTRAL CONTEXT

Central users can see cross-platform functions such as tenant management, global alerts, central dashboard metrics, and control-plane API testing.

TENANT CONTEXT

Tenant users work inside one node. Tenant-specific quick actions stay visible, while central-only modules such as tenant management are hidden.

WHY MENUS DIFFER

The UI checks permissions from the signed-in user object and only renders modules or actions that the current session is allowed to use.

FULL-ACCESS SHORTCUT

In the frontend permission helper, the roles **Super Admin** and **Admin** are treated as full-access roles for permission-gated UI.

3. Getting Started

3.1 CENTRAL SIGN-IN

1. Open the main HIVE.OS address for the environment you are using.
2. Go to `/sign-in`.
3. Enter the email address in the **System Identifier** field.
4. Enter the password in the **Encryption Key** field.
5. Select the login button to begin the authenticated session.

3.2 TENANT SIGN-IN

1. Open the tenant-specific hostname or subdomain.
2. The app automatically detects the tenant host and switches to tenant login mode.
3. Enter email and password as usual.
4. The session is validated against the tenant user endpoint instead of the central one.

Local tenant development is designed around subdomains such as `tenantapple.localhost`.

3.3 TWO-FACTOR AUTHENTICATION

- If 2FA is enabled for the user, the system redirects to the 2FA page after the first login step.
- The user enters a 6-digit authenticator code.
- If global 2FA is enforced and the user has not set it up yet, the page shows a QR code and manual secret key first.
- The same tenant-aware logic applies here, so tenant users confirm their 2FA against tenant verification endpoints.
- Users can abort the 2FA step and return to sign-in, but they cannot complete login without satisfying the security requirement.

Important: a user can authenticate successfully and still have limited access after login. Authentication and authorization are separate: the first proves identity, the second controls what the user can see and do.

3.4 WHAT HAPPENS AFTER SIGN-IN

- The app stores the access token, user record, and context information in local storage.

- The user is redirected to /dashboard.
- The dashboard shell periodically re-syncs the user session when navigation changes or the browser tab regains focus.
- If the token is missing or invalid, the app clears the session and sends the user back to sign-in.
- If the backend returns a critical access failure, the system can store a message and display it on the sign-in page after logout.

4. Access Model and Visibility Rules

The system decides what to show by combining role data, permission data, and session context. This is why two users looking at the same deployment can have very different navigation.

RULE	PRACTICAL MEANING FOR THE USER
Role and permission based navigation	Modules appear only if the current role includes one of the permissions required by that menu item.
Super Admin and Admin shortcut	These roles are treated as fully allowed by the frontend permission helper, so permission-gated controls are visible to them.
Central vs tenant session	The same user may see different modules depending on whether the app is running in central mode or tenant mode.
Tab-level access inside modules	For example, the Security page can show Operators, Roles, and Permissions tabs independently based on separate permissions.
Action-level access inside pages	A user may be allowed to view a table but not create, edit, export, archive, or delete records from it.

COMMON REASONS A MODULE IS HIDDEN

- The permission required by the navigation item is missing.

- The user is in tenant context and the module is central-only.
- The page is available but some inner tabs are restricted.

COMMON REASONS A BUTTON IS HIDDEN OR DISABLED

- The user has view access but not create, update, or delete access.
- The record is protected, such as some built-in roles or protected users.
- The current page mode, such as archived logs or trash, changes which actions are available.

5. Shared Interface and Common Controls

Desktop sidebar

The desktop sidebar is the main module launcher and can be collapsed or expanded.

ALWAYS IMPORTANT

- Shows the current brand logo or sidebar icon based on theme and collapse state.
- Supports collapsed and expanded navigation states.
- Shows primary navigation such as Dashboard, Tenant Management, Identity & Access, and Audit Logs when allowed.
- Shows secondary navigation such as Storage, Settings, and API Docs when allowed.

ADDITIONAL CONTROLS

- Includes an **Apps & Tools** expandable section where the Document Converter appears.
- Provides a **Disconnect Node** action for logout.
- Includes a theme switcher inside the sidebar itself.
- Participates in the guided tour flow.

Mobile navigation

On small screens, users open navigation through the mobile sidebar sheet.

- Search the menu directly from the mobile sidebar.
- See only the modules permitted for the session.
- Hide central-only Tenant Management automatically when the user is on a tenant node.

- Use disconnect and theme controls without leaving the menu.

Topbar controls

The topbar gives users fast access to system-wide helpers no matter which module they are in.

GLOBAL SEARCH

Search the ecosystem for users, nodes, settings, or logs without manually opening each page.

LANGUAGE SWITCHER

Switch the interface language using the current localization data published in the system.

THEME TOGGLE

Switch visual theme behavior directly from the topbar.

FULLSCREEN / FOCUS MODE

Expand the dashboard into fullscreen mode for concentrated work.

NOTIFICATIONS AND ALERTS

Open current system alerts and task notifications from the alert bell.

PROFILE MENU

Jump to Profile Settings or disconnect from the system.

Guided tours: major pages such as Dashboard, Tenant Management, Security, and Settings include manual tour buttons, and some tours auto-start on first visit to help new users learn the interface.

6. Module Playbook

ROUTE /DASHBOARD

PERMISSION VIEW_SYSTEM_DASHBOARD

CENTRAL AND TENANT

6.1 Dashboard

The dashboard is the launch point after login. It changes shape depending on whether the user is central or tenant-side.

WHAT ALL DASHBOARD USERS CAN DO

- See the current company or node label.
- Use the system tour button.
- Open stat cards that link deeper into security, tenants, and logs.
- Review the live audit panel.
- Use quick actions when the underlying permissions are present.

CONTEXT-SENSITIVE BEHAVIOR

- Central users see node counts, revenue intel, cluster health, traffic origins, and richer platform telemetry.
- Tenant users see tenant activity trends and tenant quick actions.
- If impersonation is active, the page shows a warning banner and a **Return to Admin** action.

DASHBOARD AREA	WHAT USERS CAN DO	WHO SEES IT	NOTES
Stat cards	Open linked modules such as Tenant Management, Security, and Audit Logs from high-level metrics.	All dashboard users	Cards reflect the active context and permissions.
Quick actions	Provision a node, invite an operator, open settings, or manage backups when the role allows it.	Permission-dependent	Buttons appear only when the associated permission is available.
Telemetry and module analytics	Review live telemetry and module views such as traffic, latency, or errors.	Mainly central users	The page maintains live visual telemetry state.
Revenue and cluster panels	Read MRR, plan mix, data size, Redis hit rate, and active websocket connections.	Central users	Used for platform-level oversight.
Traffic origins	See top origin locations and open a deeper analytics view when available.	Central users	Shows summarized location insight.

DASHBOARD AREA	WHAT USERS CAN DO	WHO SEES IT	NOTES
Alerts panel	Review current alerts and jump to the dedicated System Alerts page.	Central dashboard users	The dashboard shows a compact alert feed; the full page gives filtering and dismissal controls.
Tenant quick actions	Jump directly to invite operators or configure roles.	Tenant users	Designed to reduce navigation for common tenant tasks.
Live audit feed	See recent actions and open the complete audit log workspace.	All dashboard users	Central view can label the node that produced the event.

ROUTE /DASHBOARD/TENANTS

PERMISSIONS MANAGE_TENANTS OR VIEW_TENANTS

CENTRAL ONLY

6.2 Tenant Management

This is the central control workspace for provisioning and operating tenant nodes. It is intentionally blocked in tenant context.

- Search the tenant matrix by ID or organization name.
- Copy, export, print, or refresh the tenant table.
- Open tenant details to review node status, plan, domain, and Super Admin contact information.
- Provision a new tenant with name, plan, routing address, and Super Admin credentials.
- Toggle tenant network status between online and suspended when allowed.
- Enable or disable Super Admin login for the tenant.
- Reconfigure existing nodes.
- Purge tenant records and associated data when allowed.

High-impact actions: suspend, Super Admin access toggle, and purge are powerful operations. They should be limited to trusted administrators because they directly affect tenant availability and access.

6.3 Identity & Access

This page is tabbed. The available tabs are determined independently, so a user may see one, two, or all three tabs.

TAB	MAIN FUNCTIONS	VISIBILITY RULE	NOTES
Operators	Search, filter by status and role, filter by date range, create user, view details, edit, lock or unlock, impersonate, delete, export, print, copy, refresh.	manage_users or view_users	Central admins can impersonate users. Status toggle and purge actions depend on edit/delete permissions.
Access Roles	Create roles, edit capabilities, inspect details, search roles, export, print, copy, refresh.	manage_roles or view_roles	Core roles are protected; some built-in roles cannot be fully modified or deleted.
Permissions	Review permission codes, descriptions, scope, search the dictionary, export, print, copy, refresh.	view_permissions	This tab is a read-only capability dictionary.

OPERATORS TAB DETAILS

- Create or edit operator identities.
- Assign roles from the available role set.
- Filter by active or locked status.
- Filter by role and by date range.
- Inspect user details from the row action menu.
- Impersonate users when central permissions allow it.

ROLES TAB DETAILS

- Create new clearance levels.
- Search permissions while editing a role.
- Switch the permission picker between all, active, and available capabilities.
- Review capability counts and inspect saved role details.
- Protect high-risk roles such as Super Admin from normal modification.

6.4 Audit Logs

The audit workspace is split into active logs and archived logs, with additional permissions controlling export, archive, and archived-record deletion.

AREA	WHAT THE USER CAN DO	EXTRA PERMISSION	NOTES
Active Live Logs	Review current event records, filter results, inspect a record, and export current views when allowed.	Base page permission is enough to view	Designed for active operational visibility.
Cold Storage Vault	Review archived records and inspect their payloads.	Base page permission is enough to view archived results	Deleting archived records is separately protected.
Exports	Copy, print, and export the current table view.	export_logs	The export endpoint respects active filters and date ranges.
Archive controls	Set retention days and manually trigger the archive engine.	archive_logs	Moves eligible live logs to the vault.
Archive deletion	Delete one or many vaulted records.	delete_archived_logs	High-risk compliance-sensitive operation.

FILTERING AND FORENSIC REVIEW

- Search by description, module, or operator.
- Filter by event type, module, operator, node scope, and node identifier.
- Use quick date presets or manual start and end dates.
- Open a record to inspect the raw JSON payload block and metadata.

6.5 Storage and Media Workspace

Storage is more than a file list. It is a tenant-aware media workspace with upload, organization, preview, editing, sharing, favorites, and trash recovery features.

NAVIGATION AND ORGANIZATION

- Search files and folders from a single search box.
- Switch between grid and list layouts.
- Browse **All**, **Favorites**, **Recent**, and **Trash**.
- Use type filters for images, videos, documents, audio, archives, and other file types.
- Review storage usage and category metrics.

FOLDER AND FILE ACTIONS

- Create folders.
- Rename files and folders.
- Move items between folders.
- Send items to trash, restore them, empty trash, or permanently delete them.
- Mark files as favorites and generate share links.

FEATURE AREA	USER-FACING FUNCTIONS	WHY IT MATTERS	NOTES
Upload flow	Drag and drop files, choose upload folder, apply a base name, and optionally add a custom thumbnail for non-image files.	Supports controlled content ingestion.	The upload path uses chunked uploads for larger files.
Image preview and editing	Crop, resize, rotate, flip horizontally or vertically, adjust brightness, contrast, saturation, and hue, apply presets, remove background, remove logo background, reset edits, download, and save edited output.	Lets users improve images without leaving HIVE.OS.	Saved edits can be written back into the file system.
Video preview	Play video, navigate to next or previous video, use subtitles, and switch video versions when available.	Supports media review inside the system.	HLS playlists and poster thumbnails are supported.
Audio preview	Play audio, navigate through a playlist, and continue playback with the floating player.	Useful for media libraries and long-running listening sessions.	Audio integrates with the global audio provider.
PDF preview	Open PDF files directly in the built-in viewer.	Keeps document review inside the dashboard.	Useful for generated reports and uploaded documents.

FEATURE AREA	USER-FACING FUNCTIONS	WHY IT MATTERS	NOTES
Subtitle management	Attach .vtt subtitle files, assign language code and label, and delete subtitle tracks.	Improves video accessibility and localization.	Appears when working with video files.
Trash and recovery	Restore single items, restore multiple items, empty trash, or permanently delete items.	Supports recovery workflows and final clean-up.	The trash view has its own action set and messaging.

Good to know: the storage workspace also powers asset selection in other places such as brand settings and the converter, so users can reuse files already stored inside HIVE.OS instead of uploading them again.

ROUTE /DASHBOARD/SETTINGS

TAB-LEVEL PERMISSIONS

6.6 Settings

Settings is a tabbed workspace. The system shows only the tabs the current user can access.

TAB	MAIN FUNCTIONS	TYPICAL PERMISSION	NOTES
Brand Settings	Manage light and dark logos, favicon, sidebar icon, app title, footer text, primary color, typography, login background, auth welcome message, PDF logo, company tax ID, PDF header color, metadata, OG image, and watermark behavior.	manage_brand_settings	Users can upload new assets or choose existing ones from storage.

TAB	MAIN FUNCTIONS	TYPICAL PERMISSION	NOTES
General	Manage sender name, sender address, support email, support phone, timezone, currency, date format, time format, registration policy, global 2FA, maintenance mode, max upload size, session timeout, and live maintenance ticker message.	manage_general_settings	Maintenance ticker messaging is especially important for central lockout scenarios.
Localization	Add languages, set the default language, open translation files, edit source and target translations, add system keys, delete keys, delete languages, and publish the project.	manage_localization	Supports multi-file translation groups and live publishing.
System Backups	Review backup archive, schedule automated backups, trigger manual snapshots for database, files, or full system, download backups, and delete them.	view_backups or manage_backups	View and manage capabilities are separated.

BRAND TAB HIGHLIGHTS

- Visual identity for light mode and dark mode.
- Dedicated sidebar icon support.
- Login background and welcome message for the authentication portal.
- Document branding fields for exported PDFs and printed records.
- Metadata controls for white-label and sharing behavior.

BACKUPS TAB HIGHLIGHTS

- Daily, weekly, or monthly backup schedule options.
- Day-of-week or day-of-month control depending on frequency.
- Manual trigger buttons for database only, files only, or full system snapshots.
- Archive list showing automated vs manual backups.
- Download and delete controls for archived snapshots.

6.7 System Alerts

The alerts page gives a cleaner operational view than the compact dashboard alert card.

- Filter alerts by **All Events**, **Critical**, **Warnings**, and **Info**.
- Review title, description, severity styling, and relative time for each alert.
- Dismiss single alerts when management permission is available.
- Dismiss all alerts from one confirmation action when the user has alert management permission.
- Use the page as the operational follow-up point for alert counts seen on the dashboard and in the topbar.

6.8 Profile Settings

Profile Settings is the personal account workspace for the current operator.

ACCOUNT TAB

- Upload or replace the avatar.
- Choose an avatar using the embedded file manager picker.
- Update full name and email address.
- Save account changes.

SECURITY TAB

- Enable 2FA after confirming the current password.
- Scan the generated QR code.
- Confirm the 6-digit verification code.
- Receive recovery codes and copy them to the clipboard.
- Disable 2FA later with password confirmation.

Recovery code reminder: recovery codes are shown only at the moment setup finishes. Users should save them immediately because they are part of the account recovery path.

6.9 API Docs

This is an interactive Swagger workspace designed for technical users who need to test both central and tenant APIs from one place.

- Switch between **Central mode** and **Tenant mode**.
- Auto-fill the bearer token from local storage or paste a token manually.
- Set the tenant identifier used in X-Tenant when tenant mode is active.
- See a status message that confirms which mode and tenant value are currently active.
- Use interactive Swagger actions without leaving the dashboard.
- Open backend docs directly at `/api/docs`.
- Open the raw OpenAPI spec JSON from a quick link.

[ROUTE /DASHBOARD/TOOLS/CONVERTER](#)

[PERMISSION MANAGE_STORAGE](#)

[APPS AND TOOLS](#)

6.10 Document Converter

The converter turns HTML and related assets into PDF output and then lets the user save the generated document back to storage.

STEP	WHAT USERS CAN DO	WHY IT MATTERS	NOTES
Main document	Upload a local HTML file, select an HTML file from storage, or switch to IDE mode and author the document directly.	Supports both non-technical and technical users.	IDE mode starts with an editable <code>index.html</code> .
Extra assets	Upload supporting assets or pick them from storage.	Lets HTML documents reference local images, CSS, and similar files.	Useful for branded templates and richer layouts.
Engine settings	Choose paper size, orientation, print-background behavior, and margins.	Controls how the output PDF is rendered.	Supports common paper sizes such as A4, Letter, and Legal.

STEP	WHAT USERS CAN DO	WHY IT MATTERS	NOTES
Generate and review	Create the PDF and inspect it inside the built-in PDF viewer.	Keeps the generate-and-check loop inside HIVE.OS.	The page supports a tour and a final review state.
Save to Cloud	Save the generated PDF into the storage workspace.	Turns generated output into a managed system file.	Ideal for reusable reports or converted documents.

7. Common User Workflows

Workflow A. Sign in and complete 2FA

- 1 Open the correct central or tenant sign-in page.
- 2 Enter email and password, then submit the login form.
- 3 If prompted, open the authenticator app and enter the 6-digit code.
- 4 If forced setup appears, scan the QR code first and then confirm the first code.
- 5 After success, continue to the dashboard.

Workflow B. Invite a new operator

- 1 Open `/dashboard/security` and stay on the Operators tab.
- 2 Select the new operator button if it is visible for the role.
- 3 Enter identity details and assign the correct role.
- 4 Save the operator and verify they appear in the table.

Workflow C. Provision a tenant node

- 1 Open Tenant Management from the sidebar.
- 2 Select **Provision Node**.
- 3 Enter organization name, capacity plan, routing address, and Super Admin credentials.
- 4 Submit the form and confirm the node appears in the matrix.

Workflow D. Upload and manage a file

- 1 Open Storage.
- 2 Select the upload action or drag a file into the upload zone.
- 3 Choose the destination folder and optionally set a base name or custom thumbnail.
- 4 After upload, preview, rename, favorite, share, move, or trash the file as needed.

Workflow E. Enable 2FA from Profile Settings

- 1 Open Profile Settings from the topbar profile menu.
- 2 Switch to the Security tab.
- 3 Enter the current password to begin 2FA setup.
- 4 Scan the QR code and enter the verification code.
- 5 Copy and securely store the recovery codes.

Workflow F. Generate a PDF from the converter

- 1 Open the converter from **Apps & Tools**.
- 2 Load an HTML file, choose IDE mode, or select a cloud HTML document.
- 3 Add supporting assets if the HTML refers to local files.
- 4 Choose paper size, orientation, background printing, and margins.
- 5 Generate the PDF, review it, and save it to the storage workspace.

8. Troubleshooting

WHAT THE USER SEES	MOST LIKELY EXPLANATION	WHAT TO CHECK
A module is missing from the sidebar	The role lacks the required permission, or the user is in tenant context where the module is intentionally hidden.	Confirm the user role and whether the session is central or tenant.
The user lands back on sign-in	The token is missing, expired, or blocked.	Sign in again and verify the account is still active.
The 2FA page appears after entering password	The account requires 2FA, or global 2FA is enforced.	Complete the 2FA step or finish the first-time setup.
A page opens but some buttons are missing	The user has page visibility but not action-level permission.	Check whether create, edit, delete, export, archive, or manage permissions are assigned.
Settings shows only one tab	Settings access is tab-specific.	Verify which of the brand, general, localization, or backup permissions are assigned.
Tenant Management redirects away	The user is in tenant context or lacks tenant management rights.	Use a central session and verify <code>view_tenants</code> or tenant management permissions.

WHAT THE USER SEES	MOST LIKELY EXPLANATION	WHAT TO CHECK
Storage actions are unavailable	The user is missing the storage permission.	Verify <code>manage_storage</code> .
Alert dismissal buttons are disabled	The user can view alerts but cannot manage them.	Verify <code>manage_alerts</code> .

9. Route and Permission Matrix

PAGE OR TOOL	ROUTE	MAIN VISIBILITY RULE	NOTABLE ACTIONS BEHIND EXTRA PERMISSIONS
Dashboard	<code>/dashboard</code>	<code>view_system_dashboard</code>	Quick actions depend on tenant, user, settings, and backup permissions.
Tenant Management	<code>/dashboard/tenants</code>	<code>manage_tenants</code> or <code>view_tenants</code>	Create, edit, suspend, Super Admin toggle, and delete all depend on finer tenant permissions.
Security - Operators	<code>/dashboard/security?tab=users</code>	<code>manage_users</code> or <code>view_users</code>	Create, edit, delete, status toggle, and impersonation are action-specific.
Security - Roles	<code>/dashboard/security?tab=roles</code>	<code>manage_roles</code> or <code>view_roles</code>	Create, edit, and delete require role management rights.
Security - Permissions	<code>/dashboard/security?tab=permissions</code>	<code>view_permissions</code>	Mainly read-only, plus table tools.
Audit Logs	<code>/dashboard/audit-logs</code>	<code>view_logs</code>	Export, archive, and archived deletion each require additional permissions.
Storage	<code>/dashboard/storage</code>	<code>manage_storage</code>	Also unlocks converter access and storage-backed asset pickers.
Settings - Brand	<code>/dashboard/settings?tab=brand</code>	<code>manage_brand_settings</code>	Asset management flows rely on storage-backed selection helpers.

PAGE OR TOOL	ROUTE	MAIN VISIBILITY RULE	NOTABLE ACTIONS BEHIND EXTRA PERMISSIONS
Settings - General	/dashboard/settings?tab=general	manage_general_settings	Controls registration, 2FA policy, maintenance mode, and session timeout.
Settings - Localization	/dashboard/settings?tab=localization	manage_localization	Language creation, deletion, publishing, and key maintenance happen here.
Settings - Backups	/dashboard/settings?tab=backup	view_backups or manage_backups	Triggering, scheduling, and deleting backups require management rights.
System Alerts	/dashboard/alerts	view_alerts	Dismissing one or all alerts requires manage_alerts.
Profile Settings	/dashboard/profile	Authenticated session	2FA enable and disable require password confirmation.
API Docs	/dashboard/api-docs	Available in dashboard navigation	Swagger actions depend on a valid bearer token and optional tenant header.
Document Converter	/dashboard/tools/converter	manage_storage	Save-to-cloud depends on successful PDF generation and storage upload.

This manual was generated from the current repository structure and active UI logic on April 1, 2026. It is designed as a fuller operational guide so that major user-facing functionality is documented in one place.