### Introduction to Lattice Surgery

Ben Criger

May 2, 2016


Why Do We Need Lattice Surgery?

Gates By Measurement

**Proper Lattice Surgery** 

## Why Do We Need Lattice Surgery?


Transversality is a great criterion for one-qubit gates. For CNOT gates, though, transversality introduces another dimension:




What do we do?

### **Braiding Recap**

By changing the measurement schedule, we can implement unitaries which we otherwise couldn't:



However, we'd much rather do this on non-defect codes:



To see how, we'll need to recap (introduce?) some stabilizer calculus.

We all know what happens when we act a Clifford gate on an n-qubit Pauli:

We all know what happens when we act a Clifford gate on an n-qubit Pauli:

What happens when we measure a Pauli?

 Measurement collapses the state into an eigenstate of the measured operator, so the stabilizer property is preserved.

We all know what happens when we act a Clifford gate on an n-qubit Pauli:

- Measurement collapses the state into an eigenstate of the measured operator, so the stabilizer property is preserved.
- If  $(-1)^b M$  (where M is the measured Pauli) is in the stabilizer, the bit b is returned.

We all know what happens when we act a Clifford gate on an n-qubit Pauli:


- Measurement collapses the state into an eigenstate of the measured operator, so the stabilizer property is preserved.
- If  $(-1)^b M$  (where M is the measured Pauli) is in the stabilizer, the bit b is returned.
- If M is not in the stabilizer, but commutes with the stabilizer, M enters the stabiliser, and the dimension of the stabilised subspace is reduced by 1/2.

We all know what happens when we act a Clifford gate on an n-qubit Pauli:

- Measurement collapses the state into an eigenstate of the measured operator, so the stabilizer property is preserved.
- If  $(-1)^b M$  (where M is the measured Pauli) is in the stabilizer, the bit b is returned.
- If M is not in the stabilizer, but commutes with the stabilizer, M enters the stabiliser, and the dimension of the stabilised subspace is reduced by 1/2.
- If M does not commute with the stabilizer, a new stabilizer is formed from M and the largest set of stabilizers which commute with M.

# H, P, CNOT By Measurement

It may help to see some examples (without classical correction):



## Logical Gates By Measurement

To perform Clifford operations, then, all we have to do is measure the logical Paulis of some stabilizer code.

