OnePlanet.

ONEPLANET MCP

Connect your AI tool

ENDPOINT
mcp.oneplanet.com/mcp
AUDIENCE
Customer quickstart

This guide explains how to connect an AI assistant to OnePlanet using MCP. Create an API key once, then follow the section for your tool.

1. Create a key

1. Sign in to OnePlanet.
2. Open **My Profile → API keys**.
3. If you do not see **API keys**, ask your OnePlanet administrator to enable the AI Connector for your account.
4. Select **Create key**.
5. Choose:

- **Workspaces** — the workspaces this key may access (you must be a member of each) - **Capabilities** — what the key may do (read-only by default; enable write access only if required) - **Expiry** — 30 days, 90 days, 1 year, or none

1. Copy the key immediately (`opk_…`). It is shown only once. If it is lost, revoke it and create a new key.

2. Connection details

Field	Value
Endpoint	`https://mcp.oneplanet.com/mcp`
Transport	Streamable HTTP
Authentication	`Authorization: Bearer <your-key>`

Please paste the endpoint and key as **plain text** (Ctrl+Shift+V, or right-click → Paste as plain text). Copying from email, chat, or documents can introduce hidden characters that prevent a successful connection.

3. Claude in the browser (claude.ai)

Available on Free, Pro, Max, Team, and Enterprise plans. Free plans support one custom connector. On Team and Enterprise plans, an Owner typically adds the connector for the organisation first.

Pro, Max, and Free

1. Open https://claude.ai and sign in.
2. Go to **Customize → Connectors**.
3. Select **+ Add → Add custom connector**.
4. Enter a name, for example `OnePlanet` .
5. For the remote MCP server URL, paste `https://mcp.oneplanet.com/mcp` as plain text, then select **Continue**.
6. Under **Authentication**, choose **No sign in** (OnePlanet authenticates with your API key).
7. Under **Request headers**:

- Header name: `Authorization` - Value: `Bearer opk_…` (include the word `Bearer` , a single space, then your key)

1. Select **Add**.
2. In a conversation, open **+ → Connectors** and enable **OnePlanet** for that chat.

Team and Enterprise

1. As an Owner, go to **Organization settings → Connectors → Add → Custom → Web**.
2. Enter the name and URL `https://mcp.oneplanet.com/mcp` , then continue.

3. Choose **No sign in**, add the Request header `Authorization` with value `Bearer opk_…`, then select **Add**.
4. Each member opens **Customize** → **Connectors**, selects **Connect** next to OnePlanet, and enables it from the chat **+** menu.

If **Request headers** is not available in your organisation, please use Cursor or Claude Desktop (section 5).

---

4. ChatGPT (browser)

Custom MCP apps in ChatGPT require **Developer mode** on the web. Availability depends on your plan (Plus, Pro, Business, Enterprise, or Education) and, for workspace accounts, administrator permission.

Enable Developer mode

1. Open https://chatgpt.com and sign in.
2. Go to **Settings** → **Apps** → **Advanced settings** (this may also appear under **Settings** → **Security and login**).
3. Turn on **Developer mode**.
4. For Business, Enterprise, or Education workspaces, an administrator may need to allow Developer mode or custom MCP connectors in workspace settings before the option appears for members.

Add OnePlanet

1. Open **Settings** → **Apps**, or start from the composer **+** menu and open Apps.
2. Select **Create** or **+** to create a developer-mode app.
3. Enter a name, for example `OnePlanet`.
4. For the MCP server URL, paste `https://mcp.oneplanet.com/mcp` as plain text.
5. For authentication, enter your OnePlanet key as `Bearer opk_…` in the access token, API key, or Authorization field provided.
6. Select **Scan tools** and wait for the scan to complete.
7. Select **Create**.
8. Start a new chat, open the tools or apps menu from **+**, and enable OnePlanet for that conversation.

Confirm the connection

Ask ChatGPT: **“List my OnePlanet workspaces.”** If tools do not appear, check that Developer mode is enabled, that your workspace allows custom MCP apps, and that the URL ends with `/mcp`.

---

5. Cursor or Claude Desktop

Use the same connection details in a configuration file. Replace the placeholder with your key, and paste as plain text.

```
{
  "mcpServers": {
    "oneplanet": {
      "type": "http",
      "url": "https://mcp.oneplanet.com/mcp",
      "headers": {
        "Authorization": "Bearer opk_live_your_key_here"
      }
    }
  }
}
```

Tool	Configuration location
Cursor	Settings → MCP, or `.cursor/mcp.json`. Save, then refresh until the server shows as connected.
Claude Desktop	`claude_desktop_config.json` via Settings → Developer → Edit Config. Quit Claude Desktop fully, then reopen.

6. Confirm the connection

In your AI tool, ask: **“List my OnePlanet workspaces.”** A successful response confirms that your key and connection are working. This request does not change any data.

7. Troubleshooting

Issue	What to try
Authentication error	Ensure the header is exactly `Bearer opk_…` once. Avoid `Bearer Bearer …` or a truncated key.
URL or settings look incorrect after pasting	Clear the field and paste again as plain text.
Request headers unavailable in Claude	Use Cursor or Claude Desktop (section 5).
Tools missing, or write actions declined	Confirm the key includes the required capabilities, and that your OnePlanet role allows the action. Create a new key if needed.
API keys tab not visible	Ask your administrator to enable the AI Connector.

8. Revoke a key

Go to **My Profile** → **API keys** → **Revoke**. Revocation takes effect on the next request. Please revoke a key immediately if it may have been shared or exposed.