

# Chapter 6

# Digital transmission through band-limited AWGN channels

— by Prof. XIAOFENG LI SCIE, UESTC



### 5 Hrs

ISI and zero-ISI condition

(Ref p380-381, p393-394)

 Design of BL signals for zero-ISI (Ref p396-399)

OFDM



Most channels are practically BAND-LIMITED. Examples such as,

- Subscribe-line in a standard telephone system is limited to 4kHz.
- Uplink channel in GSM is for data from mobile user to the base and is a bandpass channel limited to 200kHz.


The freq response of channel, C(f)

- 1. For BB, limited to some w, and C(f) = 0, |f| > W
- 2. For PB, limited to some w about its central freq f<sub>c</sub>, and


$$C(f) = 0$$
,  $\left| f - f_c \right| \le W/2$ 



Think about the channel with BW of WHz.



Think about the channel with BW of WHz.



Flat? Impossible!

Flat? If and only if H(t) is rect.

Flat? Many chances, once H(t) is complement about R<sub>s</sub>/2.

Think about the channel with BW of WHz.

Case 1: 
$$W < R_s/2$$

#### Conclusion for BL transmission:


A digital communication system for zero-ISI must meet R<sub>s</sub><2W

Ca Nyquist Rate: The maximum symbol rate for zero-ISI transmission over a WHz-channel is 2W baud.

The highest rate can only be reached when the overall system response h(t) is a LPF of WHz.

Flat? Impossible!

Flat? If and only if H(t) is rect.




Flat? Many chances, once H(t) is complement about R<sub>s</sub>/2.

In the design of BL systems for zero-ISI, Raised-Cosine (RC) spectrum is widely used for H(f).

A RC spectrum and its time response are defined by,

$$H_{RC}(f) = \begin{cases} \frac{1}{2f_0} & 0 \le |f| \le (1-\alpha)f_0 \\ \frac{1}{4f_0} \left\{ 1 + \cos \frac{\pi \left[ |f| - (1-\alpha)f_0 \right]}{2\alpha f_0} \right\} & (1-\alpha)f_0 < |f| \le (1+\alpha)f_0 \\ 0 & |f| > (1+\alpha)f_0 \end{cases}$$

respectively, where  $\alpha$  is called the roll-off factor and  $f_0=R_s/2$  called 6dB-BW.




In the design of BL systems for zero-ISI, Raised-Cosine (RC) spectrum is widely used for H(f).


A RC spectrum and its time response are defir

$$H_{RC}(f) = \begin{cases} \frac{1}{2f_0} \\ \frac{1}{4f_0} \left\{ 1 + \cos \frac{\pi \left[ |f| - (1 - \alpha)f_0 \right]}{2\alpha f_0} \right\} & (1 - \alpha) \end{cases}$$

respectively, where  $\alpha$  is called the roll-off factor and  $f_0$ =R<sub>s</sub>/2 called 6dB-BW.

$$h_{RC}(t) = \frac{\sin(2\pi f_0 t)}{2\pi f_0 t} \cdot \frac{\cos(2\pi\alpha f_0 t)}{1 - (4\alpha f_0 t)^2}$$







In the design of BL systems for zero-ISI, Raised-Cosine (RC) spectrum is widely used for H(f).

From the figure, we read  $W=(1+\alpha)R_s/2$ .  $\alpha$  controls the transition of the band. We note that:

- 1)Large  $\alpha$  gives a smooth transition and requires large BW, while small  $\alpha$  sharp transition and small BW.
- 2)The RC spectrum for  $\alpha=0$  is exactly the LPF and BW reaches the minimum.
- 3)The smoothness of transition band with non-zero  $\alpha$  is very important in practical implementation of filters.





# Example: a **passband** channel of 600<f<3600Hz, for 7200kbps transmission.

# Analysis:

- 1. fc=(3600+600)/2=2100(Hz)
- 2. W/2=3600-2100=1500

Make W/2>=Rs/2=[
$$7200$$
/log2(M)]/2 log2(M)>= $7200$ /(2\*1500)=2.4,



- Take W/2>= $(1+\alpha)$ Rs/2, that is 1500>=1200(1+ $\alpha$ ),  $\alpha$  <=1500/1200-1=5/4-1=1/4, Take a RC filter with  $\alpha$  =0.25
- 4. The spectral efficiency is: Rb/W=7200bps/3000Hz=2.4bps/Hz

