# **Chapter 6: Synchronization Tools**

# **Objectives**

- To introduce the critical-section problem, whose solutions can be used to ensure the consistency of shared data.
- To illustrate a race condition
- To present both software and hardware solutions of the critical-section problem.
  - Illustrate hardware solutions to the critical-section problem using memory barriers, compare-and-swap operations, and atomic variables
  - Demonstrate how mutex locks, semaphores, monitors, and condition variables can be used to solve the critical section problem.
- To explore several tools that are used to solve process synchronization problems.

### **Contents**

- 1. Background
- 2. The Critical-Section Problem
- 3. Peterson's Solution
- 4. Hardware Support for Synchronization
- 5. Mutex Locks
- 6. Semaphores
- 7. Monitors
- 8. Liveness
- 9. Evaluation

# **Background**

- CPU scheduler switches rapidly between processes to provide concurrent execution. This means that one process may only partially complete execution before another process is scheduled.
- In parallel execution, instruction streams representing different processes execute simultaneously on separate processing cores.

Concurrent or Parallel execution can contribute to issues involving the integrity of data shared by several processes.

In this chapter, we discuss various mechanisms to ensure the orderly execution of cooperating processes that share a logical address space, so that data consistency is maintained.

# **Cooperating Processes**

A cooperating process is one that can affect or be affected by other processes executing in the system.

#### Cooperating processes can:

- 1. either directly share a logical address space (that is, both code and data)
  - achieved through the use of threads
- 2. Or be allowed to share data only through files or messages.

The producer-consumer problem is a representative paradigm of many operating system functions.

A bounded buffer could be used to enable processes to share memory.

# Producer-consumer problem


The producer-consumer problem is a model of a system consisting of cooperating sequential processes or threads, all running asynchronously and possibly sharing data.


#### For example,


- A compiler may produce assembly code that is consumed by an assembler. The assembler, in turn, may produce object modules that are consumed by the loader.
- ➤ In client-server paradigm a web server produces (that is, provides) HTML files and images, which are consumed (that is, read) by the client web browser requesting the resource.

### Producer

- in indicates the next available position for depositing data.
- Waits if in+1 = out (buffer Full)
- Deposits a data items into in and advances the pointer in to in+1.







Current state:

in = 5 and out = 0

Producer:

in+1 = 6 out.
No wait needed.
produces an item
deposits in 5.
increments in to 5+1 =6

State:

in = 6 and out is still 0
(Assume consumer has not consumed any)

Producer:

in+1 = 7 out.
No wait needed.
produces an item
deposits in 6.
increments in to 6+1 =7

State:

in = 7; if out = 0,

Producer:


 $in+1 \mod 8 = 7+1 \mod 8$ = 0 =

out.

Buffer full.
Producer waits.


### Consumer

- out indicates the position that contains the next data to be retrieved.
- Waits if in = out (buffer Empty)
- Retrieves the data item in out and advances the pointer out+1.



if current state is: in = 5 out = 1


in out. Buffer not empty.
No need to wait.
Remove item from buffer 1,
consume it.
increment out to 1+1 =2



#### Continue

consuming and emptying buffers while incrementing **out.** current state: **in** = 5 **out** = 4 **in out.** 

Remove item from buffer 4, increment **out** to 4+1=5



State: **out**= 5. **in** is 5 **in** = **out**Buffer empty.
Consumer waits.

### First Producer-consumer problem

```
#define BUFFERSIZE 10
                                        typedef struct {...
Producer Process
                                        }item;
item next produced;
                                        Item buffer[BUFFER SIZE];
while (true) {
                                        int in = 0; // next free position
                                        int out = 0; // first full position
   /* produce an item */
   while (((in + 1)% BUFFER SIZE) == out); // do nothing
  buffer[in] = next produced;
   in = (in + 1) % BUFFER SIZE;
}
Consumer Process
item next consumed;
while (true) {
       while (in == out); // do nothing
                                             First bounded-buffer
       next consumed = buffer[out];
                                             solution is correct,
       out = (out +1) % BUFFER SIZE;
                                             but can only use
        /* consume the item */
                                             BUFFERSIZE-1 elements
```

### **New Solution for producer-consumer problem**

Suppose that we wanted to provide a solution to the producer-consumer problem that <u>fills the buffer</u>.

Modify the algorithm to by introducing a new integer variable count.

Count keeps track of the number of full buffers.

- incremented by the producer every time it adds a new item
- decremented by the consumer after it consumes an item.
- Producer and consumer routines shown next are correct separately.
- May not function correctly when executed concurrently, if not synchronized.

### **Producer-Consumer Problem**

Integer **count** keeps track of the <u>number of filled buffers</u>. initially, count = 0

```
If count = BUFFERSZE, then
buffer is full, n filled buffers
If buffer is full, no place to put item
Producer waits.
```

```
If count = 0, then
buffer is empty, no filled buffer
If buffer empty, nothing to
consume,
Consumer waits.
```

### **Race Condition**

```
count++ could be implemented as
      register1 = count
      register1 = register1 + 1
      count = register1
count -- could be implemented as
      register2 = count
      register2 = register2 - 1
      count = register2
Consider this execution interleaving with "count = 5" initially:
                                                                   {register1
    S0: producer execute register1 = count
    = 5}
    S1: producer execute register1 = register1 + 1
                                                          \{register1 = 6\}
    S2: consumer execute register2 = count
                                                          \{register2 = 5\}
                                                          \{register2 = 4\}
    S3: consumer execute register2 = register2 - 1
    S4: producer execute count = register1
                                                          \{count = 6\}
    S5: consumer execute count = register2
                                                          \{count = 4\}
```

#### Concurrent access to shared data may result in data inconsistency

Bounded Buffer problem with use of a counter that is updated concurrently by the producer and consumer may lead to race condition.

### **Race Condition & Critical section**

- A race condition occurs when
  - Multiple processes access and manipulate same data concurrently
  - Outcome of execution depends on the particular order in which the access takes place.
- Critical section/region
  - the segment of code where process modifying shared/common variables (tables, files)
- Critical section problem, mutual exclusion problem
  - No two processes can execute in critical sections at the same time

# **Processes be Synchronized**

To guard against the race condition above, we need to ensure that only one process at a time can be manipulating the variable count.

To make such a guarantee, we require that the **processes be** synchronized in some way.

### **Critical Section Problem**

Consider system of n processes  $\{p_0, p_1, \dots p_{n-1}\}$ 

Each process has critical section segment of code

Process may be changing common variables, updating table, writing file, etc

When one process in critical section, no other may be in its critical section

Critical section problem is to design protocol to solve this

Each process must ask permission to enter critical section in entry section, may follow critical section with exit section, then remainder section

### **Critical Section**

```
General structure of process P_i
```

```
entry section
critical section


exit section
remainder section
} while (true);
```

### **Solution to Critical-Section Problem**

- 1. Mutual Exclusion If process  $P_i$  is executing in its critical section, then no other processes can be executing in their critical sections
- 2. **Progress** If no process is executing in its critical section and some processes wish to enter their critical sections, then only those <u>processes</u> that are <u>not executing in their remainder sections</u> can participate in the <u>deciding</u> which will enter its critical section <u>next</u>, and this <u>selection</u> cannot be postponed indefinitely
- 3. **Bounded Waiting** There exists a bound, or limit, on the <u>number of times</u> that <u>other</u> processes are <u>allowed</u> to enter their critical sections <u>after a process</u> has made a <u>request</u> to enter its critical section and before that request is granted
  - Assume that each process executes at a nonzero speed
  - No assumption concerning relative speed of the n processes

# Race condition in kernel-mode processes

Processes  $P_0$  and  $P_1$  are creating child processs using the fork() system call Race condition on kernel variable next\_available\_pid which represents the next available process identifier (pid)



Unless there is a mechanism to prevent  $P_0$  and  $P_1$  from accessing the variable  $next_available_pid$  the same pid could be assigned to two different processes!

### **Interrupt-based Solution**

The critical-section problem could be solved simply in a single-core environment if we could prevent interrupts from occurring while a shared variable was being modified.

Can some processes starve – never enter their critical section?

What if the critical section is code that runs for an hour?

This solution is not as feasible in a multiprocessor environment.

Disabling interrupts on a multiprocessor can be time consuming, since the message is passed to all the processors

# Critical-Section handling in OS

Two general approaches are used to handle critical sections in operating systems: preemptive kernels and nonpreemptive kernels.

#### 1. Preemptive kernels

A preemptive kernel allows a process to be preempted while it is running in kernel mode.

Must be carefully designed to ensure that shared kernel data are free from race conditions.

A preemptive kernel may be more responsive, since there is less risk that a kernel-mode process will run for an arbitrarily long period before relinquishing the processor to waiting processes.

A preemptive kernel is more suitable for real-time programming

#### 2. Non-preemptive kernels

A nonpreemptive kernel does not allow a process running in kernel mode to be preempted; a kernel-mode process will run until it exits kernel mode, blocks, or voluntarily yields control of the CPU.

A nonpreemptive kernel is essentially free of race conditions in kernel mode as only one process is active in the kernel at a time.

### **Peterson's Solution**

A classic software-based solution to the critical-section problem.

- Not guaranteed to work on modern architectures, but good algorithmic description of solving the critical-section problem
- Restricted to two processes that alternate execution between their critical sections and remainder sections

Assume that the **load** and **store** machine-language instructions are atomic; that is, cannot be interrupted

The two processes share two data items:

# Algorithm for Process Pi

- 1. To enter the critical section, process Pi first sets flag[i] to be true and then sets turn to the value j, thereby asserting that if the other process wishesto enter the critical section, it can do so.
- 2. If both processes try to enter at the same time, turn will be set to both i and j at roughly the same time, but one will be overwritten immediately. The eventual value of turn determines which of the two processes is allowed to enter its critical section first.

```
while (true) {
    flag[i] = true;
    turn = j;
    while (flag[j] && turn == j);
    // enters CS if flag[j] == false or if turn ==I

    /* critical section */
    flag[i] = false;
    /* remainder section */
}
```

# Process P<sub>j</sub>

```
// turn == i means Pi's turn to enter its critical section
int turn;
boolean flag[2]; // flag[j] true, Pj is ready to enter its critical section
         while (true) {
                 flag[j] = true;
                 turn = i;
                 while (flag[i] && turn == i);
                 /* critical section */
                 flag[j] = false;
                 /* remainder section */
```

### **Correctness of Peterson's Solution**

Provable that the three CS requirement are met:

1. Mutual exclusion is preserved.

**P**<sub>i</sub> enters CS only if:

either flag[j] = false or turn = i

- If both processes can be executing in their critical sections at the same time, then flag[0] == flag[1] == true. Not possible.
- Value of turn can be either i or j, but cannot be both
- 2. Progress requirement is satisfied
- 3. Bounded-waiting requirement is met

Since Pi does not change the value of the variable turn while executing the while statement, Pi will enter the critical section (progress) after at most one entry by Pj (bounded waiting)

#### Peterson's Solution and Modern Architecture

Although useful for demonstrating an algorithm, Peterson's Solution is not guaranteed to work on modern architectures.

To improve performance, processors and/or compilers may reorder operations that have no dependencies

Understanding why it will not work is useful for better understanding race conditions.

- 1. For single-threaded this is ok as the result will always be the same.
- 2. For multithreaded the reordering may produce inconsistent or unexpected results!

# **Modern Architecture Example**

#### Two threads share the data:

```
boolean flag = false;
int x = 0;
```

Thread 1 performs

```
while (!flag)
;
print x
```

Thread 2 performs

$$x = 100;$$
 flag = true

What is the expected output?

100


# Modern Architecture Example (Cont.)

However, since the variables flag and x are independent of each other, the instructions:

```
flag = true; x = 100;
```

for Thread 2 may be reordered If this occurs, the output may be 0!

### **Effects of instruction reordering in Peterson's Solution**



This allows both processes to be in their critical section at the same time!

To ensure that Peterson's solution will work correctly on modern computer architecture we must use **Memory Barrier**.

# **Synchronization - Hardware**

Many systems provide hardware support for implementing the critical section code.

Uniprocessors – could disable interrupts

Currently running code would execute without preemption

Generally too inefficient on multiprocessor systems

Operating systems using this not broadly scalable

We will look at three forms of hardware support:

- 1. Memory barriers
- 2. Hardware instructions
- 3. Atomic variables

# **Memory Barriers**

System may reorder instructions. This leads to unreliable data states.

**Memory model** are the memory guarantees a computer architecture makes to application programs.

Memory models may be either:

- ► Strongly ordered where a memory modification of one processor is immediately visible to all other processors.
- ► Weakly ordered where a memory modification of one processor may not be immediately visible to all other processors.

A memory barrier is an instruction that forces any change in memory to be propagated (made visible) to all other processors.

# **Memory Barrier Instructions**

When a memory barrier instruction is performed, the system ensures that all loads and stores are completed before any subsequent load or store operations are performed.

Therefore, even if instructions were reordered, the memory barrier ensures that the store operations are completed in memory and visible to other processors before future load or store operations are performed.

In parallel computing, a barrier is a type of synchronization method.

A barrier for a group of threads or processes in the source code means any thread/process must stop at this point and cannot proceed until all other threads/processes reach this barrier.

# **Memory Barrier Example**

Returning to the example of slides 6.26 - 6.27

We could add a memory barrier to the following instructions to ensure Thread 1 outputs 100:

#### Thread 1 now performs

```
while (!flag)
         memory_barrier();
print x
```

• For Thread 1 we are guaranteed that that the value of flag is loaded before the value of  $\underline{x}$ .

#### Thread 2 now performs

```
x = 100;
memory_barrier();
flag = true
```

• For Thread 2 we ensure that the assignment to  $\underline{\times}$  occurs before the assignment  $\underline{flag}$ .

### **Hardware Instructions**

Special hardware instructions that allow us to either *test-and-modify* the content of a word, or two *swap* the contents of two words atomically (uninterruptedly.)

**Test-and-Set** instruction

Compare-and-Swap instruction

### test\_and\_set Instruction

#### Definition:

- Executed atomically
  - Lock the memory bus, loadBus lock
- Thus, if two test and set() instructions are executed simultaneously (each on a different CPU), they will be executed sequentially in some arbitrary order.
- If the <u>machine supports the test and set()</u> instruction, then we can implement mutual exclusion by declaring a boolean variable lock, initialized to false.

### Mutual-exclusion implementation with test\_and\_set()

- test\_snd\_set() is atomic
- if lock = true, busy wait

```
boolean test_and_set (boolean *target)
{
          boolean rv = *target;
          *target = true;
          return rv:
}
```

Shared boolean variable lock:

Lock is false: no process is in critical section

Lock is true: one process is in critical seriolly, lock = false.

- 2. First process passes 'false' to test\_and\_set()
  - i. Sets lock to true, so no other process can execute
  - ii. Returns the passed 'false', so this process can enter the critical section.

Process exits 'while loop' if returned value (of test\_and\_set) is false. Process then:

- i. completes critical section
- ii. sets lock to false, so the next process can enter critical section

# compare\_and\_swap Instruction

- 1. Executes atomically
- 2. Returns the original value of passed parameter value
- 3. Set the variable value the value of the passed parameter new\_value but only if (\*value == expected) is true. That is, the swap takes place only under this condition.

#### Mutual exclusion is provided as follows:

- 1. A global variable **lock** is initialized to **0**.
- 2. The first process that invokes compare\_and\_swap() will set lock to 1
- 3. It will then **enter its critical section**, because the <u>original value of lock</u> **0** was equal to the <u>expected value of **0**</u>.
- 4. <u>Subsequent calls</u> to compare\_and\_swap() <u>will not succeed</u>, because lock is now 1 which is not equal to the expected value of 0.
- 5. When a process exits its critical section, it sets lock back to **0**, which allows another process to enter its critical section.
- 1. Does this solution satisfy mutual exclusion? Yes
- 2. Bounded waiting? No. (Figure 6.9 algorithm in the book, satisfies all the critical-section requirements)

## Solution using compare\_and\_swap

```
int compare _and_swap(int *value, int expected, int
new_value) {
    int temp = *value;

    if (*value == expected)
        *value = new_value;
    return temp;
}
```

Note: On Intel x86 architecture, the assembly language statement cmpxchg is used to implement compare\_and\_swap()

### **Atomic Variables**

Typically, instructions such as compare-and-swap are used as building blocks for other synchronization tools.

Many modern computer systems provide special hardware instructions that allow us either to test and modify the content of a word or to swap the contents of two words **atomically**—that is, as one uninterruptible unit.

One tool is an atomic variable that provides atomic (uninterruptible) updates on basic data types such as integers and booleans.

Most systems that support atomic variables provide special atomic data types as well as functions for accessing and manipulating atomic variables. These functions are often implemented using compare\_and\_swap() operations.

## **Atomic Operation**

In the old days, it would be a "lock" pin on the processor(s) - an actual external pin on the chip - that would be wired to anything else that could access the memory bus, and when that pin was active, all other devices has to wait for it to become inactive before accessing the memory bus.

These days, most systems use an "exclusive cache content" method: The processor signals all it's peers that "I want this address to be exclusive in my cache", at which point all other processors will "flush and invalidate" that particular address in their caches. Then the atomic operation is performed in the cache, and the results available to be read by other processors only when the atomic operation is completed.

## **Atomic Variables - Example**

Let **sequence** be an atomic variable

Let **increment()** be operation on the atomic variable **sequence**The following ensures **sequence** is incremented without interruption:

increment(&sequence);

The increment () function can be implemented as follows:

```
void increment(atomic_int *v)
{
    int temp;

    do {
        temp = *v;
    }
    while (temp != (compare_and_swap(v,temp,temp+1));
}
```

#### **Mutex Locks**

The hardware-based solutions to the critical-section problem presented are complicated as well as generally inaccessible to application programmers.

- Instead, operating-system designers build higher-level software tools to solve the critical-section problem.
- The simplest of these tools is the mutex lock.
- The term mutex is short for mutual exclusion.
- We use the mutex lock to protect critical sections and thus prevent race conditions
- But this solution requires busy waiting

## **Busy Waiting, Spinlocks**

While a process is in its critical section, any other process that tries to enter its critical section must loop continuously in the call to acquire().

**Busy waiting** is this continual looping wasting CPU cycles that some other process might be able to use productively.

It is a problem in a real multiprogramming system, where a single CPU core is shared among many processes.

#### Spinlock:

This type of mutex lock is also called a **spinlock** because the process

"spins" while waiting for the lock to become available.

Spinlocks are often identified as the locking mechanism of choice on multiprocessor systems when the lock is to be held for a short duration.

#### **Mutex Lock Definitions**

- Protect a critical section by first acquire() a lock before entering a critical section then release() the lock when it exits the critical section
  - A mutex lock has a boolean variable available whose value indicates if the lock is available or not.
  - If the lock is available, a call to acquire() succeeds, and the lock is then considered unavailable.
  - A process that attempts to acquire an unavailable lock is blocked until the lock is released.
- Calls to <u>acquire() and release() must be atomic</u>
  - Usually implemented via hardware atomic instructions such as test-and-set and compare-and-swap.

#### **Solution to Critical-section Problem Using Mutex Locks**

```
The definition of acquire():
acquire() {
       while (!available)
          ; /* busy wait */
       available = false;;
                                   while (true) {
The definition of release():
release() {
                                           acquire lock
       available = true;
                                                       critical
                                       section
                                               release lock
                                               remainder section
```

## **Semaphore**

Synchronization tool that provides more sophisticated ways (than Mutex locks) for processes to synchronize their activities.

A semaphore S is an integer variable that, apart from initialization, is accessed only through two standard atomic operations: wait() and signal().

Introduced by the Dutch computer scientist Dijkstra. Originally termed P() from the Dutch proberen, "to test" and V from verhogen, "to increment"

```
Definition of the wait() operation.
    wait(S) {
        while (S <= 0);  // busy wait
        S--;
    }

Definition of the signal() operation.
        signal(S) {
        S++;
    }</pre>
```

## Semaphore Implementation

- All modifications to the integer value of the semaphore in the wait() and signal() operations must be executed atomically.
- That is, when one process modifies the semaphore value, no other process can simultaneously modify that same semaphore value.
- In addition, in the case of wait(S), the testing of the integer value of S (S ≤ 0), as well as its possible modification (S--), must be executed without interruption.
- The implementation becomes the critical section problem where the wait code is placed before the critical section and signal code is placed after the critical section
- Could now have busy waiting in critical section implementation.
- Note that applications may spend lots of time in critical sections and therefore this is not a good solution

## **Counting Semaphores**

**Counting semaphore** - integer value can range over an unrestricted domain.

Can be used to control access to a given resource consisting of a finite number of instances:

- The semaphore is initialized to the number of resources available.
- Each process that wishes to use a resource performs a wait() operation on the semaphore (thereby decrementing the count).
- When a process releases a resource, it performs a signal() operation (incrementing the count).
- When the count for the semaphore goes to 0, all resources are being used.
- After that, processes that wish to use a resource will block until the count becomes greater than 0

## **Binary Semaphore**

Binary semaphore – integer value can range only between 0 and 1

Similarly to mutex locks

On systems that do not provide mutex locks, binary semaphores can be used instead for providing mutual exclusion.

```
Solution to the Critical Section Problem:

Create a semaphore "mutex" initialized to 1

wait (mutex);

CS

signal (mutex);
```

## Semaphore Usage Example

With semaphores we can solve various synchronization problems.

#### Problem:

Consider two concurrently running processes:  $P_1$  with a statements  $S_1$ , and  $P_2$  that with a statements  $S_2$  and the requirement that  $S_1$  to happen before  $S_2$ .

#### Solution:

Create to let  $P_1$  and  $P_2$  share a common semaphore "synch", initialized to 0. Insert the wait() in  $P_2$  and signal() in  $P_1$ .

```
Process P1:
    S<sub>1</sub>;
    signal(synch);
Process P2:
    wait(synch);
    S<sub>2</sub>;
```

Because synch is initialized to 0, *P*2 will execute *S*2 only after *P*1 has invoked signal(synch), which is after statement *S*1 has been executed.

### Semaphore Implementation with No Busy Waiting

**Avoids busy waiting** by temporarily putting the waiting process to sleep and then awakening it once the lock becomes available.

With each semaphore there is an associated waiting queue Each entry in a waiting queue has two data items:

value (of type integer)
pointer to next record in the list

### Semaphores: Process Blocking and Awakening

admitted

ready

I/O or event completion

interrupt

scheduler dispatch

waiting

exit

I/O or event wait

running

terminated

#### Suspending a process:

- When a process executes the wait() operation and finds that the semaphore value is not positive, it must wait.
- However, rather than engaging in busy waiting, the process can suspend itself.
- The suspend operation places a process into a waiting queue associated with the semaphore, and the state of the process is switched to the waiting state.
- Then control is transferred to the CPU scheduler, which selects another process to execute.

#### Restarting the process:

- A process that is suspended, waiting on a semaphore S, should be restarted when some other process executes a signal() operation.
- The process is restarted by a wakeup() operation, which changes the process from the waiting state to the ready state.
- The process is then placed in the Feady

#### Implementation with no Busy waiting (Cont.)

**block** – place the process invoking the operation on the appropriate waiting queue

```
wait(semaphore *S) {
    S->value--;
    if (S->value < 0) {
        add this process to S->list;
        sleep();
    }
}
```

Each semaphore has an integer value and a list of process list. Entry in a waiting list contains semaphore value and a pointer to next record in the list.

```
typedef struct {
        int value;
        struct process
*list;
    } semaphore;
```

wakeup – remove one of processes in the waiting queue and place it in the ready queue signal (semaphore \*S) {

```
S->value++;
if (S->value <= 0) {
   remove a process P from S->list;
   wakeup(P);
}
```

The sleep() and wakeup() operations are provided by the operating system as basic system calls.

## **Semaphore values**

Semaphore values are never negative under the classical definition of Semaphores with busy waiting.

In Semaphore implementation with no busy waiting, semaphore values may be negative. If a semaphore value is negative, its magnitude is the number of processes waiting on that semaphore.

## **Semaphore order**

- Although semaphores provide a convenient and effective mechanism for process synchronization, using them incorrectly can result in timing errors that are difficult to detect, since these errors happen only if particular execution sequences take place, and these sequences do not always occur.
- To illustrate how, we review the semaphore solution to the critical-section problem. All processes share a semaphore variable mutex, which is initialized to 1.
  - Each process must execute wait(mutex) before entering the critical section and signal(mutex) afterward.
  - If this sequence is not observed, two processes may be in their critical sections simultaneously.

## **Problems with Semaphores**

 Incorrect order in which the wait() and signal() operations on the semaphore mutex

```
process interchanges the operations
signal (mutex) ... critical section ... wait (mutex)
```

several processes maybe executing in their critical sections simultaneously, violating the mutual-exclusion requirement

- 2. wait (mutex) ... wait (mutex) a deadlock will occur.
- 3. process omits the wait(mutex), or the signal(mutex), or both

  Omitting of wait (mutex) and/or signal (mutex)

  either mutual exclusion is violated or a deadlock will occur.

These – and others – are examples of what can occur when semaphores and other synchronization tools are used incorrectly.

#### **Monitors**

A *monitor type* is an ADT that includes a set of programmer-defined operations that are provided with mutual exclusion within the monitor.


#### An abstract data type—or ADT—

- encapsulates data with a set of functions to operate on that data
- internal variables only accessible by code within the procedure

Only one process may be active within the monitor at a time Pseudocode syntax of a monitor:

```
monitor monitor-name
{
          // shared variable declarations
          function P1 (...) { .... }
          function P2 (...) { .... }
          function Pn (...) {.....}
        initialization code (...) { ... }
}
```

### **Schematic view of a Monitor**



## **Monitor Type**


A **monitor type** is an ADT that includes a set of programmer-defined operations that are provided with mutual exclusion within the monitor.

- A programming language construct that supports controlled access to shared data. It encapsulates:
  - Shared data
  - Procedures that operate on the shared data
  - Synchronization between concurrent processes that invoke those procedures (only one thread can execute any of the procedures at a time)
- A Monitor has a mutex lock and a queue
  - Processes has to acquire the lock before invoking a procedure in the monitor
  - If the lock has been acquired by a process, other requesting processes are put in the queue

## **Monitors (cont'd)**

- 1. Shared data can only be accessed through procedures
- 2. Only one thread can enter the monitor to invoke procedures at a time
- 3. These rules guarantee that all threads access the shared data in a mutual exclusive way

Monitor is easy to use, but less flexible than Semaphore



#### **Condition Variables**

For modeling some synchronization schemes, additional synchronization mechanisms are provided by the condition construct.

```
condition x, y;
```

Two operations are allowed on a condition variable:

- x.wait() a process that invokes the operation is suspended until x.signal()
- x.signal() resumes one of processes (if any) that
  invoked x.wait()

If no x.wait() on the variable, then it has no effect on the variable

#### **Condition Variables Choices**

If process P invokes x.signal(), and process Q is suspended in x.wait(), what should happen next?

Both Q and P cannot execute in parallel. If Q is resumed, then P must wait

#### Options include


**Signal and wait** – P waits until Q either leaves the monitor or it waits for another condition

**Signal and continue** – Q waits until P either leaves the monitor or it waits for another condition

Both have pros and cons – language implementer can decide.

A compromise implemented in languages including C#, Java
P executing signal immediately leaves the monitor, Q is resumed

### **Illustration of a Monitor**



A single entry point that is guarded so that only one process may be in the monitor at a time.

A process in monitor may block itself on condition x by issuing cwait(x) enters associated queue

A process in monitor detects a change in condition variable x; it issues csignal(x) that alerts the queue

### Liveness

Processes may have to wait indefinitely while trying to acquire a synchronization tool such as a mutex lock or semaphore.

Waiting indefinitely violates the progress and bounded-waiting criteria discussed at the beginning of this chapter.

**Liveness** refers to a set of properties that a system must satisfy to ensure processes make progress.

Indefinite waiting is an example of a liveness failure.

#### **Deadlock**

**Deadlock** – two or more processes are waiting indefinitely for an event that can be caused by only one of the waiting processes

Let S and Q be two semaphores initialized to 1

Consider if  $P_0$  executes wait(S) and  $P_1$  wait(Q). When  $P_0$  executes wait(Q), it must wait until  $P_1$  executes signal(Q)

However,  $P_1$  is waiting until  $P_0$  execute signal(S).

Since these signal() operations will never be executed,  $P_0$  and  $P_1$  are **deadlocked**.

## **Lliveness problem - Priority Inversion**

**Priority Inversion** – Scheduling problem when lower-priority process holds a lock needed by higher-priority process

Since kernel data are typically protected with a lock, the higher-priority process will have to wait for a lower-priority one to finish with the resource.

The situation becomes more complicated if the lower-priority process is preempted in favor of another process with a higher priority.

- Assume we have three processes—L, M, and H—whose priorities follow the order L < M < H.
- Assume that process H requires resource R, which is currently being accessed by process L.
- Ordinarily, process H would wait for L to finish using resource R.
- However, now suppose that process M becomes runnable, thereby preempting process L. Indirectly, a process with a lower priority process M—has affected how long process H must wait for L to relinquish resource R.

## **Priority Inheritance Protocol**

To prevent this from occurring, a **priority inheritance protocol** is used.

- 1. All processes that are accessing resources needed by a higherpriority process inherit the higher priority until they are finished with the resources in question.
- 2. When they are finished, their priorities revert to their original values.

#### In the example:

- a priority-inheritance protocol would allow process L to temporarily inherit the priority of process H, thereby preventing process M from preempting its execution.
- When process L had finished using resource R, it would relinquish its inherited priority from H and assume its original priority.
- Because resource R would now be available, process H not M would run next.

# **End of Chapter 6**