

```
% Load the inversion model of Jakobshavn Isbrae and plot some result parameters md=loadmodel('/Users/rishi/Desktop/ISSM/examples/Jakobshavn/Jakob_inversion');

plotmodel(md,'data',md.geometry.surface,'title','Surface Elevation',...'data',md.geometry.base,'title','Bed Elevation (m)',...'data',md.initialization.vel,'title','Velocity (m/yr)',...'data',md.friction.coefficient,'title','Friction coefficient',...'unit#all','km','figposition','fullscreen')
```






Coupled SHAKTI-ISSM simulation of Jakobshavn, starting from previous inversion

```
%
------
% md.hydrology
%
% hydrologyshakti solution parameters:
% head : -- subglacial hydrology water head (m)
```

```
%
                                      -- height of gap separating ice to
           gap_height
bed (m)
%
           gap height min
                                      -- minimum allowed gap height (m)
                                      -- maximum allowed gap height (m)
%
           gap_height_max
%
           bump spacing
                                      -- characteristic bedrock bump
spacing (m)
                                     -- characteristic bedrock bump height
           bump_height
(m)
%
          englacial input
                                  : -- liquid water input from englacial
to subglacial system (m/yr)
           moulin input
                                      -- liquid water input from moulins
%
(at the vertices) to subglacial system (m^3/s)
           reynolds
                                      -- Reynolds' number
%
           neumannflux
                                      -- water flux applied along the model
boundary (m^2/s)
%
                                      -- water head constraints (NaN means
           spchead
no constraint) (m)
                                      -- under-relaxation coefficient for
           relaxation
                                  :
nonlinear iteration
%
                                      -- englacial storage coefficient
           storage
(void ratio)
           requested_outputs : -- additional outputs requested
%
%
% Turn off inversion first
md.inversion.iscontrol=0;
% HYDROLOGY SPECIFIC PARAMETERIZATION:
md.hydrology=hydrologyshakti(); % Change hydrology class to SHAKTI model
% Next, we initialize the SHAKTI-specific hydrological parameters:
md.hydrology.englacial input = 0.0*ones(md.mesh.numberofvertices,1); %
distributed englacial input to the subglacial system (m/yr)
md.hydrology.head = (0.8*md.materials.rho_ice/md.materials.rho_freshwater)
* md.geometry.thickness + md.geometry.base; ...% initial water head such
that water pressure is 80% of ice overburden pressure
md.hydrology.gap_height = 0.01*ones(md.mesh.numberofelements,1); % Initial
subglacial gap height of 0.01m everywhere
md.hydrology.bump_spacing = 1.0*ones(md.mesh.numberofelements,1); % Typical
bed bump bump spacing — must be non-zero
md.hydrology.bump height = 0.0*ones(md.mesh.numberofelements,1); % Typical
bed bump height -- set to zero to turn off opening by sliding
md.hydrology.reynolds= 1000*ones(md.mesh.numberofelements,1); % Initial
Reynolds number (start at Re=1000 everywhere)
% BOUNDARY CONDITIONS
```

```
md.hydrology.spchead = NaN(md.mesh.numberofvertices,1);
% Set head=0 for thin ice, everywhere <=10m ice thickness
pos=find(md.geometry.thickness==10);
md.hydrology.spchead(pos)=0;
% Set pressure in fjord equal to hydrostatic pressure of fjord water
pos=find(md.mask.ice levelset>0);
md.hydrology.spchead(pos)=0;
md.hydrology.moulin_input = zeros(md.mesh.numberofvertices,1); % No moulin
inputs
md.hydrology.neumannflux=zeros(md.mesh.numberofelements,1); % No-flux b.c.
on domain boundary
% % Deal with terminus b.c. in SHAKTI
% terminus=ContourToNodes(md.mesh.x,md.mesh.y,'Exp/terminus_big.exp',1);
% pos=find(terminus & md.mask.ice_levelset<=0);</pre>
% md.hydrology.spchead(pos)=0;
% Coupling and friction
md.transient = deactivateall(md.transient);
md.transient.isstressbalance=1; % 1=Solve for ice velocity, 0=turn off
stress balance
md.transient.ishydrology=1;
% Friction and effective pressure
Neff = md.materials.rho_ice*md.constants.g*md.geometry.thickness-
md.materials.rho water*md.constants.g*...
    (md.hydrology.head - md.geometry.base); %Initial effective pressure
md.friction.effective_pressure = Neff;
md.friction.coupling = 4; % Change this to couple (4) /uncouple with
prescribed N (3) ***
% Plot the initial effective pressure from the model output
plotmodel(md,'data',md.friction.effective_pressure,'unit','km','title','Init
ial Effective Pressure Guess (Pa)')
```



RUN TRANSIENT SIMULATION

```
% Change the number of processors according to your machine md.cluster=generic('np',4);

% Define the time stepping scheme md.timestepping.time_step = 1*3600/md.constants.yts; % Time step (1 hours in years) md.timestepping.final_time = 1/365; % Final time (3 days expressed in years) - 24 time steps of 1 hour each md.settings.output_frequency = 6; % Save results for only every 6 hours (4 results per day)

% Run! md.verbose.solution=1; % Set to 1 to keep track of time step progress, If set to 0, the model runs silently (useful for long jobs on HPC). md=solve(md,'Transient'); save Jakob_SHAKTI-hydrology md % save the model output for future use
```

% Plot and Evaluate the end result of the transient simulation plotmodel(md, ...

```
'data', md.results.TransientSolution(end).Vel, ...
'title', 'Velocity (m/yr)', ...
'data', md.results.TransientSolution(end).EffectivePressure, ...
'title', 'Effective Pressure (Pa)', ...
'data', log10(md.results.TransientSolution(end).HydrologyBasalFlux), ...
'title', 'log_{10}(Basal Water Flux) (m^2 s^{-1})', ...
'data', md.results.TransientSolution(end).HydrologyHead, ...
'title', 'Hydraulic Head (m)','figposition','fullscreen');
```

