

CHAPTER 1

The Gram-Schmidt Process

The Gram-Schmidt process is a method use to transform a set of linearly independent vectors to a set of orthogonal (perpendicular vectors). The original vectors and the transformed vectors span the same subspace.

The process was named after two mathematicians: Jørgen Pedersen Gram, a Danish actuary mathematician, and Erhard Schmidt, a German mathematician. The men developed the orthogonalization process independently. Gram introduced the process in 1883 whereas Schmidt did his work in 1907. It wasn't named the Gram-Schmidt process until sometime later, after both mathematicians became well-known in the mathematical community.

This method has many practical applications in science and engineering. These are just two application of Gram-Schmidt:

- 1. In signal processing, it can represent an audio signal with fewer components making it easier to isolate and remove noise.
- 2. In statistics and data analysis, it can reduce the complexity of a dataset so that it is easier to see which aspects or features contribute to the analysis.

The Gram-Schmidt process orthonormalizes a set of vectors in an inner product space, most commonly the Euclidean space \mathbb{R}^n . The process takes a finite, linearly independent set $S = \{v_1, v_2, \ldots, v_k\}$ for $k \leq n$, and generates an orthogonal set $S' = \{u_1, u_2, \ldots, u_k\}$ that spans the same k-dimensional subspace of \mathbb{R}^n as S.

1.1 The Process

Let's look at how the process works. Given a set of vectors $S = \{v_1, v_2, \dots, v_k\}$, the Gram-Schmidt process is as follows:

- 1. Let $u_1 = v_1$.
- 2. For j = 2, 3, ..., k:
 - (a) Let $w_j = v_j \sum_{i=1}^{j-1} \frac{\langle v_j, u_i \rangle}{\langle u_i, u_i \rangle} u_i$
 - (b) Let $u_i = w_i$

Here, $\langle ., . \rangle$ denotes the inner product.

The set of vectors $S'=\{u_1,u_2,\ldots,u_k\}$ obtained from this process is orthogonal, but not necessarily orthonormal. To create an orthonormal set, you simply need to normalize each vector u_i to unit length. That is, $u_i'=\frac{u_i}{\|u_i\|}$, where $\|.\|$ denotes the norm (or length) of a vector.

Among other things, making vectors orthonormal simplifies calculations, makes it easier to define rotations and transformations, and provides a framework for calculations in fields such as quantum mechanics.

1.2 Example Calculation

Given a set of linearly independent vectors, we will use the Gram-Schmidt process to find an orthogonal basis.

Let

$$W = Span(x_1, x_2, x_3)$$

where

$$x_1 = (1, 2, -2)$$

$$x_2 = (1, 0, -4)$$

$$x_3 = (5, 2, 0)$$

The three orthogonal vectors will define the same subspace as the original vectors.

The first vector of the orthogonal subspace is easy to define. We set it to be the same as x_1 .

$$v_1 = x_1 = (1, 2, -2)$$

The second orthogonal vector is a projection of x_2 onto v_1 . You learned projections in the last chapter, so this should be fairly straightforward.

$$v_2 = x_2 - \frac{x_2 v_1}{v_1 v_1} v_1$$

Substitute the values:

$$v_2 = (1, 0, -4) - \frac{(1, 0, -4)(1, 2, -2)}{(1, 2, -2)(1, 2, -2)} (1, 2, -2)$$

Calculate the coefficient for v_1 :

$$v_2 = (1, 0, -4) - \frac{9}{9}(1, 2, -2)$$

Perform the subtraction:

$$v_2 = (0, -2, -2)$$

The third vector for the orthogonal subspace is a projection onto v_1 and v_2 .

$$v_3 = x_3 - \frac{x_3 v_1}{v_1 v_1} v_1 - \frac{x_3 v_2}{v_2 v_2} v_2$$

Substitute the values:

$$v_{3} = (5,2,0) - \frac{(5,2,0)(1,2,-2)}{(1,2,-2)(1,2,-2)}(1,2,-2) - \frac{(5,2,0)(1,0,-4)}{(1,0,-4)(1,0,-4)}(1,0,-4)$$

$$v_{3} = (5,2,0) - (9/9)(1,2,-2) - (-4/8)(1,0,-4)$$

$$v_{3} = (5,2,0) - (1,2,-2) + (1/2)(1,0,-4)$$

$$v_{3} = (5,2,0) - (1,2,-2) + (0,-1,-1)$$

$$v_{3} = (4,-1,1)$$

This set of vectors is orthogonal, so we need to normalize them so that the vectors are orthonormal. Recall that an orthonormal vector has a length of 1 and is computed using this formula:

Thus the normalized set of vectors is:

$$v_1 = (0.33, 0.67, -0.67)$$

$$v_2 = (0.0, -0.71, -0.71)$$

$$v_3 = (0.94, -0.24, 0.24)$$

Exercise 1 Gram-Schmidt Process

Use the Gram-Schmidt process to to find an orthogonal basis for the span defined by x_1, x_2 where:

$$x_1 = (1, 1, 1)$$

$$x_2 = (0, 1, 1)$$

Working Space

Answer on Page 7

1.3 The Gram-Schmidt Process in Python

Create a file called vectors_gram-schmidt.py and enter this code:

```
# import numpy to perform operations on vector
import numpy as np
```

Find an orthogonal basis for the span of these three vectors

x1 = np.array([1, 2, -2])

x2 = np.array([1, 0, -4])

x3 = np.array([5, 2, 0])

$$#v1 = x1$$

v1 = x1

```
print("v1 = ",v1)

# v2 = x2 - (the projection of x2 on v1)
v2 = x2 - (np.dot(x2,v1)/np.dot(v1,v1))*v1
print("v2 = ", v2)

# v3 = x3 - (the projection of x3 on v1) - (the projection of x3 on v3)
v3 = x3 - (np.dot(x3,v1)/np.dot(v1,v1))*v1 - (np.dot(x3,v2)/np.dot(v2,v2))*v2
print("v3 =", v3)

# Next, normalize each vector to get a set of vectors that is both orthogonal and orthon
v1_norm = v1 / np.sqrt(np.sum(v1**2))
v2_norm = v2 / np.sqrt(np.sum(v2**2))
v3_norm = v3 / np.sqrt(np.sum(v3**2))
print("v1_norm = ", v1_norm)
print("v2_norm = ", v2_norm)
print("v3_norm = ", v3_norm)
```

1.4 Where to Learn More

Watch this video from Khan Academy about the Gram-Schmidt process: INSERT LINK

This is a draft chapter from the Kontinua Project. Please see our website (https://kontinua.org/) for more details.



APPENDIX A

Answers to Exercises

Answer to Exercise 1 (on page 4)

The first vector of the orthogonal subspace is:

$$v_1 = x_1 = (1, 1, 1)$$

The second vector of the subspace is a projection of x_2 onto v_1 .

$$v_2 = x_2 - \frac{x_2 v_1}{v_1 v_1} v_1$$

Substitute the values:

$$v_2 = (0, 1, 1) - \frac{(0, 1, 1)(1, 1, 1)}{(1, 1, 1)(1, 1, -1)}(1, 1, 1)$$
$$v_2 = (0, 1, 1) - (2/3)(1, 1, 1)$$
$$v_2 = (-2/3, 1/3, 1/3)$$

Normalize:

$$\nu_1 = \nu_1/\sqrt{|\nu_1|}$$

$$\begin{aligned} \nu_1 &= (1,1,1)/\sqrt{|\nu_1|} \\ \nu_1 &= (0.577,0.577,0.577) \\ \nu_2 &= \nu_2/\sqrt{|\nu_2|} \\ \nu_2 &= (0,1,1)\sqrt{|\nu_2|} \\ \nu_2 &= (-0.816,0.408,0.408) \end{aligned}$$



INDEX

Gram-Schmidt process, 2