

Packet Tracer - Implement Port Security

Addressing Table

| Device | Interface | IP Address | Subnet Mask |
|--------------|-----------|-------------|---------------|
| S1 | VLAN 1 | 10.10.10.2 | 255.255.255.0 |
| PC1 | NIC | 10.10.10.10 | 255.255.255.0 |
| PC2 | NIC | 10.10.10.11 | 255.255.255.0 |
| Rogue Laptop | NIC | 10.10.10.12 | 255.255.255.0 |

Objective

Part 1: Configure Port Security

Part 2: Verify Port Security

Background

In this activity, you will configure and verify port security on a switch. Port security allows you to restrict a port's ingress traffic by limiting the MAC addresses that are allowed to send traffic into the port.

Part 1: Configure Port Security

a. Access the command line for **S1** and enable port security on Fast Ethernet ports 0/1 and 0/2.

```
S1(config) # interface range f0/1 - 2
S1(config-if-range) # switchport port-security
```

b. Set the maximum so that only one device can access the Fast Ethernet ports 0/1 and 0/2.

```
S1(config-if-range)# switchport port-security maximum 1
```

c. Secure the ports so that the MAC address of a device is dynamically learned and added to the running configuration.

```
S1(config-if-range)# switchport port-security mac-address sticky
```

d. Set the violation mode so that the Fast Ethernet ports 0/1 and 0/2 are not disabled when a violation occurs, but a notification of the security violation is generated and packets from the unknown source are dropped.

```
S1(config-if-range) # switchport port-security violation restrict
```

e. Disable all the remaining unused ports. Use the **range** keyword to apply this configuration to all the ports simultaneously.

```
S1(config-if-range)# interface range f0/3 - 24, g0/1 - 2
S1(config-if-range)# shutdown
```

Part 2: Verify Port Security

a. From PC1, ping PC2.

Packet Tracer - Implement Port Security

- b. Verify that port security is enabled and the MAC addresses of **PC1** and **PC2** were added to the running configuration.
 - S1# show run | begin interface
- c. Use port-security show commands to display configuration information.
 - S1# show port-security
 - S1# show port-security address
- d. Attach Rogue Laptop to any unused switch port and notice that the link lights are red.
- e. Enable the port and verify that **Rogue Laptop** can ping **PC1** and **PC2**. After verification, shut down the port connected to **Rogue Laptop**.
- f. Disconnect **PC2** and connect **Rogue Laptop** to F0/2, which is the port to which PC2 was originally connected. Verify that **Rogue Laptop** is unable to ping **PC1**.
- g. Display the port security violations for the port to which **Rogue Laptop** is connected.
 - S1# show port-security interface f0/2

How many violations have occurred?

не менее четырех, по одному для каждого запроса на ping

h. Disconnect Rouge Laptop and reconnect PC2. Verify PC2 can ping PC1.

Why is PC2 able to ping PC1, but the Rouge Laptop is not?

Безопасность порта, которая была включена на порту, позволяла только устройству, МАС-адрес которого был изучен первым, доступ к порту, не допуская доступ ко всем другим устройствам

© 2013 - 2021 Cisco and/or its affiliates. All rights reserved. Cisco Public

Page **2** of **2**

www.netacad.com