# Architecture and Open Queue Model

### Thesis

Silvio Dei Giudici, Marco Morella, Mattia Nicolella 21 September 2020

### 1 Introduction

This section will deal with the assumptions we have made so far and why we've made them. Alternatives will be described for the various possibilities.

### 1.1 Assumptions

- 1. **Assumption 1**: All layers have no horizontal connection. The scheme we will present in section 2 will feature LANs accessible by all nodes of the same layer so this type of communication is actually possible through those LANs, but for now decided to not have horizontality in the message system.
- 2. **Assumption 2**: The only entity needing a storage system is the Central Node, in particular we are assuming that all other nodes receive information that can be processed, stored and aggregated in the RAM which will never be full. This is a strong assumption that can be relaxed if needed by adding disks in the regional and primary/secondary layer.
- 3. **Assumption 3**: more of a design choice for the moment, each node is modeled as a simple queue composed of CPU+RAM, in future they

will be extended (for example a disk) and may need more component and a review of the entire queue model.

- 4. **Assumption 4**: In this first stage we won't be holding account of the fault tolerance of the system, in particular we are not considering duplication of the data not in storaging neither in multiple link sending.
- 5. **Assumption 5**: Equiprobability of receiving a command message on any given level, indeed we will assume that, each time a central sends a command message to a node on a level the probability that any one of them is the target is the same, this can be relaxed easily by putting a fixed probability parameter in the formulas.

### 1.2 Table

First of all, we started by compiling the table with the responses as we expect them to be. The green ones are those decisions we made while the black ones are trivial ones that have no alternatives.

Entity	Generate s a transition / telemetry message ?	Receives a reply to a transition message ?	Generate s a command in response to a transition message ?	Generate s a command independ ently from a transition message ?	Transition message s are sent to nodes in the upper layer?	Telemetry message s are sent to nodes in the upper layer?	Transition message s are sent to nodes in the same layer?	Telemetry message s are sent to nodes in the same layer?	Aggregati on rate by message type	There are multiple links to the upper layer?	There is duplicatio n of the message s on different upper links?
Sensor	transition and telemetry	no	no	no	yes	yes	no	no	no	*	no
Actuator	transition only	no	no	no	yes	yes	no	no	no	*	no
Primary Network Node	no	yes	yes	no	yes	yes	no	no	param	*	no
Secondar y Network Node	no	yes	yes	no	yes	yes	no	no	param	*	no
Regional Node	no	yes	no	no	yes	yes	no	no	param	*	no
Central Node	no	no	no	yes	no	no	no	no	param	*	no

Now, row by row we will justify or explain our answers:

- 1. Generate a transition or telemetry message: the sensor gives telemetry informations to the upper node with a certain rate. Both actuators and sensor will generate a transitions message in the case that their state is changed without a transition command received. All others entities have no case in which they need to do so.
- 2. Receives a reply to a transition message: sensor and actuators don't need an acknowledgment from the upper level, while all other entities do. The only exception is the Central node since he doesn't have an upper node to send to.
- 3. Generates a command in response to a transition message: the primary/secondary node reading the transition messages may need to issue commands to actuators in order to keep the system flowing.

- 4. Generates a command independently from a transition message: none of the entities may generate a command without any trigger, the only exception being the central node which sends commands when needed.
- 5. Transition messages are sent to nodes in the upper layer: all entities need to send to an upper level until the central node is reached.
- 6. Telemetry messages are sent to nodes in the upper layer: same as last one.
- 7. Transition messages are sent to nodes in the same layer: no, for assumption 1.
- 8. Telemetry messages are sent to nodes in the same layer: no, for assumption 1.
- 9. Aggregation rate by message type: we don't have the actual rate so we put a parameter in the aggregation formulas.
- 10. There are multiple links to the upper layer: not useful at the moment for modeling and queue formulas so we skipped over it. Also for Assumption 4 we may implement it in a later stage.
- 11. There is duplication of the messages on different upper links: No, for assumption 4.

### 2 Structural scheme

This section will explain how the structural scheme for the system is made and its project's choices.

In the model we are going to show, we used as connection between the upper level LAN (The central LAN was modeled since it could be used by replicas of the central node in future versions) and the LAN of the lower level nodes a WAN between two routers. An alternative is possible if we transform this WAN into a long distance LAN where only one router is needed for this connection on the upper level node side.

The choice of a LAN that connects all the regional nodes could be infeasible due to the high regional span that the second level nodes are going to cover. Another alternative is to connect each regional node to the WAN.




Figure 1: Focus on Central and Regional nodes




Figure 2: Focus on Regional and Primary/Secondary nodes

Figure 1 represents the connection between Central and Regional nodes, while Figure 2 shows the connection between Regional and Primary/Secondary. We can see that lower level router is used as an interface for lower level nodes to receive and send messages to the upper level node. Keeping in mind assumption 1 on the horizontal level communication, even if the nodes on a level share a LAN they won't send messages to their peers.




Figure 3: Focus on Primary/Secondary nodes and end points

Instead in figure 3, which displays the connection between Primary/Secondary nodes and the end points of the edge system, namely actuators and sensors, one LAN is used for each type of connection technology, in this case MANET and WIRELESS, both spanning between end points and their respective upper level node.

Furthermore this model is parametric so a central node manages n regional nodes. Each regional node manages m primary and k secondary nodes, these parameters varies with the regional node they are associated to. Same thing extends to primary/secondary with respect to the sensors/actuators, respectively in numbers s and a.

One last note about the scheme is that at the moment we divided on two LANs primary and secondary for clarity since they have different rate, operations and technology. Likewise for the different communication technology with actuators and sensors.

The whole scheme:




Figure 4: Structural scheme

# 3 Queues Scheme and Formulas

The following open queue scheme will be divided in segments during the analysis of each queue.




Figure 5: The open queue scheme

#### 3.1 Classes

Based on the specifics and the architecture, we opted for a multi-class open queueing model, in particular at the moment we have three different classes going through the system:

- t: telemetry events, where a sensors sends to its superior the data it has periodically, this data then will be aggregated at each level up until the central node.
- e: transition events, which are sent by actuators and sensors when the network state changes.
- c: command events, generated either indipendently by the central node when managing the network or by a primary node in response to a transition message from one of its sensors/actuators.

Another type of message flowing through the network is a reply message but since they are triggered only by transition events we aggregated them in the visits. Due to the nature of this kind of open queueing model, the formulas regarding Utilization factor, system demand and response time are very similar for the components.

#### 3.2 Notation

We will deline the notation in the following formulas, each of them has one or many subscripts for the item they refer to, the same type of element in a different part has the same notation even though it's not the same element:

- $\lambda_t$ ,  $\lambda_e$ ,  $\lambda_c$ :  $\lambda$  is the arrival rate, respectively for the data type telemetry, transition and command.
- V: mean number of visits.
- S: service time.
- D: service demand.
- *U*: utilization factor.

 $\bullet$  R: response time.

The elements we are going to analyze are:

- cn : central node.
- $\bullet \ {\rm cns}:$  central node storage
- rn : regional node.
- pn : primary node.
- $\bullet$  sn : secondary node.
- wl: wireless.
- mt : manet.
- pl : primary lan.
- $\bullet$  sl : secondary lan.
- $\bullet\,$  ps : primary-secondary lan.
- rl : regional lan.
- $\bullet$  cl : central lan.

We will navigate the queue network starting from the sensors and actuators until reaching the central node.




Figure 6: Focus on actuators, sensors, primary/secondary nodes, wireless and MANET LANs

### 3.3 Actuators and Sensors

Sensors at the moment don't receive any command, we still have drawn them as queues for future extensions. Conversely, actuators are modeled as queues since they can receive command from the central node or from the primary/secondary node where they are connected in response to a transition event.

Regarding the sensors,  $\lambda_{s,t}$  and  $\lambda_{s,e}$  are the rates at which the sensor sends a telemetry or a transition message respectively. The same is valid for the transition events rate of the actuators with  $\lambda_{a,e}$ .

We will now analyze the behaviour of an actuator which receives commands from its primary node though a wireless or MANET LAN. The same relations apply also if the actuator is connected to a secondary node.

The mean number of visits for a command message is 1. The rate at which an actuator can receive a command  $(\lambda_{a,c})$  is composed by the rate at which a command can be received from the central node and by the probability to receive a command message from the primary/secondary node in response to a transition message. We assumed that commands from the central node are sent with a rate of  $\lambda_{cn,c}$  and can reach any actuator in the whole network with the same probability by Assumption 5, so we need to weight the rate of the central node issuing commands with all the possible paths that this command can follow (over the possible n regional nodes, their primary and secondary nodes, m + k and over all the actuators connected to one of these primary/secondary nodes,  $a_{wl} + a_{mt}$ ). The probability of issuing a command in response to a transition message received by the upper primary/secondary node (with a rate of  $\lambda_{pn,e}$ ) is prb and must be weighted by all the possible actuators connected to that node,  $a_{mt} + a_{wl}$ , which can be contacted by that message.

$$V_{a,c} = 1$$

$$\lambda_{a,c} = \frac{1}{n} * (\frac{1}{m+k}) * \frac{1}{a_{mt} + a_{wt}} * \lambda_{cn,c} + prb * \frac{1}{a_{wt} + a_{mt}} * \lambda_{pn,e}$$
(1)

$$D_{a,c} = V_{a,c} * S_{a,c} U_{a,c} = \lambda_{a,c} * D_{a,c} R_{a,c} = \frac{D_{a,c}}{1 - U_{a,c}}$$
(2)

## 3.4 WIRELESS/MANET Lan

We are not considering the implication of the different technology, since the difference between them is only the service time of the network. Thus we will only show the formulas for Wireless and the Manet's formulas will be mirrored.

For the formulas we used the assumption 5 on equiprobability and the table presented in section 1.2, in particular the first four columns.

The mean number of visits is trivially one for telemetry and commands since only one messages goes through the LAN, it's two for transition since a reply is needed.

More interesting are the formulas regarding the arrival rates.

In the telemetry cases the total arrival rate  $\lambda_{wl,t}$  is the rate of a single sensor multiplied by the number of sensors.

For transition instead,  $\lambda_{wl,e}$  will be a sum of two terms, since both actuators and sensors send messages.

Finally for  $\lambda_{wl,c}$ , the first term is the case where the central node issues a command, so the sent command of that class of messages will arrive to an actuator with a certain probability, given the assumption 5 this probability is one over the sum of all possible paths that can be taken by this message: one of the regional node, then one of the primary or secondary node and then one of all the actuators, in this case we are concerned only if they go on the WIRELESS( $\frac{a_{wl}}{a_{wl}+a_{mt}}$ ). The second term instead is the case where a command is prompted due to a transition message; so we multiply the arrival rate of transition event for primary or secondary node ( $\lambda_{pn,e}$  or  $\lambda_{sn,e}$  the LAN is connected to a secondary node) by the probability of the transition to generate a command (prb), multiplied by the probability that

the message needs to reach an actuator in this network  $(\frac{a_{wl}}{a_{wl}+a_{mt}})$ . We are using Assumption 5 so all the actuators have the same probability to be contacted. It is a strong assumption and may need to be relaxed in future work.

$$\begin{split} V_{wl,t} &= 1 \\ V_{wl,e} &= 2 \\ V_{wl,c} &= 1 \\ \lambda_{wl,t} &= s * \lambda_{s,t} \\ \lambda_{wl,e} &= s * \lambda_{s,e} + a * \lambda_{a,e} \\ \lambda_{wl,c} &= \frac{1}{n*(m+k)} * \frac{a_{wl}}{a_{wl} + a_{mt}} * \lambda_{cn,c} + prb * \frac{a_{wl}}{a_{wl} + a_{mt}} * \lambda_{pn,e} \end{split}$$

In the last equation, the second term requires a change from primary node arrival rate to secondary node arrival rate in the case that the upper node is indeed a secondary.

From the previous formulas and the open queue model we can compute the Service Demand, Utilization factor and Response time.

$$D_{wl,t} = V_{wl,t} * S_{wl,t}$$

$$D_{wl,e} = V_{wl,e} * S_{wl,e}$$

$$D_{wl,c} = V_{wl,c} * S_{wl,c}$$

$$U_{wl,t} = \lambda_{wl,t} * D_{wl,t}$$

$$U_{wl,e} = \lambda_{wl,e} * D_{wl,e}$$

$$U_{wl,c} = \lambda_{wl,c} * D_{wl,c}$$

$$U_{wl} = U_{wl,t} + U_{wl,e} + U_{wl,c}$$

$$R_{wl,t} = \frac{D_{wl,t}}{1 - U_{wl}}$$

$$R_{wl,e} = \frac{D_{wl,e}}{1 - U_{wl}}$$

$$R_{wl,c} = \frac{D_{wl,e}}{1 - U_{wl}}$$

$$R_{wl,c} = \frac{D_{wl,c}}{1 - U_{wl}}$$
(4)

### 3.5 Primary Node

All formulas in this section are relatable to the previous one and thus we won't need any note on them.

Formulas for secondary nodes are the same as primary ones for now so we will only discuss these one.

The equations of the previous element will be used as arrival rates for the primary node thus both MANET and WIRELESS will be referred to.

While transitions and telemetries are simply the sum of the rates coming from MANET and WIRELESS, commands need an explanation.

Indeed the first term is the rate arriving to a single primary node thus divided by the number of regionals and then by the number of primary plus secondary nodes. The second term is again the probability of dependent commands.

$$V_{pn,t} = 1$$

$$V_{pn,e} = 2$$

$$V_{pn,c} = 1$$

$$\lambda_{pn,t} = \lambda_{wl,t} + \lambda_{mt,t}$$

$$\lambda_{pn,e} = \lambda_{wl,e} + \lambda_{mt,e}$$

$$\lambda_{pn,c} = \frac{1}{n} * (\frac{1}{m+k}) * \lambda_{cn,c} + prb * \lambda_{pn,e}$$

$$(5)$$

From the previous formulas and the open queue model we can compute the Service Demand, Utilization factor and Response time.

$$D_{pn,t} = V_{pn,t} * S_{pn,t}$$

$$D_{pn,e} = V_{pn,e} * S_{pn,e}$$

$$D_{pn,c} = V_{pn,c} * S_{pn,c}$$

$$U_{pn,t} = \lambda_{pn,t} * D_{pn,t}$$

$$U_{pn,e} = \lambda_{pn,e} * D_{pn,e}$$

$$U_{pn,c} = \lambda_{pn,c} * D_{pn,c}$$

$$U_{pn} = U_{pn,t} + U_{pn,e} + U_{pn,c}$$

$$R_{pn,t} = \frac{D_{pn,t}}{1 - U_{pn}}$$

$$R_{pn,e} = \frac{D_{pn,e}}{1 - U_{pn}}$$

$$R_{pn,c} = \frac{D_{pn,e}}{1 - U_{pn}}$$

# 3.6 Primary LAN




Figure 7: Focus on primary/secondary WAN, primary/secondary LAN and primary/secondary nodes

The primary LAN element of the system will deal with messages having as sender or receiver one of the m primary nodes, thus all rates will be multiplied by m.

Furthermore in the telemetry case, since the primary nodes do a first step of data aggregation, the arrival rate on the primary LAN will be divided by the aggregation rate of the primary nodes  $aggr_{pn}$ .

Lastly, a command passes through the primary LAN if it is directed to one of the nodes that it manages, the probability that a message arrives then is the probability that it goes through its regional  $\frac{1}{n}$  multiplied the probability that the message is for a primary instead of a secondary  $\frac{m}{m+k}$ .

Regarding the secondary LAN the same formulas will be applied for now,

instead of pl we will have sl and the fraction for command will be  $\frac{k}{m+k}$ .

$$V_{pl,t} = 1$$

$$V_{pl,e} = 2$$

$$V_{pl,c} = 1$$

$$\lambda_{pl,t} = m * \frac{\lambda_{pn,t}}{aggr_{pn}}$$

$$\lambda_{pl,e} = m * \lambda_{pn,e}$$

$$\lambda_{pl,c} = \frac{1}{n} * (\frac{m}{m+k}) * \lambda_{cn,c}$$

$$(7)$$

From the previous formulas and the open queue model we can compute the Service Demand, Utilization factor and Response time.

$$D_{pl,t} = V_{pl,t} * S_{pl,t}$$

$$D_{pl,e} = V_{pl,e} * S_{pl,e}$$

$$D_{pl,c} = V_{pl,c} * S_{pl,c}$$

$$U_{pl,t} = \lambda_{pl,t} * D_{pl,t}$$

$$U_{pl,e} = \lambda_{pl,e} * D_{pl,e}$$

$$U_{pl,c} = \lambda_{pl,c} * D_{pl,c}$$

$$U_{pl} = U_{pl,t} + U_{pl,e} + U_{pl,c}$$

$$R_{pl,t} = \frac{D_{pl,t}}{1 - U_{pl}}$$

$$R_{pl,e} = \frac{D_{pl,e}}{1 - U_{pl}}$$

$$R_{pl,c} = \frac{D_{pl,e}}{1 - U_{pl}}$$

$$R_{pl,c} = \frac{D_{pl,c}}{1 - U_{pl}}$$

Regarding the WAN PRIMARY, it forwards all the messages received from the LAN PRIMARY-SECONDARY directly to the LAN PRIMARY. The LAN PRIMARY needs to forward all the messages received from the primary nodes towards the WAN PRIMARY; so we will have the same rate and number of visits per message. The only parameter that can be different between these two LANs is the service time. The same formulas can also be applied to the WAN SECONDARY and the LAN SECONDARY using the parameters that characterize these network.

# 3.7 LAN Primary-Secondary




Figure 8: Focus on regional nodes, LAN primary-secondary, primary WAN and secondary WAN

The Primary-Secondary LAN will relay messages to and from primary and secondary LANs.

Telemetry and transition rate is the sum of the same rates for the lower level nodes, while for the command events, this LAN will receive  $\frac{1}{n}$  command messages from the central, only the ones for its upper level regional node to be forwarded to the correct primary or secondary node.

$$V_{ps,t} = 1$$

$$V_{ps,e} = 2$$

$$V_{ps,c} = 1$$

$$\lambda_{ps,t} = \lambda_{pl,t} + \lambda_{sl,t}$$

$$\lambda_{ps,e} = \lambda_{pl,e} + \lambda_{sl,e}$$

$$\lambda_{ps,c} = \frac{\lambda_{cn,c}}{n}$$
(9)

$$D_{ps,t} = V_{ps,t} * S_{ps,t}$$

$$D_{ps,e} = V_{ps,e} * S_{ps,e}$$

$$D_{ps,c} = V_{ps,c} * S_{ps,c}$$

$$U_{ps,t} = \lambda_{ps,t} * D_{ps,t}$$

$$U_{ps,e} = \lambda_{ps,e} * D_{ps,e}$$

$$U_{ps,c} = \lambda_{ps,c} * D_{ps,c}$$

$$U_{ps} = U_{ps,t} + U_{ps,e} + U_{ps,c}$$

$$R_{ps,t} = \frac{D_{ps,t}}{1 - U_{ps}}$$

$$R_{ps,e} = \frac{D_{ps,e}}{1 - U_{ps}}$$

$$R_{ps,c} = \frac{D_{ps,e}}{1 - U_{ps}}$$

$$R_{ps,c} = \frac{D_{ps,c}}{1 - U_{ps}}$$

## 3.8 Regional Node

The rates are the same as the Primary-Secondary LAN, since all the elements that go through that LAN will need to go through the relative Regional Node.

$$V_{rn,t} = 1$$

$$V_{rn,e} = 2$$

$$V_{rn,c} = 1$$

$$\lambda_{rn,t} = \lambda_{ps,t}$$

$$\lambda_{rn,e} = \lambda_{ps,e}$$

$$\lambda_{rn,c} = \frac{\lambda_{cn,c}}{n}$$
(11)

$$D_{rn,t} = V_{rn,t} * S_{rn,t}$$

$$D_{rn,e} = V_{rn,e} * S_{rn,e}$$

$$D_{rn,c} = V_{rn,c} * S_{rn,c}$$

$$U_{rn,t} = \lambda_{rn,t} * D_{rn,t}$$

$$U_{rn,e} = \lambda_{rn,e} * D_{rn,e}$$

$$U_{rn,c} = \lambda_{rn,c} * D_{rn,c}$$

$$U_{rn} = U_{rn,t} + U_{rn,e} + U_{rn,c}$$

$$R_{rn,t} = \frac{D_{rn,t}}{1 - U_{rn}}$$

$$R_{rn,e} = \frac{D_{rn,e}}{1 - U_{rn}}$$

$$R_{rn,c} = \frac{D_{rn,e}}{1 - U_{rn}}$$

$$R_{rn,c} = \frac{D_{rn,c}}{1 - U_{rn}}$$
(12)

# 3.9 Regional LAN




Figure 9: Focus on regional LAN and regional nodes

The regional LAN connects the central node to all the regionals, for this reason the rate of transition and telemetry will be multiplied by n, the number of regional node.

In particular, regarding the telemetry events the regional node rates will also be divided by the aggregation factor, made by those nodes which will cut the number of messages that will actually be sent up the LAN.

The command rate is not divided by anything since all the commands will

need to go through this LAN.

$$V_{rl,t} = 1$$

$$V_{rl,e} = 2$$

$$V_{rl,c} = 1$$

$$\lambda_{rl,t} = n * \frac{\lambda_{rn,t}}{aggr_{rn}}$$

$$\lambda_{rl,e} = n * \lambda_{rn,e}$$

$$\lambda_{rl,c} = \lambda_{cn,c}$$
(13)

From the previous formulas and the open queue model we can compute the Service Demand, Utilization factor and Response time.

$$D_{rl,t} = V_{rl,t} * S_{rl,t}$$

$$D_{rl,e} = V_{rl,e} * S_{rl,e}$$

$$D_{rl,c} = V_{rl,c} * S_{rl,c}$$

$$U_{rl,t} = \lambda_{rl,t} * D_{rl,t}$$

$$U_{rl,e} = \lambda_{rl,e} * D_{rl,e}$$

$$U_{rl,c} = \lambda_{rl,c} * D_{rl,c}$$

$$U_{rl,c} = U_{rl,t} + U_{rl,e} + U_{rl,c}$$

$$R_{rl,t} = \frac{D_{rl,t}}{1 - U_{rl}}$$

$$R_{rl,e} = \frac{D_{rl,e}}{1 - U_{rl}}$$

$$R_{rl,c} = \frac{D_{rl,e}}{1 - U_{rl}}$$

Regarding the WAN CENTRAL, it forwards all messages from the CENTRAL LAN to the REGIONAL LAN. The REGIONAL LAN instead, forwards all the messages from the regional nodes to the WAN CENTRAL, so the service time and number of visits per message are the same, with the exception of the service time which can be different.

### 3.10 Central LAN




Figure 10: Focus on regional LAN, WAN central, central LAN and central node

The Central LAN has the same traffic as the Regional LAN, with the only different value being the service time.

The reasoning behind this LAN's existence is that there may be more than one central node, by the specific there can be two for fault tolerance and availability.

$$V_{cl,t} = 1$$

$$V_{cl,e} = 2$$

$$V_{cl,c} = 1$$

$$\lambda_{cl,t} = \lambda_{rl,t}$$

$$\lambda_{cl,e} = \lambda_{rl,e}$$

$$\lambda_{cl,c} = \lambda_{cn,c}$$

$$(15)$$

$$D_{cl,t} = V_{cl,t} * S_{cl,t}$$

$$D_{cl,e} = V_{cl,e} * S_{cl,e}$$

$$D_{cl,c} = V_{cl,c} * S_{cl,c}$$

$$U_{cl,t} = \lambda_{cl,t} * D_{cl,t}$$

$$U_{cl,e} = \lambda_{cl,e} * D_{cl,e}$$

$$U_{cl,c} = \lambda_{cl,c} * D_{cl,c}$$

$$U_{cl} = U_{cl,t} + U_{cl,e} + U_{cl,c}$$

$$R_{cl,t} = \frac{D_{cl,t}}{1 - U_{cl}}$$

$$R_{cl,e} = \frac{D_{cl,e}}{1 - U_{cl}}$$

$$R_{cl,c} = \frac{D_{cl,c}}{1 - U_{cl}}$$

$$R_{cl,c} = \frac{D_{cl,c}}{1 - U_{cl}}$$
(16)

### 3.11 Central Node

In the central node  $\lambda_{cn,c}$  is given by the user sending commands to adjust the network(or an automatic system) thus it would just be a parameter.

$$V_{cn,t} = 1$$

$$V_{cn,e} = 2$$

$$V_{cn,c} = 1$$

$$\lambda_{cn,t} = \lambda_{cl,t}$$

$$\lambda_{cn,e} = \lambda_{cl,e}$$

$$(17)$$

$$D_{cn,t} = V_{cn,t} * S_{cn,t}$$

$$D_{cn,e} = V_{cn,e} * S_{cn,e}$$

$$D_{cn,c} = V_{cn,c} * S_{cn,c}$$

$$U_{cn,t} = \lambda_{cn,t} * D_{cn,t}$$

$$U_{cn,e} = \lambda_{cn,e} * D_{cn,e}$$

$$U_{cn,c} = \lambda_{cn,c} * D_{cn,c}$$

$$U_{cn} = U_{cn,t} + U_{cn,e} + U_{cn,c}$$

$$R_{cn,t} = \frac{D_{cn,t}}{1 - U_{cn}}$$

$$R_{cn,e} = \frac{D_{cn,e}}{1 - U_{cn}}$$

$$R_{cn,c} = \frac{D_{cn,c}}{1 - U_{cn}}$$

$$R_{cn,c} = \frac{D_{cn,c}}{1 - U_{cn}}$$
(18)

### 3.11.1 Central node storage system

In this first draft, the central node storage system is not characterized with a specific system(RAID 1-5, etc) and it is modeled as a simple queue filled by the central node.

Since the central node will do some aggregation and computations on the telemetry messages received by the regional nodes, the rate arriving on the disk will be divided by the aggregation parameter of the central node.

In this model the commands go directly to the lower levels, in a future extension of the project they may need to be logged onto the disk and thus we will need a  $\lambda_{cns,c}$ .

$$V_{cns,t} = 1$$

$$V_{cns,e} = 1$$

$$\lambda_{cns,t} = \frac{\lambda_{cn,t}}{aggr_{cn}}$$

$$\lambda_{cns,e} = \lambda_{cn,e}$$
(19)

$$D_{cn,t} = V_{cn,t} * S_{cn,t}$$

$$D_{cn,e} = V_{cn,e} * S_{cn,e}$$

$$U_{cn,t} = \lambda_{cn,t} * D_{cn,t}$$

$$U_{cn,e} = \lambda_{cn,e} * D_{cn,e}$$

$$U_{cn} = U_{cn,t} + U_{cn,e}$$

$$R_{cn,t} = \frac{D_{cn,t}}{1 - U_{cn}}$$

$$R_{cn,e} = \frac{D_{cn,e}}{1 - U_{cn}}$$
(20)