sendfile(2) — Linux manual page

NAME | SYNOPSIS | DESCRIPTION | RETURN VALUE | ERRORS | VERSIONS | CONFORMING TO | NOTES | SEE ALSO | COLOPHON

Search online pages

SENDFILE(2)

Linux Programmer's Manual

SENDFILE(2)

NAME

top

sendfile - transfer data between file descriptors

SYNOPSIS

top

#include <sys/sendfile.h>

ssize_t sendfile(int out fd, int in fd, off_t *offset, size_t count);

DESCRIPTION

top

sendfile() copies data between one file descriptor and another.
Because this copying is done within the kernel, sendfile() is
more efficient than the combination of read(2) and write(2),
which would require transferring data to and from user space.

in_fd should be a file descriptor opened for reading and out_fd should be a descriptor opened for writing.

If offset is not NULL, then it points to a variable holding the file offset from which **sendfile**() will start reading data from in_fd . When **sendfile**() returns, this variable will be set to the offset of the byte following the last byte that was read. If offset is not NULL, then **sendfile**() does not modify the file offset of in_fd ; otherwise the file offset is adjusted to reflect the number of bytes read from in_fd .

If offset is NULL, then data will be read from in_fd starting at the file offset, and the file offset will be updated by the call.

count is the number of bytes to copy between the file
descriptors.

The in fd argument must correspond to a file which supports

mmap(2)-like operations (i.e., it cannot be a socket).

In Linux kernels before 2.6.33, *out_fd* must refer to a socket. Since Linux 2.6.33 it can be any file. If it is a regular file, then **sendfile**() changes the file offset appropriately.

RETURN VALUE top

If the transfer was successful, the number of bytes written to <code>out_fd</code> is returned. Note that a successful call to <code>sendfile()</code> may write fewer bytes than requested; the caller should be prepared to retry the call if there were unsent bytes. See also <code>NOTES</code>.

On error, -1 is returned, and errno is set to indicate the error.

ERRORS top

EAGAIN Nonblocking I/O has been selected using **O_NONBLOCK** and the write would block.

EBADF The input file was not opened for reading or the output file was not opened for writing.

EFAULT Bad address.

EINVAL Descriptor is not valid or locked, or an mmap(2)-like operation is not available for *in_fd*, or *count* is negative.

EINVAL out_fd has the **O_APPEND** flag set. This is not currently supported by **sendfile**().

EIO Unspecified error while reading from in fd.

ENOMEM Insufficient memory to read from in_fd.

EOVERFLOW

count is too large, the operation would result in exceeding the maximum size of either the input file or the output file.

ESPIPE offset is not NULL but the input file is not seekable.

VERSIONS top

sendfile() first appeared in Linux 2.2. The include file
<sys/sendfile.h> is present since glibc 2.1.

CONFORMING TO top

Not specified in POSIX.1-2001, nor in other standards.

Other UNIX systems implement **sendfile**() with different semantics and prototypes. It should not be used in portable programs.

NOTES top

sendfile() will transfer at most 0x7ffff000 (2,147,479,552)
bytes, returning the number of bytes actually transferred. (This
is true on both 32-bit and 64-bit systems.)

If you plan to use **sendfile**() for sending files to a TCP socket, but need to send some header data in front of the file contents, you will find it useful to employ the **TCP_CORK** option, described in tcp(7), to minimize the number of packets and to tune performance.

In Linux 2.4 and earlier, out_fd could also refer to a regular file; this possibility went away in the Linux 2.6.x kernel series, but was restored in Linux 2.6.33.

The original Linux **sendfile**() system call was not designed to handle large file offsets. Consequently, Linux 2.4 added **sendfile64**(), with a wider type for the *offset* argument. The glibc **sendfile**() wrapper function transparently deals with the kernel differences.

Applications may wish to fall back to read(2)/write(2) in the case where sendfile() fails with EINVAL or ENOSYS.

If out_fd refers to a socket or pipe with zero-copy support, callers must ensure the transferred portions of the file referred to by in_fd remain unmodified until the reader on the other end of out_fd has consumed the transferred data.

The Linux-specific splice(2) call supports transferring data between arbitrary file descriptors provided one (or both) of them is a pipe.

SEE ALSO top

copy file range(2), mmap(2), open(2), socket(2), splice(2)

COLOPHON top

This page is part of release 5.11 of the Linux man-pages project. A description of the project, information about reporting bugs,

and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

Linux 2021-03-22 SENDFILE(2)

Pages that refer to this page: copy_file_range(2), send(2), splice(2), syscalls(2), socket(7), tcp(7)

Copyright and license for this manual page

HTML rendering created 2021-04-01 by Michael Kerrisk, author of *The Linux Programming Interface*, maintainer of the Linux *man-pages* project.

For details of in-depth **Linux/UNIX system programming training courses** that I teach, look here.

Hosting by jambit GmbH.

