NT219- Cryptography

Week 6: Asymmetric Cryptography

PhD. Ngoc-Tu Nguyen

tunn@uit.edu.vn

Outline

- Why asymmetric cryptography?
- Factoring Based Cryptography (P1)
  - RSA
  - *Rabin*
- Logarithm Based Cryptography (P2)
- Elliptic Curve Cryptography (P3)
- Some advanced cryptography system (quantum resistance)

Textbooks and References

- Text books



[1] Chapter 9,10



[2] Chapter 5,6,7

Terminology Related to Asymmetric Encryption

Asymmetric Keys
Two related keys, a public key and a private key, that are used to perform complementary operations, such as encryption and decryption or signature generation and signature verification.

Public Key Certificate
A digital document issued and digitally signed by the private key of a Certification Authority that binds the name of a subscriber to a public key. The certificate indicates that the subscriber identified in the certificate has sole control and access to the corresponding private key.

Public Key (Asymmetric) Cryptographic Algorithm
A cryptographic algorithm that uses two related keys, a public key and a private key. The two keys have the property that deriving the private key from the public key is computationally infeasible.

Public Key Infrastructure (PKI)
A set of policies, processes, server platforms, software and workstations used for the purpose of administering certificates and public-private key pairs, including the ability to issue, maintain, and revoke public key certificates.

Source: *Glossary of Key Information Security Terms*, NISTIR 7298.

Motivations

Symmetric cipher vs Asymmetric cipher



Why Public-Key Cryptosystems?

- The concept of public-key cryptography evolved from an attempt to overcome two of the most difficult problems associated with symmetric encryption:
- **Key distribution**
  - How to have secure communications in general without having to trust a KDC with your key
- **Digital signatures**
  - How to verify that a message comes intact from the claimed sender
- Whitfield Diffie and Martin Hellman from Stanford University achieved a breakthrough in 1976 by coming up with a method that addressed both problems and was radically different from all previous approaches to cryptography

Misconceptions about Public-Key Encryption

- Public-key encryption is more secure from cryptanalysis than symmetric encryption
- Public-key encryption is a general-purpose technique that has made symmetric encryption obsolete
- There is a feeling that key distribution is trivial when using public-key encryption, compared to the cumbersome handshaking involved with key distribution centers for symmetric encryption

Public-Key Cryptosystems

- A public-key encryption scheme has six ingredients:
- **Plaintext**
  - The readable message or data that is fed into the algorithm as input
- **Encryption algorithm**
  - Performs various transforma-tions on the plaintext
- **Public key**
  - Used for encryption or decryption
- **Private key**
  - Used for encryption or decryption
- **Ciphertext**
  - The scrambled message produced as output
- **Decryption algorithm**
  - Accepts the ciphertext and the matching key and produces the original plaintext

Public-Key Cryptography (1 of 2)



(a) Encryption with public key

Public-Key Cryptography (2 of 2)



(b) Encryption with private key

Conventional and Public-key Encryption

Conventional Encryption	Public-Key Encryption
Needed to Work: 1. The same algorithm with the same key is used for encryption and decryption. 2. The sender and receiver must share the algorithm and the key.	*Needed to Work:* 1. One algorithm is used for encryption and a related algorithm for decryption with a pair of keys, one for encryption and one for decryption. 2. The sender and receiver must each have one of the matched pair of keys (not the same one).
Needed for Security: 1. The key must be kept secret. 2. It must be impossible or at least impractical to decipher a message if the key is kept secret. 3. Knowledge of the algorithm plus samples of ciphertext must be insufficient to determine the key.	*Needed for Security:* 1. One of the two keys must be kept secret. 2. It must be impossible or at least impractical to decipher a message if one of the keys is kept secret. 3. Knowledge of the algorithm plus one of the keys plus samples of ciphertext must be insufficient to determine the other key.

Public-Key Cryptosystem: Confidentiality

Public-Key Cryptosystem: Confidentiality



Public-Key Cryptosystem: Authentication

Public-Key Cryptosystem: Authentication



Public-Key Cryptosystem: Authentication and Secrecy

Public-Key Cryptosystem: Authentication and Secrecy



Applications for Public-Key Cryptosystems

Public-key cryptosystems can be classified into three categories:

- **Encryption/decryption**
  - The sender encrypts a message with the recipient's public key
- **Digital signature**
  - The sender "signs" a message with its private key
- **Key exchange**
  - Two sides cooperate to exchange a session key

Some algorithms are suitable for all three applications, whereas others can be used only for one or two

Applications for Public-Key Cryptosystems

Algorithm	Encryption/Decryption	Digital Signature	Key Exchange
RSA	Yes	Yes	Yes
Elliptic Curve	Yes	Yes	Yes
Diffie–Hellman	No	No	Yes
DSS	No	Yes	No

Public-Key Requirements

- Cryptology= Cryptography + Cryptanalysis

Secret writing

How?

"Readable data" "One-way function" "Unreadable data"

Plaintext ⟷ Ciphertext

Easy to compute →

"Hard" to compute ←

Public-Key Requirements (1 of 2)

- Conditions that these algorithms must fulfill:
  - It is computationally easy for a party B to generate a pair (public-key PU_b, private key PR_b)
  - It is computationally easy for a sender A, knowing the public key and the message to be encrypted, to generate the corresponding ciphertext
  - It is computationally easy for the receiver B to decrypt the resulting ciphertext using the private key to recover the original message
  - It is computationally infeasible for an adversary, knowing the public key, to determine the private key
  - It is computationally infeasible for an adversary, knowing the public key and a ciphertext, to recover the original message
  - The two keys can be applied in either order

Public-Key Requirements (2 of 2)

- **Need a trap-door one-way function**
  - A one-way function is one that maps a domain into a range such that every function value has a unique inverse, with the condition that the calculation of the function is easy, whereas the calculation of the inverse is infeasible
    - $Y = f(X)$ easy
    - $X = f^{-1}(Y)$ infeasible
- A trap-door one-way function is a family of invertible functions f_k, such that
  - $Y = f_k(X)$ easy, if k and X are known
  - $X = f_k^{-1}(Y)$ easy, if k and Y are known
  - $X = f_k^{-1}(Y)$ infeasible, if Y known but k not known
- **A practical public-key scheme depends on a suitable trap-door one-way function**

Public-Key Cryptanalysis

- A public-key encryption scheme is vulnerable to a brute-force attack
  - Countermeasure: use large keys
  - Key size must be small enough for practical encryption and decryption
  - Key sizes that have been proposed result in encryption/decryption speeds that are too slow for general-purpose use
  - Public-key encryption is currently confined to key management and signature applications
- Another form of attack is to find some way to compute the private key given the public key
  - To date it has not been mathematically proven that this form of attack is infeasible for a particular public-key algorithm
- Finally, there is a probable-message attack
  - This attack can be thwarted by appending some random bits to simple messages

Outline

- Why asymmetric cryptography?
- Factoring Based Cryptography (P1)
  - RSA
  - *Rabin*
- Logarithm Based Cryptography (P2)
- Elliptic Curve Cryptography (P3)
- Some advanced cryptography system (quantum resistance)

Rivest-Shamir-Adleman (RSA) Algorithm

- Developed in 1977 at MIT by Ron Rivest, Adi Shamir & Len Adleman
- Most widely used general-purpose approach to public-key encryption
- Is a cipher in which the plaintext and ciphertext are integers between 0 and $n - 1$ for some n
  - A typical size for n is 3072 bits

Cryptograph review

- Cryptology= Cryptography + Cryptanalysis

Secret writing

How?

"Readable data" ⟷ "One-way function" ⟷ "Unreadable data"

Plaintext

Ciphertext

Easy to compute →

"Hard" to compute ←

Prime factorization problem

Factorize number

$N = 864$

$= 2^5 \times 3^3$



Input: n-bits composite number N

Output: $N = p_1^{\alpha_1} p_2^{\alpha_2} \ldots p_k^{\alpha_k}, \alpha_k \in {}^{*}$

No classical algorithm has been published that can factor all integers in polynomial time.

https://en.wikipedia.org/wiki/Integer_factorization

Prime factorization problem

"Prime factorization one-way function!"

Input: large prime number p, q and a large number d

Easy to compute $\longrightarrow$

$$\begin{cases} n = p.q \\ e = d^{-1} \bmod (p-1)(q-1) \\ C = M^{e} \bmod n \end{cases}$$

Input: n, e, C

"Hard" to compute $\longleftarrow$

$$\begin{cases} n = p.q \leftarrow p, q \\ d = e^{-1} \bmod (p-1)(q-1) \end{cases}$$

$$\boxed{C^{d} \bmod n = M^{e.d} \bmod n = M^{e.d \bmod (p-1)(q-1)} \bmod n = M}$$

RSA Algorithm

- RSA makes use of an expression with exponentials
- Plaintext is encrypted in blocks with each block having a binary value less than some number *n*
- Encryption and decryption are of the following form, for some plaintext block *M* and ciphertext block C

$$C = M^{e} \bmod n$$

$$M = C^{d} \bmod n = (M^{e})^{d} \bmod n = M^{ed} \bmod n$$

- Both sender and receiver must know the value of *n*
- The sender knows the value of *e,* and only the receiver knows the value of *d*
- This is a public-key encryption algorithm with a public key of *PU={e,n}* and a private key of *PR={d,n}*

Algorithm Requirements

- For this algorithm to be satisfactory for public-key encryption, the following requirements must be met:
  1. It is possible to find values of *e, d, n* such that M^{ed} mod $n = M$ for all $M < n$
  2. It is relatively easy to calculate M^e mod n and C^d mod n for all values of $M < n$
  3. It is infeasible to determine *d* given *e* and *n*



The RSA Algorithm

Key Generation by Alice	
Select p, q	p and q both prime, $p \neq q$
Calculate $n = p \times q$	
Calculate $\phi(n)=(p-1)(q-1)$	
Select integer e	$\gcd(\phi(n), e) = 1; 1 < e < \phi(n)$
Calculate d	$d \equiv e^{-1} \pmod{\phi(n)}$
Public key	$PU = \{e, n\}$
Private key	$PR = \{d, n\}$

Encryption by Bob with Alice's Public Key	
Plaintext:	$M < n$
Ciphertext:	$C = M^e \bmod n$

Decryption by Alice with Alice's Private Key	
Ciphertext:	C
Plaintext:	$M = C^d \bmod n$

Example of RSA Algorithm



RSA Processing of Multiple Blocks (1/2)



RSA Processing of Multiple Blocks (2/2)



Exponentiation in Modular Arithmetic

- Both encryption and decryption in RSA involve raising an integer to an integer power, mod *n*
- Can make use of a property of modular arithmetic:

  $[(a \bmod n) \times (b \bmod n)] \bmod n = (a \times b) \bmod n$

- With RSA you are dealing with potentially large exponents so efficiency of exponentiation is a consideration

Algorithm for Computing a^b mod n

Note: The integer b is expressed as a binary number $b_k b_{k-1} \ldots b_0$

```
c ← 0; f ← 1
for i ← k downto 0
    do  c ← 2 × c
        f ← (f × f) mod n
    if  b_i = 1
        then c ← c + 1
             f ← (f × a) mod n
return f
```


Algorithm for Computing a^b mod n

Result of the Fast Modular Exponentiation Algorithm for a^b mod n, where a = 7, b = 560 = 1000110000, and n = 561

I	9	8	7	6	5	4	3	2	1	0
B_i	1	0	0	0	1	1	0	0	0	0
C	1	2	4	8	17	35	70	140	280	560
F	7	49	157	526	160	241	298	166	67	1

Efficient Operation Using the Public Key

- To speed up the operation of the RSA algorithm using the public key, a specific choice of *e* is usually made
- The most common choice is 65537 (2^{16} + 1)
  - Two other popular choices are *e*=3 and *e*=17
  - Each of these choices has only two 1 bits, so the number of multiplications required to perform exponentiation is minimized
  - With a very small public key, such as *e* = 3, RSA becomes vulnerable to a simple attack

Efficient Operation Using the Private Key

- Decryption uses exponentiation to power *d*
  - A small value of *d* is vulnerable to a brute-force attack and to other forms of cryptanalysis
- Can use the Chinese Remainder Theorem (CRT) to speed up computation
  - The quantities *d* mod (*p – 1)* and *d* mod (*q – 1)* can be precalculated
  - End result is that the calculation is approximately four times as fast as evaluating $M = C^d \bmod n$ directly

Key Generation

- Before the application of the public-key cryptosystem each participant must generate a pair of keys:
  - Determine two prime numbers *p* and *q*
  - Select either *e* or *d* and calculate the other
- Because the value of *n* = *pq* will be known to any potential adversary, primes must be chosen from a sufficiently large set
  - The method used for finding large primes must be reasonably efficient



Procedure for Picking a Prime Number

- Pick an odd integer *n* at random
- Pick an integer *a* < *n* at random
- Perform the probabilistic primality test with *a* as a parameter. If *n* fails the test, reject the value *n* and go to step 1
- If *n* has passed a sufficient number of tests, accept *n;* otherwise, go to step 2



The Security of RSA

- Five possible approaches to attacking RSA are:
  - Brute force
    - Involves trying all possible private keys
  - Mathematical attacks
    - There are several approaches, all equivalent in effort to factoring the product of two primes
  - Timing attacks
    - These depend on the running time of the decryption algorithm
  - Hardware fault-based attack
    - This involves inducing hardware faults in the processor that is generating digital signatures
  - Chosen ciphertext attacks
    - This type of attack exploits properties of the RSA algorithm

Timing Attacks

- Paul Kocher, a cryptographic consultant, demonstrated that a snooper can determine a private key by keeping track of how long a computer takes to decipher messages
- Are applicable not just to RSA but to other public-key cryptography systems
- Are alarming for two reasons:
  - It comes from a completely unexpected direction
  - It is a ciphertext-only attack

Countermeasures

- **Constant exponentiation time**
  - Ensure that all exponentiations take the same amount of time before returning a result; this is a simple fix but does degrade performance
- **Random delay**
  - Better performance could be achieved by adding a random delay to the exponentiation algorithm to confuse the timing attack
- **Blinding**
  - Multiply the ciphertext by a random number before performing exponentiation; this process prevents the attacker from knowing what ciphertext bits are being processed inside the computer and therefore prevents the bit-by-bit analysis essential to the timing attack

Fault-Based Attack

- An attack on a processor that is generating RSA digital signatures
  - Induces faults in the signature computation by reducing the power to the processor
  - The faults cause the software to produce invalid signatures which can then be analyzed by the attacker to recover the private key
- The attack algorithm involves inducing single-bit errors and observing the results
- While worthy of consideration, this attack does not appear to be a serious threat to RSA
  - It requires that the attacker have physical access to the target machine and is able to directly control the input power to the processor

Chosen Ciphertext Attack (CCA)

- The adversary chooses a number of ciphertexts and is then given the corresponding plaintexts, decrypted with the target's private key
  - Thus the adversary could select a plaintext, encrypt it with the target's public key, and then be able to get the plaintext back by having it decrypted with the private key
  - The adversary exploits properties of RSA and selects blocks of data that, when processed using the target's private key, yield information needed for cryptanalysis
- To counter such attacks, RSA Security Inc. recommends modifying the plaintext using a procedure known as *optimal asymmetric encryption padding* (OAEP)

Encryption Using Optimal Asymmetric Encryption Padding (OAEP)



P = encoding parameters
M = message to be encoded
H = hash function
DB = data block
MGF = mask generating function
EM = encoded message

Summary

- Present an overview of the basic principles of public-key cryptosystems
- Explain the two distinct uses of public-key cryptosystems
- List and explain the requirements for a public-key cryptosystem
- Present an overview of the RSA algorithm
- Understand the timing attack
- Summarize the relevant issues related to the complexity of algorithms