Chapter 3
Transport Layer



Computer Networking: A Top Down Approach ,
6th edition.
James F. Kurose,
Keith W. Ross.
Addison-Wesley, 2013.

Chapter 3: Transport Layer

Our goals:

- understand principles behind transport layer services:
  - multiplexing/demultiplexing
  - reliable data transfer
  - flow control
  - congestion control
- learn about transport layer protocols in the Internet:
  - User Datagram Protocol (UDP) : connectionless transport
  - Transmission Control Protocol (TCP) : connection-oriented transport
  - TCP congestion control

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport services and protocols

- provide *logical communication* between application processes running on different hosts
- transport protocols run in end systems
  - send side: breaks application messages into segments, passes to network layer
  - receive side: reassembles segments into messages, passes to application layer
- more than one transport protocol available to applicatioins
  - Internet: TCP and UDP



Transport vs. network layer

- *transport layer:* logical communication between processes
  - relies on, enhances, network layer services
- *network layer:* logical communication between hosts

Household analogy:

12 kids sending letters to 12 kids

- processes = kids
- application messages = letters in envelopes
- hosts = houses
- transport protocol = Ann and Bill
- network-layer protocol = postal service

Internet transport-layer protocols

- reliable, in-order delivery (TCP)
  - congestion control
  - flow control
  - connection setup
- unreliable, unordered delivery: UDP
  - no-frills extension of "best-effort" IP
- services not available:
  - delay guarantees
  - bandwidth guarantees



Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Multiplexing/demultiplexing

multiplexing at sender:
handle data from multiple sockets, add transport header (later used for demultiplexing)

demultiplexing at receiver:
use header info to deliver received segments to correct socket



How demultiplexing works

- host receives IP datagrams
  - each datagram has source IP address, destination IP address
  - each datagram carries 1 transport-layer segment
  - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

Connectionless demultiplexing

- Create sockets with port numbers:

```
DatagramSocket mySocket1 = new
   DatagramSocket(12534);
DatagramSocket mySocket2 = new
   DatagramSocket(12535);
```

- UDP socket identified by two-tuple:

(dest IP address, dest port number)

- When host receives UDP segment:
  - checks destination port number in segment
  - directs UDP segment to socket with that port number
- datagrams with *same destination port number,* but different source IP addresses and/or source port numbers will be directed to *same socket* at destination

Connectionless demux: example

```
DatagramSocket
 mySocket2 = new
 DatagramSocket
  (9157);
```

```
DatagramSocket
  serverSocket = new
  DatagramSocket
  (6428);
```

```
DatagramSocket
 mySocket1 = new
 DatagramSocket
 (5775);
```



Connection-oriented demux

- TCP socket identified by 4-tuple:
  1. source IP address
  2. source port number
  3. destination IP address
  4. destination port number
- receiver host uses all four values to direct segment to appropriate socket
- Server host may support many simultaneous TCP sockets:
  - each socket identified by its own 4-tuple
- Web servers have different sockets for each connecting client
  - non-persistent HTTP will have different socket for each request

Connection-oriented demux: example



three segments, all destined to IP address: B,
dest port: 80 are demultiplexed to *different* sockets

Connection-oriented demux: example



Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
  - lost
  - delivered out-of-order to application
- *connectionless:*
  - no handshaking between UDP sender, receiver
  - each UDP segment handled independently of others

- UDP use:
  - streaming multimedia applications (loss tolerant, rate sensitive)
  - DNS
  - SNMP
- reliable transfer over UDP:
  - add reliability at application layer
  - application-specific error recovery!

UDP: segment header



UDP segment format

why is there a UDP?

- no connection establishment (which can add delay)
- simple: no connection state at sender, receiver
- small header size
- no congestion control: UDP can blast away as fast as desired

UDP checksum

Goal: detect "errors" (e.g., flipped bits) in transmitted segment

Sender:
- treat segment contents as sequence of 16-bit integers
- checksum: addition (1's complement sum) of segment contents
- sender puts checksum value into UDP checksum field

Receiver:
- compute the sum of all 16-bit integers in the received segment (including checksum)
- If the sum is all 1's, no error detected. Otherwise, errors have been introduce to the packet.

Internet Checksum Example

- Note
  - When adding numbers, a carryout from the most significant bit needs to be added to the result
- Example: add two 16-bit integers

		1	1	1	0	0	1	1	0	0	1	1	0	0	1	1	0
		1	1	0	1	0	1	0	1	0	1	0	1	0	1	0	1
wraparound	1	1	0	1	1	1	0	1	1	1	0	1	1	1	0	1	1
sum		1	0	1	1	1	0	1	1	1	0	1	1	1	1	0	0
checksum		0	1	0	0	0	1	0	0	0	1	0	0	0	0	1	1

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Principles of Reliable data transfer

- important in application, transport, link layers
- top-10 list of important networking topics!



(a) provided service

- characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

Principles of Reliable data transfer

- important in app., transport, link layers
- top-10 list of important networking topics!



- characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

Principles of Reliable data transfer

- important in app., transport, link layers
- top-10 list of important networking topics!



- characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

Reliable data transfer: getting started

rdt_send(): called from above, (e.g., by app.). Passed data to deliver to receiver upper layer

deliver_data(): called by **rdt** to deliver data to upper



udt_send(): called by rdt, to transfer packet over unreliable channel to receiver

rdt_rcv(): called when packet arrives on rcv-side of channel

Reliable data transfer: getting started

We'll:

- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
  - but control info will flow on both directions!
- use finite state machines (FSM) to specify sender, receiver



Rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
  - no bit errors
  - no loss of packets
- separate FSMs for sender, receiver:
  - sender sends data into underlying channel
  - receiver read data from underlying channel



sender receiver

rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
  - checksum to detect bit errors
- *the* question: how to recover from errors:

How do humans recover from "errors" during conversation?

Rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
  - checksum to detect bit errors
- *the question*: how to recover from errors:
  - *acknowledgements (ACKs):* receiver explicitly tells sender that packet received OK
  - *negative acknowledgements (NAKs):* receiver explicitly tells sender that packet had errors
  - sender retransmits packet on receipt of NAK
- new mechanisms in **`rdt2.0`** (beyond **`rdt1.0`**):
  1. error detection
  2. receiver feedback: control messages (ACK,NAK) receiver->sender
  3. retransmission

rdt2.0: FSM specification



rdt2.0: operation with no errors



rdt2.0: error scenario



rdt2.0 has a fatal flaw!

What happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate

Handling duplicates:

1. sender retransmits current packet if ACK/NAK garbled
2. sender adds *sequence number* to each packet
3. receiver discards (doesn't deliver up) duplicate packet

stop and wait
Sender sends one packet, then waits for receiver response

rdt2.1: sender, handles garbled ACK/NAKs



rdt2.1: receiver, handles garbled ACK/NAKs



rdt2.1: discussion

Sender:

- sequence # added to packet
- two sequence #'s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
  - state must "remember" whether "current" packet has 0 or 1 sequence #

Receiver:

- must check if received packet is duplicate
  - state indicates whether 0 or 1 is expected packet sequence #
- note: receiver can *not* know if its last ACK/NAK received OK at sender

rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last packet received OK
  - receiver must *explicitly* include sequence # of packet being ACKed
- duplicate ACK at sender results in same action as NAK: *retransmit current packet*

rdt2.2: sender, receiver fragments



rdt3.0: channels with errors *and* loss

New assumption: underlying channel can also lose packets (data or ACKs)

- checksum, sequence #, ACKs, retransmissions will be of help, but not enough

Approach: sender waits "reasonable" amount of time for ACK

- retransmits if no ACK received in this time
- if packet (or ACK) just delayed (not lost):
  - retransmission will be duplicate, but use of sequence #'s already handles this
  - receiver must specify sequence # of packet being ACKed
- requires countdown timer

rdt3.0 sender



rdt3.0 in action



(a) no loss

(b) packet loss

rdt3.0 in action



(c) ACK loss



(d) premature timeout/ delayed ACK

Performance of rdt3.0

- rdt3.0 works, but performance stinks
- ex: 1 Gbps link, 15 ms prop. delay, 8000 bit packet:

$$d_{trans} = \frac{L}{R} = \frac{8000\,\text{bits}}{10^9\,\text{bps}} = 8\,\text{microseconds}$$

  - U_{sender}: utilization – fraction of time sender busy sending

$$U_{sender} = \frac{L / R}{RTT + L / R} = \frac{.008}{30.008} = 0.00027$$

  - 1KB pkt every 30 msec -> 33kB/sec throughtput over 1 Gbps link
  - network protocol limits use of physical resources!

rdt3.0: stop-and-wait operation



$$U_{\text{sender}} = \frac{L / R}{RTT + L / R} = \frac{.008}{30.008} = 0.00027$$

Pipelined protocols

Pipelining: sender allows multiple, "in-flight", yet-to-be-acknowledged packets

1. range of sequence numbers must be increased
2. buffering at sender and/or receiver



(a) a stop-and-wait protocol in operation (b) a pipelined protocol in operation

- Two generic forms of pipelined protocols: *go-Back-N, selective repeat*

Pipelining: increased utilization



Increase utilization by a factor of 3!

$$U_{sender} = \frac{3 * L / R}{RTT + L / R} = \frac{.024}{30.008} = 0.0008$$

Pipelining Protocols

Go-back-N: big picture:

- Sender can have up to N unacked packets in pipeline
- Receiver only sends cumulative acks
  - Doesn't ack packet if there's a gap
- Sender has timer for oldest unacked packet
  - If timer expires, retransmit all unacked packets

Selective Repeat: big picture

- Sender can have up to N unacked packets in pipeline
- Receiver sends *individual ack* for each packet
- Sender maintains timer for each unacked packet
  - When timer expires, retransmit only unacked packet

Go-Back-N

Sender:

- k-bit sequence # in packet header
- "window" of up to N, consecutive unack'ed packets allowed



- ACK(n): ACKs all packets up to, including sequence # n - "cumulative ACK"
    - may receive duplicate ACKs (see receiver)
- timer for each in-flight packet
- *timeout(n):* retransmit packet N and all higher sequence # packets in window

GBN: sender extended FSM



GBN: receiver extended FSM



- ACK-only: always send ACK for correctly-received packet with highest *in-order* seq #
  - may generate duplicate ACKs
  - need only remember **expectedseqnum**
- out-of-order packet:
  - discard (don't buffer) -> no receiver buffering!
  - Re-ACK packet with highest in-order sequence #

GBN in action



Selective Repeat

- receiver *individually* acknowledges all correctly received packets
  - buffers packets, as needed, for eventual in-order delivery to upper layer
- sender only resends packets for which ACK not received
  - sender timer for each unACKed packet
- sender window
  - N consecutive sequence #'s
  - again limits sequence #s of sent, unACKed packets

Selective repeat: sender, receiver windows



Selective repeat

sender

data from above :

- if next available sequence # in window, send packet

timeout(n):

- resend packet n, restart timer

ACK(n) in [sendbase,sendbase+N]:

- mark packet n as received
- if n smallest unACKed packet, advance window base to next unACKed sequence #

receiver

packet n in [rcvbase, rcvbase+N-1]

- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order packets), advance window to next not-yet-received packet

packet n in [rcvbase-N,rcvbase-1]

- ACK(n)

otherwise:

- ignore

Selective repeat in action



Q: what happens when ack2 arrives?

Selective repeat: dilemma

example:

- seq #'s: 0, 1, 2, 3
- window size=3
- receiver sees no difference in two scenarios!
- duplicate data accepted as new in (b)

Q: what relationship between seq # size and window size to avoid problem in (b)?



Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

TCP: Overview

RFCs: 793, 1122, 1323, 2018, 2581

- point-to-point:
  - one sender, one receiver
- reliable, in-order *byte steam:*
  - no "message boundaries"
- pipelined:
  - TCP congestion and flow control set window size
- *send & receive buffers*



- full duplex data:
  - bi-directional data flow in same connection
  - MSS: maximum segment size
- connection-oriented:
  - handshaking (exchange of control msgs) initial's sender, receiver state before data exchange
- flow controlled:
  - sender will not overwhelm receiver

TCP segment structure



TCP seq. #'s and ACKs

Seq. #'s:

- byte stream "number" of first byte in segment's data

ACKs:

- seq # of next byte expected from other side
- cumulative ACK

Q: how receiver handles out-of-order segments

- A: TCP specification doesn't say, - up to implementor



simple telnet scenario

TCP Round Trip Time and Timeout

Q: how to set TCP timeout value?

- longer than RTT
  - but RTT varies
- too short: premature timeout
  - unnecessary retransmissions
- too long: slow reaction to segment loss

Q: how to estimate RTT?

- **`SampleRTT`**: measured time from segment transmission until ACK receipt
  - ignore retransmissions
- **`SampleRTT`** will vary, want estimated RTT "smoother"
  - average several recent measurements, not just current **`SampleRTT`**

TCP round trip time, timeout

```
EstimatedRTT = (1- α)*EstimatedRTT + α*SampleRTT
```

- exponential weighted moving average
- influence of past sample decreases exponentially fast
- typical value: $\alpha = 0.125$



TCP Round Trip Time and Timeout

Setting the timeout

- `EstimtedRTT` plus "safety margin"
  - large variation in `EstimatedRTT` -> larger safety margin
- first estimate of how much SampleRTT deviates from EstimatedRTT:

```
DevRTT = (1-β)*DevRTT +
              β*|SampleRTT-EstimatedRTT|

(typically, β = 0.25)
```

Then set timeout interval:

```
TimeoutInterval = EstimatedRTT + 4*DevRTT
```

estimated RTT "safety margin"

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

TCP reliable data transfer

- TCP creates reliable data transfer service on top of IP's unreliable service
  - Pipelined segments
  - Cumulative acks
  - TCP uses single retransmission timer
- Retransmissions are triggered by:
  1. timeout events
  2. duplicate acks
- Initially consider simplified TCP sender:
  - ignore duplicate acks
  - ignore flow control, congestion control

TCP sender events:

data received from app:

- Create segment with sequence #
- sequence # is byte-stream number of first data byte in segment
- start timer if not already running (think of timer as for oldest unacked segment)
- expiration interval: `TimeOutInterval`

timeout:

- retransmit segment that caused timeout
- restart timer

Ack received:

- If acknowledges previously unacked segments
  - update what is known to be acked
  - start timer if there are outstanding segments

TCP sender (simplified)

```
NextSeqNum = InitialSeqNum
SendBase = InitialSeqNum

 loop (forever) {
   switch(event)

   event: data received from application above
         create TCP segment with sequence number NextSeqNum
         if (timer currently not running)
              start timer
         pass segment to IP
         NextSeqNum = NextSeqNum + length(data)

    event: timer timeout
         retransmit not-yet-acknowledged segment with
               smallest sequence number
         start timer

    event: ACK received, with ACK field value of y
         if (y > SendBase) {
              SendBase = y
              if (there are currently not-yet-acknowledged segments)
                     start timer
              }

  }  /* end of loop forever */
```

Comment:

- SendBase-1: last cumulatively ack'ed byte

Example:

- SendBase-1 = 71; y= 73, so the rcvr wants 73+ ; y > SendBase, so that new data is acked

TCP: retransmission scenarios



lost ACK scenario

premature timeout

TCP retransmission scenarios (more)



Cumulative ACK scenario

TCP ACK generation [RFC 1122, RFC 2581]

Event at Receiver	TCP Receiver action
Arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	Delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
Arrival of in-order segment with expected seq #. One other segment has ACK pending	Immediately send single cumulative ACK, ACKing both in-order segments
Arrival of out-of-order segment higher-than-expect seq. # . Gap detected	Immediately send *duplicate ACK*, indicating seq. # of next expected byte
Arrival of segment that partially or completely fills gap	Immediate send ACK, provided that segment starts at lower end of gap

TCP fast retransmit

- time-out period often relatively long:
  - long delay before resending lost packet
- detect lost segments via duplicate ACKs.
  - sender often sends many segments back-to-back
  - if segment is lost,

TCP fast retransmit

if sender receives 3 ACKs for same data ("triple duplicate ACKs"), resend unacked segment with smallest seq #

- likely that unacked segment lost, so don't wait for timeout

TCP fast retransmit



fast retransmit after sender receipt of triple duplicate ACK

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

TCP flow control



receiver protocol stack

flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast

TCP flow control

- receiver "advertises" free buffer space by including **`rwnd`** value in TCP header of receiver-to-sender segments
  - **`RcvBuffer`** size set via socket options (typical default is 4096 bytes)
  - many operating systems autoadjust **`RcvBuffer`**
- sender limits amount of unacked ("in-flight") data to receiver's **`rwnd`** value
- guarantees receive buffer will not overflow



receiver-side buffering

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Connection Management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters




```
Socket clientSocket =
  newSocket("hostname","port
   number");
```

```
Socket connectionSocket =
  welcomeSocket.accept();
```

TCP 3-way handshake



TCP 3-way handshake: FSM



TCP: closing a connection

- client, server each close their side of connection
  - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
  - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

TCP: closing a connection



Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Principles of Congestion Control

Congestion:

- informally: "too many sources sending too much data too fast for *network* to handle"
- different from flow control!
- manifestations:
  - lost packets (buffer overflow at routers)
  - long delays (queueing in router buffers)
- a top-10 problem!

Causes/costs of congestion: scenario 1

- two senders, two receivers
- one router, infinite buffers
- output link capacity: R
- no retransmission





- maximum per-connection throughput: R/2



- large delays as arrival rate, λ_{in}, approaches capacity

Causes/costs of congestion: scenario 2

- one router, *finite* buffers
- sender retransmission of timed-out packet
  - application-layer input = application-layer output: $\lambda_{in} = \lambda_{out}$
  - transport-layer input includes *retransmissions* : $\lambda'_{in} \geq \lambda_{in}$



Causes/costs of congestion: scenario 2

idealization: perfect knowledge

- sender sends only when router buffers available





Causes/costs of congestion: scenario 2

Idealization: known loss
packets can be lost, dropped at router due to full buffers

- sender only resends if packet *known* to be lost



Causes/costs of congestion: scenario 2

Idealization: known loss packets can be lost, dropped at router due to full buffers

- sender only resends if packet *known* to be lost





Causes/costs of congestion: scenario 2

Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending *two* copies, both of which are delivered





Causes/costs of congestion: scenario 2

Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending *two* copies, both of which are delivered



"costs" of congestion:

- more work (retransmission) for given "goodput"
- unneeded retransmissions: link carries multiple copies of packet
  - decreasing goodput

Causes/costs of congestion: scenario 3

- four senders
- multihop paths
- timeout/retransmit

Q: what happens as λ_{in} and λ_{in}' increase ?

A: as red λ_{in}' increases, all arriving blue pkts at upper queue are dropped, blue throughput → 0



Causes/costs of congestion: scenario 3





another "cost" of congestion:

- when packet dropped, any "upstream transmission capacity used for that packet was wasted!

Approaches towards congestion control

two broad approaches towards congestion control:

end-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

network-assisted congestion control:

- routers provide feedback to end systems
  - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
  - explicit rate for sender to send at

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

TCP congestion control: additive increase multiplicative decrease

- *approach:* sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
  - *additive increase:* increase **`cwnd`** by 1 MSS every RTT until loss detected
  - *multiplicative decrease:* cut **`cwnd`** in half after loss

AIMD saw tooth behavior: probing for bandwidth



TCP Congestion Control: details



- sender limits transmission:

$$\texttt{LastByteSent-}\ \texttt{LastByteAcked} \leq \texttt{cwnd}$$

- **cwnd** is dynamic, function of perceived network congestion

TCP sending rate:

- *roughly:* send cwnd bytes, wait RTT for ACKS, then send more bytes

$$\text{rate} \approx \frac{\text{cwnd}}{\text{RTT}} \text{ bytes/sec}$$

TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
  - initially **cwnd** = 1 MSS
  - double **cwnd** every RTT
  - done by incrementing **cwnd** for every ACK received
- *summary:* initial rate is slow but ramps up exponentially fast



TCP: detecting, reacting to loss

- loss indicated by timeout:
  - **`cwnd`** set to 1 MSS;
  - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
  - duplicate ACKs indicate network capable of delivering some segments
  - **`cwnd`** is cut in half window then grows linearly
- TCP Tahoe always sets **`cwnd`** to 1 (timeout or 3 duplicate acks)

TCP: switching from slow start to CA

Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.

Implementation:

- variable **ssthresh**
- on loss event, **ssthresh** is set to 1/2 of **cwnd** just before loss event



Summary: TCP Congestion Control



Chapter 3: Summary

- principles behind transport layer services:
  - multiplexing, demultiplexing
  - reliable data transfer
  - flow control
  - congestion control
- instantiation and implementation in the Internet
  - UDP
  - TCP

Next:

- leaving the network "edge" (application, transport layers)
- into the network "core"